

Memory Management - Paging

Dr Rahul NagpalComputer Science



Memory Management - Paging

Dr. Rahul NagpalComputer Science

Paging

- Physical address space of a process can be noncontiguous; process is allocated physical memory whenever the latter is available
 - Avoids external fragmentation
 - Avoids problem of varying sized memory chunks
- Divide physical memory into fixed-sized blocks called frames
 - Size is power of 2, between 512 bytes and 16 Mbytes
- Divide logical memory into blocks of same size called pages
- Keep track of all free frames
- To run a program of size N pages, need to find N free frames and load program
- Set up a page table to translate logical to physical addresses
- Backing store likewise split into pages
- Still have Internal fragmentation



Address Translation Scheme


- Address generated by CPU is divided into:
 - Page number (p) used as an index into a page table which contains base address of each page in physical memory
 - Page offset (d) combined with base address to define the physical memory address that is sent to the memory unit

page number	page offset
р	d
m -n	n

• For given logical address space 2^m and page size 2ⁿ




Paging Hardware






Paging Model of Logical and Physical Memory





Paging Example



n=2 and m=4 4-byte pages




Paging (Contd.)

- Calculating internal fragmentation
 - Page size = 2,048 bytes
 - Process size = 72,766 bytes
 - 35 pages + 1,086 bytes
 - Internal fragmentation of 2,048 1,086 = 962 bytes
 - Worst case fragmentation = 1 frame 1 byte
 - On average fragmentation = 1 / 2 frame size
 - So small frame sizes desirable?
 - But each page table entry takes memory to track
 - Page sizes growing over time
 - Solaris supports two page sizes 8 KB and 4 MB
- Process view and physical memory now very different
- By implementation process can only access its own memory




Free Frames





Implementation of Page Table



- Page-table base register (PTBR) points to the page table
- Page-table length register (PTLR) indicates size of the page table
- In this scheme every data/instruction access requires two memory accesses
 - One for the page table and one for the data / instruction
- The two memory access problem can be solved by the use of a special fast-lookup hardware cache called associative memory or translation look-aside buffers (TLBs)



Implementation of Page Table (contd.)

- Some TLBs store address-space identifiers (ASIDs) in each TLB entry – uniquely identifies each process to provide address-space protection for that process
 - Otherwise need to flush at every context switch
- TLBs typically small (64 to 1,024 entries)
- On a TLB miss, value is loaded into the TLB for faster access next time
 - Replacement policies must be considered
 - Some entries can be wired down for permanent fast access



Associative Memory




Associative memory – parallel search

Page #	Frame #

- Address translation (p, d)
 - If p is in associative register, get frame # out
 - Otherwise get frame # from page table in memory

Paging Hardware with TLB





Effective Access Time

- Associative Lookup = ε time unit
 - Can be < 10% of memory access time
- Hit ratio = α
 - Hit ratio percentage of times that a page number is found in the associative registers; ratio related to number of associative registers
- Consider α = 80%, ϵ = 20ns for TLB search, 100ns for memory access
- Effective Access Time (EAT)

EAT =
$$(1 + \varepsilon) \alpha + (2 + \varepsilon)(1 - \alpha)$$

= $2 + \varepsilon - \alpha$

- Consider α = 80%, ϵ = 20ns for TLB search, 100ns for memory access
 - EAT = $0.80 \times 100 + 0.20 \times 200 = 120 \text{ns}$
- Consider more realistic hit ratio -> α = 99%, ϵ = 20ns for TLB search, 100ns for memory access
 - EAT = $0.99 \times 100 + 0.01 \times 200 = 101 \text{ns}$




Memory Protection

- Memory protection implemented by associating protection bit with each frame to indicate if read-only or read-write access is allowed
 - Can also add more bits to indicate page execute-only, and so on
- Valid-invalid bit attached to each entry in the page table:
 - "valid" indicates that the associated page is in the process' logical address space, and is thus a legal page
 - "invalid" indicates that the page is not in the process' logical address space
 - Or use page-table length register (PTLR)
- Any violations result in a trap to the kernel



Valid (v) and Invalid (i) bit in Page Table





Shared Pages

Shared code


- One copy of read-only (reentrant) code shared among processes (i.e., text editors, compilers, window systems)
- Similar to multiple threads sharing the same process space
- Also useful for interprocess communication if sharing of read-write pages is allowed

Private code and data

- Each process keeps a separate copy of the code and data
- The pages for the private code and data can appear anywhere in the logical address space



Shared Pages Example







THANK YOU

Dr Rahul Nagpal

Computer Science

rahulnagpal@pes.edu