Strong-field quantum phonodynamics

Matt Lilley

March 7, 2025

1 Introduction

I had a chat with my friend Chris Ridgers about his work on laser plasma interactions in a regime described as "Strong-field QED". The laser field is so intense that perturbation theory no longer works. Chris remarked on how part of the work involved using the "low" energy laser photons to cause an electron to emit a photon with many orders or magnitude more energy. Superficially this sounded similar to the phonon-nuclear system in which we use a low energy phonon to mediate a nuclear energy transition. We also have a highly excited phonon field that makes the system non-perturbative. Chris described various mathematical tools used in his work and I wondered whether we might be able to use some of them in our work.

In this document, I'll try and describe a regime that we might call "Strong-field quantum phonodynamics" or "Strong-field QPD" and compare/contrast it with what people sometimes refer to as "Deep strong coupling".

Unlike "Strong-field QED" that has as well defined parameter range given in terms of the "normalised vector potential" $a_0 \equiv eE/m_e\omega c \gg 1$, for "Strong field QPD" I've not yet come up with a single parameter. Let's see whether one comes out of the analysis in this document.

2 Dicke model

For more detail on the Dicke model, see the notes I made on the subject.

2.1 Describing the states

The Dicke model describes a system where we have N identical TLS coupled to a single mode (i.e. single frequency/wavelength) of a quantised field. The Dicke Hamiltonians can be written as:

$$H = \Delta E J_z + \hbar \omega \left(a^{\dagger} a + \frac{1}{2} \right) + 2U \left(a^{\dagger} + a \right) \left(J_+ + J_- \right) \tag{1}$$

where ΔE is the transition energy between the 2 levels of the TLS, $\hbar \omega$ is the energy of each quantum of the field, and U is the coupling constant between the TLS and the field. The a^{\dagger} , a are the field creation and annihilation operators respectively and the J operators are total pseudo angular momentum operators:

$$J_{+} + J_{-} = J_{x} = \frac{1}{2} \sum_{i=1}^{N} \sigma_{ix} \quad J_{z} = \frac{1}{2} \sum_{i=1}^{N} \sigma_{iz}$$
 (2)

Here σ are the Pauli spin matrices the i in σ_i means that this operator only acts on TLS number i.

When written in this way, states are described in terms of 3 numbers $|n, j, m\rangle$ where n describes the number of field quanta, j describes the total pseudo angular momentum number (which is conserved) and m describes the z component of the total pseudo angular momentum (which can change). This notation allows us to conveniently describe situations where excitations are "delocalised" among the TLS. By far the most significant kind of delocalised states are called "Dicke states" which have the largest $j=j_{\rm max}=N/2$. These states are capable of accelerated emission rates due to superradiance. Dicke starts are symmetric in the sense that if you swap any of the TLS around, the state remains unchanged. For example, consider a single excitation in 4 TLS - the Dicke state written in $|n, \pm, \pm, \pm, \pm\rangle$ notation looks like:

$$\Psi = \frac{1}{\sqrt{4}} \left(|n, +, -, -, -\rangle + |n, -, +, -, -\rangle + |n, -, -, +, -\rangle + |n, -, -, -, +\rangle \right) \tag{3}$$

Notice that if you swap any two TLS, the state looks the same.

The above state can instead be described by $j_{\text{max}} = 4/2 = 2$ and $m = 1 \times 1/2 + 3 \times -1/2 = -1$

$$\Psi = |n, 2, -1\rangle \tag{4}$$

2.2 Coupling strength

The strength of the interaction between the TLS and the field is not only determined by the constant U but also how many field quanta n we have. This is because of how the field operators work:

$$a^{\dagger}|n,j,m\rangle = \sqrt{n+1}|n+1,j,m\rangle$$
 (5)

$$a|n, j, m\rangle = \sqrt{n}|n-1, j, m\rangle$$
 (6)

$$a^{\dagger}a|n,j,m\rangle = n|n,j,m\rangle \tag{7}$$

The more field quanta we have (the stronger the field), the larger the coupling terms will be compared to the TLS term which remains unchanged.

The coupling is also affected by the number of TLS we have. This is because of how the the <u>ladder operators</u> J_{+} and J_{-} create and destroy excitations of the TLS. This causes a raising and lowering of the m value like this:

$$J_{+}|n,j,m\rangle = \sqrt{j(j+1) - m(m+1)}|n,j,m+1\rangle$$
 (8)

$$J_{-}|n,j,m\rangle = \sqrt{j(j+1) - m(m-1)}|n,j,m-1\rangle$$
 (9)

These ladder operators are conceptually similar to the creation and annihilation operators of the field (see Eqs. 5 and 6). The details are however more complicated due to the addition rules of angular momentum. Despite the complexity, we know that the maximum total angular momentum $j_{\text{max}} = N/2$ (from N TLS with pseudo angular momentum 1/2). We can therefore see that the number of TLS is going to have an effect on the coupling between TLS and field. The effect scales like at least \sqrt{N} and at most N (see Dicke model notes for more detail).

The coupling term in Eq. 1 therefore conservatively scales like $U\sqrt{N}\sqrt{n}$ and optimistically as $UN\sqrt{n}$.

3 Deep strong coupling

In the notes on <u>Deep strong coupling</u>, we described a regime in which all the terms in the Hamiltonian in Eq. 1 were of the same order. In other words:

$$\Delta E \sim n\hbar\omega \sim U\sqrt{N}\sqrt{n} \tag{10}$$

where we have taken the conservative Dicke scaling of \sqrt{N} . This regime is characterised by a superradiant phase transition.

For a given $\Delta E, \hbar \omega$, Eq. 10 fixes the strength of the field n and the number of TLS N. For nuclear transitions mediated by phonons via a relativistic phonon nuclear coupling, we found that we could **not** satisfy Eq. 10.

Mathematically, the reason Eq. 10 is hard to satisfy is because $n\hbar\omega \sim U\sqrt{N}\sqrt{n}$ limits how large n can be because n grows faster than \sqrt{n} .

What happens if we look for a regime in which n is not constrained?

4 Strong field

Let's imagine that the field is so strong, i.e. n is so large, that the following is satisfied:

$$\Delta E \lesssim U\sqrt{N}\sqrt{n} \ll n\hbar\omega \tag{11}$$

In this regime, the field retains its "identity" but the TLS gets significantly altered by the field and the coupling.

Eq. 11 can in principle be satisfied for any type of coupling by just increasing the field strength. In practice, there will be physical limits on how strong a field can be. Let's try and work through an example using relativistic phonon nuclear coupling to mediate a nuclear transition with phonons.

From notes on <u>Coupling constants in nuclear physics</u>, we derived the relativistic phonon nuclear coupling as:

$$\frac{U}{\hbar\omega_A} = \sqrt{\frac{2}{N}} \sqrt{\frac{\Delta E}{Mc^2}} \sqrt{\frac{\Delta E}{\hbar\omega_A}} \times 10^{-3}$$
 (12)

where N is the number of nuclei involved in the phonon motion, and M is the mass of the nucleus and ω_A is the acoustic phonon mode frequency. The first condition in Eq. 11 gives:

$$\Delta E \lesssim U\sqrt{N}\sqrt{n}$$

$$\frac{\Delta E}{\hbar\omega_A} \lesssim \sqrt{2}\sqrt{\frac{\Delta E}{Mc^2}}\sqrt{\frac{\Delta E}{\hbar\omega_A}} \times 10^{-3}\sqrt{n}$$

$$1 \lesssim \sqrt{2}\sqrt{\frac{\hbar\omega_A}{Mc^2}} \times 10^{-3}\sqrt{n}$$

$$\frac{1}{2}\frac{Mc^2}{\hbar\omega_A} \times 10^6 \lesssim n$$
(13)

For palladium nuclear transitions mediated by acoustic phonons, $Mc^2 \approx 10^{11}$ eV and $\hbar\omega_A \approx 10^{-8}$ eV . This tells us that the number of phonons must be at least:

$$n \gtrsim 5 \times 10^{24} \tag{14}$$

This seems like a very large number of phonons, so let's sense check the total energy content of the field:

$$5 \times 10^{24} \times 10^{-8} \times 1.6 \times 10^{-19} = 8 \,\mathrm{mJ}$$
 (15)

This does not seem like an outrageous amount of energy.

The second condition in Eq. 11 gives:

$$U\sqrt{N}\sqrt{n} \ll n\hbar\omega_A$$

$$\sqrt{2}\sqrt{\frac{\Delta E}{Mc^2}}\sqrt{\frac{\Delta E}{\hbar\omega_A}} \times 10^{-3}\sqrt{n} \ll n$$

$$2\frac{\Delta E}{Mc^2}\frac{\Delta E}{\hbar\omega_A} \times 10^{-6} \ll n$$
(16)

For a 24 MeV palladium transition mediated by acoustic phonons we have:

$$n \gg 10^6 \tag{17}$$

So, we can describe some different regions of n for this palladium example:

- $n < 10^6$ weak field, the coupling term is greater than the total field energy but is a lot less than the TLS energy.
- $10^6 < n < 5 \times 10^{24}$ intermediate field, the field and the TLS dominate over the coupling.
- $n > 5 \times 10^{24}$ strong field, the field dominates but now the coupling is bigger than the TLS energy

When the field is strong, and the field quanta have a low enough energy such that $U\sqrt{N} > \hbar\omega$ then there can be a free exchange of energy between the field and the TLS because even though an individual low energy energy quanta cannot "hold" all the energy of a TLS transition, the coupling term can. Another way of thinking about this is that incredibly unlikely transitions like the downconversion of nuclear energy into phonon energy or the upconversion of phonon energy to nuclear energy become possible.