# yquant.sty package documentation

Typesetting quantum circuits in a human-readable language

Benjamin Desef

March 15, 2020

This manual introduces yquant, a ETEX-only package that outputs quantum circuits. They are entered using a human-readable language that, even from the source code, allows for a fluent understanding of the logic that underlies the circuit. yquant internally builds on TikZ and can be easily combined with arbitrary ETEX code. More than forty pages of examples complement the formal manual.

# Contents

1	Intro	oduction 4			
	1.1	How to read the manual			
	1.2	Installation			
	1.3	Purpose of yquant, alternatives			
	1.4	License			
2	Basic elements of yquant 7				
	2.1	General usage			
	2.2	Starred vs. unstarred environment			
	2.3	Formal syntax			
	2.4	Registers			
	2.5	Arguments			
	2.6	Controls			
3	Configuration 12				
	3.1	Circuit layout			
	3.2	Register creation			
	3.3	Register outputs			
	3.4	General styling			
	3.5	Styles for operators			
4	Doin	g the impossible 19			
5	Reference: Gates and operations 20				
	5.1	align 20			
	5.2	barrier			
	5.3	box			
	5.4	cbit			
	5.5	cnot			
	5.6	discard			
	5.7	dmeter			
	5.8	h			
	5.9	hspace			
	5.10	init 22			
	5.11	measure			
	5.12	nobit			
	5.13	not			
	5.14	output			

	5.15 phase	24
	5.16 qubit	24
	5.17 qubits	25
	5.18 setwire	25
	5.19 slash	25
	5.20 swap	25
	5.21 x	26
	5.22 xx	26
	5.23 y	26
	5.24 z	26
	5.25 zz	27
6	Examples	28
_	6.1 qasm documentation	2.8
	6.2 qcircuit documentation	
	6.3 quantikz documentation	
	qualities documentation	01
7	Wishlist	7/

### 1 Introduction

This document outlines the scope and usage of the yquant package. It contains both a reference and a huge number of examples. yquant is a package that makes typesetting quantum circuits easy; the package is not yet available on CTAN. This alpha version 0.1 *should* be stable and interfaces are not very likely to change in an incompatible way in the future. Please do report all issues and desirable additions.

### 1.1 How to read the manual

The probably fastest way to start using yquant is by just scanning through the examples in section 6. A more formal description of the yquant grammar and its fundamental concepts can be found in section 2. If your desire is to change the appearance of yquant elements, use the configuration reference in section 3. The full list of all available gates is provided in section 5. Finally, you may find that yquant almost does what you want, but there is some final tweak that you cannot achieve.... Then, have a look at section 4 (or section 1.3).

#### 1.2 Installation

At the moment, clone this repository or download a copy and extract the files to a path visible to your TEX compiler. For example, you may put them in the same directory as your document (if you just want to give a try), or you may extract them to tex/latex/yquant in your local texmf (followed by an update of the file name database).

# 1.3 Purpose of yquant, alternatives

yquant is the acronym for "yet another quantum circuit package." This highlights the fact that nothing that this package provides cannot be achieved by other means. In particular, there are at least the following methods to typeset quantum circuits in TeX.

- Use some external program to draw them and include the output via \includegraphics.
- Use either T<sub>E</sub>X's own drawing capabilities (the picture environment) or other drawing packages such as TikZ or pstricks.
- Use a package specifically designed to draw quantum circuits (if you feel some other package should be mentioned here, please file an issue):

- qasm is probably the first of them (in terms of age). It was developed to typeset the circuits found in Nielsen and Chuang's famous *Quantum Computation and Quantum Information* book. qasm consists of a Python 2 script (qasm2circ) that reads a quantum circuit written in a very intuitive language: declare names for your qubits, perform gates on them in each line. qasm2circ converts those circuits into TEX files that internally make use of the xy package to display the output. Consequently, the user is restricted to the set of features that qasm directly offers (which is small). Changes to the output, while possible, will be overwritten if qasm2circ is run again. qasm output often looks sub-optimal do to the fact that, e.g., rectangles are made up of four lines that do not properly connect and give a crumbly general feeling.

Maintenance status: last update of qasm in 2005. Also, xy was last updated in 2013, and the script is not compatible out-of-the-box with Python 3, though an automatic conversion should work.

- qcircuit is probably the most-widely used package. It provides commands that make it much easier to create quantum circuits using the xy package. Its syntax therefore is grid-oriented; inferring what a circuit does or locating a gate in the code can be tough. This is particularly true for multi-qubit gates. Additionally, the \xymatrix syntax is also somewhat cryptic. qcircuit provides some flexibility within the limits of xy as to configuring the output.

Maintenance status: last update in 2018; and remember this is xy based, with last update in 2013.

- quantikz is a relatively recent package that, following the same grid-based approach as qcircuit, instead builds on TikZ as a backend. As a consequence, it provides the full flexibility of customization that TikZ offers, where hardly anything cannot be done. It also reduces burdens of the xy syntax. However, the disadvantages of the grid-based syntax still remain.

Maintenance status: last update in 2019; the underlying TikZ is actively maintained again by now.

- qpic follows the approach of qasm: It makes use of an external Python program that reads the quantum circuits in an own language and converts them into TikZ commands. The language qpic follows is much more powerful than qasm's. The disadvantage that modifications in the output code will not remain after running the Python script again is mitigated by the possibility to define own TeX macros. Being an external

program, qpic's intrinsic set of features (including, e.g., vertically set circuits) are huge. However, the language qpic uses cannot be understood without a detailed study of the manual, it appears to have been designed with the aim to minimize the length of command names. A disadvantage of external programs is that the amount of space gates need is not accessible by the script; hence, manual intervention may be required.

Maintenance status: last update in 2016; the underlying TikZ is actively maintained, and the script is compatible with Python 3.

### 1.4 License

This work may be distributed and/or modified under the conditions of the MEX Project Public License, either version 1.3 of this license or (at your option) any later version. The latest version of this license is in

http://www.latex-project.org/lppl.txt

and version 1.3 or later is part of all distributions of LaTeX version 2005/12/01 or later.

# 2 Basic elements of yquant

yquant, as some of the aforementioned packages, builds on TikZ. Its basic syntax is similar to pgfplots: Start a tikzpicture environment (perhaps passing some options); inside, start a yquant environment.

Inside the yquant environment, TEX will now understand the yquant language—so yquant falls into the same category as qasm and qpic, providing a human-readable language for the specification of the circuit that is not fixed to the actual layout.

However, yquant is a TeX-only package (actually,  $\text{ETeX} 2_{\varepsilon}$ , but not ETeX 3) that requires no external script to run—so it also falls into the same category as quantikz.

Since it runs entirely within TEX, you can at any time interject yquant code with arbitrary TEX or TikZ code (though if it is "too arbitrary," you may need to restart the yquant interpreter).

### 2.1 General usage

```
% preamble: \usepackage{yquant}
\begin{tikzpicture}% tikz options possible
    % tikz commands go here
   \begin{yquant}% yquant options possible. Watch the newlines!
          % yquant and tikz commands go here
   \end{yquant}
    % tikz commands go here
\end{tikzpicture}
```

Note that yquant depends on etoolbox, TikZ, and trimspaces. Additionally, it requires a moderately recent version of MTeX  $2_{\varepsilon}$ , using either LuaMTeX, or (untested), pdf MTeX or XHMTeX.

### **Optional arguments**

The optional arguments for the yquant environment have to appear on the same line as the environment itself. If you want to put the arguments into a new line, it is crucial to mask the line break by putting a comment symbol after the environment: \begin{yquant}\%. Without this comment, yquant will detect your line break (this is one of the few places in TeX where line breaks and spaces are different) and assume that the expression in square brackets instead provides arguments for the following operation!



#### 2.2 Starred vs. unstarred environment

You may choose to use either the yquant or the yquant\* environment. The former one requires you to define all your registers before you use them (though you may decide to define a register after some operations on *different* registers, but before its first usage).

The starred form additionally supports the use of undeclared registers: it basically declares a registers upon its first usage. This will always be a qubit register; but if you use the corresponding option and the first usage is an init command, you may overwrite this.

Additionally, if you refer to the index i of a vector register of length L < i, this register will automatically be enlarged to i := L. It is also possible to convert a scalar register into a vector register in this manner. However, this only works if the vector register is the last one currently in use; all registers above the last one are "sealed," i.e., they cannot be enlarged any more.

This might be a good point to proceed to the examples section 6.

### 2.3 Formal syntax

Every yquant command has the same structure (described here in EBNF syntax):

```
Command = { Arguments }, ?command?, [ Value ] Register, Controls, ";";
Arguments = "[", ?pgfkeys?, "]";
Value = "{", ?TeX code?, "}";
Register = RegisterSingle | RegisterMulti, [ ",", Register ];
RegisterSingle = RegisterName | RegisterRange;
RegisterMulti = "(", RegisterSingle, ")";
RegisterName = ?name?, [ "[", RegisterIndex, "]" ];
RegisterRange = [ RegisterName ], "-", [ RegisterName ];
Controls = [ "|", [ Register ] ], [ "~", [ Register ] ];
```

Here, we use <code>?pgfkeys</code>? to describe any valid content passed to the <code>\pgfkeys</code> macro (rather, <code>\yquantset</code> is invoked with some subtleties); and by <code>?name</code>? we denote any valid register name. <code>yquant</code> does not pose particular restrictions on register names, but they should not contain any of the control literals used before (semicolon, comma, parentheses, square brackets, dash, pipe, tilde); and you should avoid using special <code>TeX</code> characters. Valid values for <code>?command</code>? (case-insensitive) are documented in a later section.

# 2.4 Registers

Every quantum circuit is structured by means of *registers*. A register has a *type* that specifies how its wire is drawn, and that may even change during its lifetime.

At the moment, yquant supports four types:

- 1. qubit is the most common type, used for a quantum register. It corresponds to a single line.
- 2. cbit is a classical register, which can be either declared from the beginning or arises by using measurements. It corresponds to a double line.
- 3. qubits is a "quantum bundle," i.e., a bunch of quantum registers that are always addressed in a group as a single register. Operations between bundles of the same length should be interpreted as transversal. It corresponds to a triple line. An alternative (and more common) representation is to use the qubit type and a slash gate at its very beginning.
- 4. nobit is the most obscure type, corresponding to a non-existing wire. Mostly, this register type arises by using the discard command. However, it can also be directly declared, which on rare occasions might be necessary (its type can then be changed by means of an init or setwire pseudo-gate). If you want to declare a register only at a certain horizontal position in the circuit, consider using the after argument instead.

Registers must be declared before they can be used (though in the yquant\* environment, this declaration may be implicit, creating a qubit register).

Registers can have a vector character, i.e., not only a *name*, but also an *index* (or, in the declaration, a *length*). The index (zero-based) or length is specified in square brackets following the name, which closely mimics the OpenQASM language.

Registers are referenced—i.e., used in operations—by their name and index. If the latter is omitted, all indices of the register are targeted. Multiple registers can be referenced by joining their names in a comma-separated list, or by means of a range specifier: give the name of the first (topmost), a dash, and the last (bottom-most) register. Both are inclusive. In a range specifier, omitting the start name means that the range begins at the first known qubit; omitting the end name means that the range ends at the last known (at the moment of its use) qubit. Omitting both indicates a range over all known registers.

Note that all those specifications refer to the operation being carried out on each of the registers *individually*, i.e., producing several copies of the operation. This is different from using the operation multiple times on the individual single registers only with regard to the vertical positioning: if specified as a register list with one operation, all copies of the operation will be aligned at the same vertical position (as if an align command had been carried out before). Consequently it

is forbidden (in the sense of "not useful," but yquant does not check for this) to list the same register multiple times in one operation.

Instead of copies of single-register operations, one might want to carry out a multi-register operation. In this case, the desired list of registers (comma separated, range, or both) must be surrounded by parentheses. It is possible to mix single-and multi-register operations arbitrarily. However, note that some gates, such as the swap gate, always require multi-register operations with a fixed number of constituents; others, such as the slash pseudo-gate always require single-register operations. Again others are completely flexible. yquant will prevent you from using a gate in a multi-qubit setting when it may only be used for single registers simply by no longer recognizing the parenthesis—this check comes almost for free. All other types of validity checks are up to the user.

# 2.5 Arguments

Every command may take one or multiple arguments. Those are specified in square brackets that precede the command itself. The content of those square brackets is essentially fed to a \pgfkeys-like macro. The default path is set appropriately such that the arguments of the command can be accessed without and path specifiers. If the key is not a valid argument for the command or a global argument and it is not given by an absolute path, it is searched for in the /yquant namespace. If it cannot be found there, it is passed to /yquant/operator style.

Note that commands may have required arguments. If a required argument is missing, an error will be issued.

The value attribute can alternatively be given inside curly brackets after the command name and before the register specification. This has the advantage that special characters such as a closing square bracket need not be escaped. If both alternatives are present, the value inside curly brackets takes precedence and a warning is issued.

#### 2.6 Controls

Lots of gates may have controls, i.e., they are only to be executed if some other gate is set or unset. The former case is called a *positive control*, the latter one a *negative control*. Those are indicated by filled and empty circles on the control registers and a vertical line that joins the registers that belong together.

The gate specification is followed by the list of target registers. By then writing a pipe ("|"), the list of positive controls is introduced; this mimics the mathematical syntax "conditioned on" for probabilities or "given" for sets. If there are no positive controls, the list may be empty or, together with the pipe, omitted. Preceded by

a tilde ("~"), the list of negative controls then follows; this mimics the syntax of many programming languages that denote logical negation by a tilde. If there are no negative controls, the list may be empty or, together with the pipe, omitted.

# 3 Configuration

yquant uses pgfkeys to control its options, which are located in the path /yquant. The following list contains all options and styles that are recognized, apart from gate arguments. Those are listed together with their operations.

# 3.1 Circuit layout

/yquant/register/minimum height

default: 3mm

yquant automatically determines the total height of a register as the height of the largest operation. This might be too small for two reasons:

- if the register is used only with small gates (e.g., only as a control, or as a swap), and it does not have a label (or one containing only x-height letters).
- if the register is used only with multi-qubit gates. For those, yquant cannot decide where to put the height—and it is easy to see that an equal distribution over all affected registers is not necessarily a good solution. Hence, multiqubit gates are ignored in the height calculation. Usually, this is not a problem since those operations are large enough as they take the height of all involved registers and separations.

This key provides an easy alleviation of the problem by requiring a minimal height for every register.

/yquant/register/separation

default: 1mm

This key controls the amount of vertical space that is inserted between two successive registers.

/yquant/operator/minimum width

default: 3mm

yquant automatically determines the width of an operator according to its content. However, single-letter boxes are among the most common operators, and giving them slightly different widths would result in a very uneven spacing, as yquant does not use a grid layout but stacks the operators horizontally one after each other. Hence, this key provides a minimum width that will be set for every operator. This does not imply that the *visual* appearance (i.e., the x radius key) is enlarged, but that operators of a smaller actual width will be centered in a virtual box of the minimum width.

/yquant/operator/separation

default: 1mm

This key controls the amount of horizontal space that is inserted between two successive operators.

### 3.2 Register creation

#### /yquant/register/default name

The printed name that is used by default if a new register is created explicitly (qubit, cbit, qubits; not used for nobit or for implicit declarations) and no value is specified. The following macros are available:

- \reg contains the internal name that is used to identify this register.
- \idx contains the index (zero-based) of the current register within a vector register.
- \regidx expands to \reg if the register is of length one, and to \reg [\idx] else.
- \len contains the length of the current register vector.

### /yquant/every label

default: shape=yquant-text, anchor=circuit,

align=right

default: \regidx

This style is installed for every single register name label (i.e., upon creation and when used with the init gate). The default style allows to use line breaks in the labels.

### /yquant/every initial label

default: anchor=east

This style is installed for every single register name label at the left border of the circuit. Hence, it is only used for the init gate if in the yquant\* environment, the gate occurs for a new register (which allows to override the default register type).

### /yquant/every qubit label

default:

This style is installed for every single register name label of a register of type qubit.

# /yquant/every cbit label

default:

This style is installed for every single register name label of a register of type cbit.

# /yquant/every qubits label

default:

This style is installed for every single register name label of a register of type qubits.

This style is installed for every register name label that is attached to a multi-qubit register by means of the init gate. yquant additionally inserts a straight line that connects the topmost and the bottom-most register at their left ends. The default style turns this line into a brace and places the description at the appropriate position.

### 3.3 Register outputs

/yquant/every output default: shape=yquant-text, anchor=west, align=left
This style is installed for every output label at the end of the circuit. The default
style allows to use line breaks in the labels.

```
/yquant/every qubit output default:
This style is installed for every output label of a register of type qubit.
```

```
/yquant/every cbit output default:
This style is installed for every output label of a register of type cbit.
```

```
/yquant/every qubits output default:
This style is installed for every output label of a register of type qubits.
```

This style is installed for every output label that is attached to a multi-qubit register. yquant additionally inserts a straight line that connects the topmost and the bottom-most register at their right ends. The default style turns this line into a brace and places the description at the appropriate position.

### 3.4 General styling

/yquant/every circuit

default:

Style that is installed for every yquant and yquant\* environment, as if it had been given as an option. The style's default path is /yquant, in contrast to all other styles that operate in the /tikz path by default.

/yquant/every wire

default: draw

This style is installed whenever a wire is drawn.

/yquant/every qubit wire

default:

This style is installed whenever a wire for a register of type qubit is drawn.

/yquant/every cbit wire

default:

This style is installed whenever a wire for a register of type cbit is drawn.

/yquant/every qubits wire

default:

This style is installed whenever a wire for a register of type qubits is drawn.

/yquant/every control line

default: draw

This style is used to draw the vertical control line that connects controlled operations and their controls.

/yquant/every control

default: shape=yquant-circle, anchor=circuit,

radius=.5mm

This style is used to draw the node for a control, both positive and negative.

/yquant/every positive control

default: fill=black

This style is installed for every positive control (i.e., one that conditions on the register being in state  $|1\rangle$  or 1).

/yquant/every negative control

default: draw

This style is installed for every negative control (i.e., one that conditions on the register being in state  $|0\rangle$  or 0).

/yquant/every operator

default: anchor=circuit

This style is installed for every gate (and also pseudo-gates such as the slash operator) that acts on one or multiple registers.

/yquant/this operator

default:

This style is appended to the current style installed for an operator; it should be used only locally to overwrite any global configuration effect.

/yquant/this control

default:

This style is appended to the current style installed for a control; it should be used only locally to overwrite any global configuration effect.

- /yquant/operator style default:/yquant/this operator/.append style={#1}
  This is a shorthand that can be used to modify the appearance of the current operator.
- /yquant/control style default:/yquant/every control line/.append style={#1}, /yquant/this control/.append style={#1}
  This is a shorthand that can be used to modify the appearance of the current control and its associated line.
- /yquant/style default:/yquant/operator style={#1}, /yquant/control style={#1}

This is a shorthand that modifies the appearance of both the current operator and any controls or control lines.

### 3.5 Styles for operators

- /yquant/operators/every barrier default: shape=yquant-barrier, x radius=\pgflinewidth, dashed, draw This style is installed for every barrier pseudo-gate, i.e., the one that is used to explicitly denote a separation between "before" and "after" within the circuit. The yquant-barrier shape is a vertical line of width x radius.
- /yquant/operators/every box default: shape=yquant-rectangle, draw, align=center, inner xsep=1mm, x radius=2mm, y radius=2.47mm
  This style is installed for every box operator.
- /yquant/operators/every dmeter default: shape=yquant-dmeter, x radius=2mm, y radius=2mm, fill=white, draw
  This style is installed for every dmeter gate. The yquant-dmeter shape consists of a rectangle whose right side is replaced by a circle, resembling the letter "D."
- /yquant/operators/every h default:/yquant/operators/every box This style is installed for every h (Hadamard) operator.

/yquant/operators/every measure

default: shape=yquant-measure, x radius=4mm, y radius=2.5mm, draw

This style is installed for every measure gate. The yquant-measure shape is a rectangle that contains a "meter" symbol. It allows for a text to be put inside (e.g., a basis), which then shifts the meter symbol accordingly.

/yquant/operators/every measure meter

default: draw,

-{Latex[length=2.5pt]}

This style is applied to the path that resembles the "meter" symbol that is drawn by the yquant-measure shape. Due to the default style, the TikZ library arrows.meta is automatically loaded with yquant.

/yquant/operators/every not default: shape=yquant-oplus, radius=1.3mm, draw

This style is installed for every not or cnot gate (which are synonyms, and actually do the same as the Pauli  $\sigma_x$  gate). The yquant-oplus shape resembles the addition-modulo-two symbol  $\oplus$ .

/yquant/operators/every pauli default:/yquant/operators/every box This style is installed for every Pauli operator, i.e., x, y, and z.

/yquant/operators/every phase default: shape=yquant-circle, radius=.5mm, fill

This style is installed for every phase gate  $|0\rangle\langle 0| + e^{i\phi} |1\rangle\langle 1|$ .

/yquant/operators/every slash default: shape=yquant-slash, x radius=.5mm, y radius=.7mm, draw
This style is installed for every slash pseudo-gate, i.e., the one that is used to indicate that a single register line actually denotes multiple registers.

/yquant/operators/every swap default: shape=yquant-swap, x radius=.75mm, draw

This style is installed for every bipartite swap gate that interchanges two qubits. The yquant-swap shape consists of two crosses that are connected by a middle line. The length of the virtual square that contains the crosses is twice the x radius property; the total height (twice y radius) will automatically be set according to the registers involved. Hence, this gate must always act on a two-qubit register.

/yquant/operators/every x default:/yquant/operators/every pauli This style is installed for every Pauli operator  $\sigma_x$ , i.e., x.

/yquant/operators/every xxdefault: shape=yquant-xx, x radius=.75mm, draw This style is installed for every bipartite xx gate in symmetrized notation  $(|++\rangle\langle++|+|+-\rangle\langle+-|+|-+\rangle\langle-+|-|---\rangle\langle--|)$ . The yquant-xx shape consists of two open squares that are connected by a middle line. The length of one side in the square is twice the x radius property; the total height (twice y radius) will automatically be set according to the registers involved. Hence, this gate must always act on a two-qubit register.

/yquant/operators/every y default:/yquant/operators/every pauli This style is installed for every Pauli operator  $\sigma_y$ , i.e., y.

/yquant/operators/every z default:/yquant/operators/every pauli This style is installed for every Pauli operator  $\sigma_z$ , i.e., z.

/yquant/operators/every zz default: shape=yquant-zz, x radius=.5mm, fill, draw

This style is installed for every bipartite zz gate (aka CPhase) in symmetrized notation ( $|00\rangle\langle00|+|01\rangle\langle01|+|10\rangle\langle10|-|11\rangle\langle11|$ ). The yquant-zz shape consists of two circles that are connected by a middle line. The radius of the circles is controlled via the x radius property; the total height (twice y radius) will automatically be set according to the registers involved. Hence, this gate must always act on a two-qubit register.

# 4 Doing the impossible

yquant will almost certainly never be able to do everything an author has in mind. Sometimes, there is the need to draw something non-standard, and this cannot be implemented in the yquant language. However, since yquant is a layer on top of TikZ, it should be very hard to find something (meaningful) that cannot be done by combining the power of both packages.

Before or after any gate, you may interrupt the yquant instructions to perform arbitrary TikZ path operations. After every such operation, yquant will automatically restart its parser so that you can fluently jump between yquant and TikZ code. You can even interject arbitrary TeX code (or, say, low-level pgf commands); however, then, yquant is not able to restart its parser. For this reason, after the last command in a block of TeX commands, you must issue \yquant, which then re-enables the yquant language.

The feature to perform arbitrary TikZ operations is powerful in itself, but would be of limited use were there no way to access the elements in the quantum circuit. yquant provides a global attribute name that can be assigned to every gate. All quantum operations are in fact TikZ nodes, and the name you give to them then becomes a TikZ name, which you can easily reference to get the coordinates of a particular operator. Note that the name you specify is only available if a single register is targeted. The name is suffixed by -\idx, where \idx refers to the (zero-based) index of the operation ordered from top to bottom (i.e., if an operator acts on two qubits and should be named op, the topmost operator will be available as op-0 and the second as op-1). All controls are also named, suffixed by -p\idx or -n\idx for positive and negative controls (i.e., the topmost positive control of the previous operator will be available as op-p0). Counters for target registers, positive, and negative controls are all independent.

All yquant shapes have the anchors available you would typically expect from a TikZ shape of the given outline. Additionally, yquant shapes will have an anchor circuit; and apart from border anchors, they also implement projection anchors. As with the former, you will need low-level macros to access these anchors, which are \pgfpointshapexproj and \pgfpointshapeyproj. They will expect the name of the node as first argument and a pgf point as second argument. This point will be projected onto the shape in horizontal or vertical direction. These special types of anchors are internally used to determine where the intersection of wire and shape is located.

# 5 Reference: Gates and operations

This section lists all operations yquant currently understands. It also details all arguments that can be given to customize the operation, apart from name, which is always available. Note that the [value=<value>] attribute can (and should) alternatively be given as a braced expression that follows the name of the register.

#### 5.1 align

Syntax: align <target>;

This is an invisible pseudo-gate that enforces all affected registers to share a common horizontal position for their next gate, which is determined by the largest position of all gates involved. It may not span multiple registers and does not allow for controls.

Possible attributes: none

#### 5.2 barrier

Syntax: barrier <target>;

This is a pseudo-gate that denotes some physical barrier that ensures execution with a specific timing; it is basically a visible version of the align gate, denoted by a vertical line. It may span multiple registers, but does not allow for controls. The style /yquant/operators/every barrier is installed.

Possible attributes: none

### 5.3 box

Syntax: box <target> | <pcontrol> ~ <ncontrol>;

This is a generic register of a rectangular shape that can be filled with arbitrary content. It may span multiple registers and allows for controls. The style /yquant/operators/every box is installed.

Possible attributes:

[value=<value>]
 Denotes the content of the box.

# **5.4** cbit

```
Syntax: cbit <name>[<len>];
Declares a register of type cbit.
see qubit
```

#### 5.5 cnot

This is a synonym for the not gate. Note that despite its name, controls are not mandatory and also here, the style /yquant/operators/every not is installed.

# 5.6 discard

Syntax: discard <target>;

This is an invisible pseudo-gate that changes the type of all target registers to nobit, i.e., no line will be drawn for them. This has effect already for the outgoing line of the last visible gate on the target registers. The gate may not span multiple registers and does not allow for controls. To change into a register type on-the-fly into something different from nobit, use the setwire pseudo-gate.

Possible attributes: none

#### 5.7 dmeter

Syntax: dmeter <target>;

This is a measurement gate, denoted by a "D" shape. It changes the type of all targets involved. It may span multiple registers, but does not allow for controls. The style /yquant/operators/every dmeter is installed.

Possible attributes:

- [value=<value>]
  Allows to specify a text that will be included inside the gate, possible enlarging its width. For outside texts, use TikZ labels instead.
- [type=<qubit|cbit|qubits>]
  Allows to specify the type into which the affected targets are converted.

  Default is cbit.

#### 5.8 h

Syntax: h <target> | <pcontrol> ~ <ncontrol>; This is a Hadamard gate,  $\frac{1}{\sqrt{2}}(|0\rangle\langle 0|+|0\rangle\langle 1|+|1\rangle\langle 0|-|1\rangle\langle 1|)$ , denoted by a rectangle that contains the letter H. It may not span multiple registers, but allows for controls. The style /yquant/operators/every h is installed.

Possible attributes: none

### 5.9 hspace

Syntax: hspace <target>;

This is an invisible pseudo-gate that inserts a certain amount of white space into all target registers. It may not span multiple registers and does not allow for controls. *Possible attributes*:

[value=<dim>] (required)
 Gives the amount of white space that is to be inserted. Must be a valid TeX dimension.

#### 5.10 init

Syntax: init <target>;

This is a pseudo-gate that (re)initializes a registers to a given state. It may span multiple registers, but does not allow for controls. The style /yquant/every label is installed. Note that this pseudo-gate, unlike all others, behaves differently if it the first operation acting on a register: in this case, it does not increment the horizontal position, but uses the space available to the left. If it is the first operation, the style /yquant/every initial label is installed additionally. For multiple registers, the style /yquant/every multi label is installed at the end, and a path is constructed that extends from the left end of the first to the left end of the last register in the multi-register compound.

Possible attributes:

- [type=<qubit|cbit|qubits>]
  Allows to specify the type into which the affected target registers are converted. Default is the type of the first target register that is different from nobit, or qubit if they all are nobit. The style /yquant/every <type> label is installed additionally.
- [value=<value>] (required)
   Denotes the label that is printed to the left of the wire.
   Inside the value, \idx expands to the current index within the register list.

#### 5.11 measure

Syntax: measure <target>;

This is a measurement gate, denoted by a rectangle with a meter symbol. It changes the type of all targets involved. It may span multiple registers, but does not allow for controls. The style /yquant/operators/every measure is installed.

Possible attributes:

- [type=<qubit|cbit|qubits>]
  Allows to specify the type into which the affected targets are converted.
  Default is cbit.
- [value=<value>]
  Allows to specify a text that will be included at the bottom of the rectangle (which will shift the meter symbol upwards accordingly). For outside texts, use TikZ labels instead.

#### 5.12 nobit

Syntax: nobit <name>[<len>];

Declares a register of type nobit. The <name> must be a self-chosen name for the register which was not previously used as a register name in this yquant environment. Names are case-insensitive. The register can be made into a vector register by specifying <len> (default 1).

Possible attributes: none

#### 5.13 not

Syntax: not <target> | <pcontrol> ~ <ncontrol>;

This is a NOT gate,  $|0\rangle\langle 1|+|1\rangle\langle 0|$ , denoted by the  $\oplus$  symbol. It may not span multiple registers, but allows for controls. Due to its common usage, the synonymous gate cnot is provided. The style /yquant/operators/every not is installed.

Possible attributes: none

### 5.14 output

Syntax: output <target>;

This is a pseudo-gate that allows to write some text at the very end of the register line. It may only be specified once per register. It may span multiple registers, but does not allow for controls. The style /yquant/every output is installed, and also the style /yquant/every <type> output, where <type> is the type of the

affected register (at the time of printout). For outputs on multiple registers, the style /yquant/every multi output is installed instead of the two previously mentioned ones; and additionally, a path is constructed that extends from the first to the last register in the multi-register compound.

Possible attributes:

• [value=<value>] (required)

Denotes the text that is to be printed. Inside the value, \idx expands to the current index within the register list.

# **5.15** phase

Syntax: phase <name> | <pcontrol> ~ <ncontrol>; This is a phase gate,  $|0\rangle\langle 0| + \mathrm{e}^{\mathrm{i}\phi}\,|1\rangle\langle 1|$ , denoted by a filled circle. It may not span multiple registers, but allows for controls (and should have them, to make any sense). The style /yquant/operators/every phase is installed.

Possible attributes:

• [value=<value>] (required) Denotes the angle  $\phi$  that is to be printed together with the gate. Position and appearance can be influenced by setting the position of TikZ labels, as this is internally used. Note that at the moment, it is not possible to change any label options on a gate-type basis, only locally or fully globally (TikZ feature request #811).

### **5.16** qubit

Syntax: qubit <name>[<len>];

Declares a register of type qubit. The <name> must be a self-chosen name for the register which was not previously used as a register name in this yquant environment. Names are case-insensitive. The register can be made into a vector register by specifying <len> (default 1).

Possible attributes:

- [after=<regname>]
  If given, the register will start not at the left of the circuit but instead at the position at which the last gate in the register <regname> ended.
- [value=<value>]
  Denotes the label that is printed to the left of the wire. If the value is omitted, the default is used (/yquant/register/default name, preinitialized to \regidx).

Inside the value, \reg expands to <name>, \len expands to <len>, \idx expands to the current index within the vector register  $(0 \le \text{idx} < \text{len})$ , and \regidx expands to \reg if <len> is one, or to \reg[\idx] else.

### 5.17 qubits

```
Syntax: qubits <name>[<len>];
Declares a register of type qubits.
   see qubit
```

#### 5.18 setwire

Syntax: setwire <target>;

This is an invisible pseudo-gate that immediately changes the type of the targets registers, taking effect with the output line extending from the last drawn gate. It may not span multiple registers and does not allow for controls.

Possible attributes:

• [value=<qubit|cbit|qubits>] (required)

Denotes the new type that is assigned to all registers. To change the type to nobit, use the discard pseudo-gate instead.

#### 5.19 slash

Syntax: slash <target>;

This is a pseudo-gate used to denote that a single line actually represents multiple registers. It is drawn as a short slash through the line of the register. Note that this gate, in contrast to all others, is positioned on the line extending from the last gate or the initialization line of the registers and does not advance the register's horizontal position. The style /yquant/operators/every slash is installed.

Possible attributes: none

#### 5.20 swap

Syntax: swap <targets> | <pcontrol> ~ <ncontrol>;

This is the two-qubit swap gate  $|00\rangle\langle00| + |01\rangle\langle10| + |10\rangle\langle01| + |11\rangle\langle11|$  that exchanges two qubits. It is denoted by crosses at the affected registers which are connected by a control line. It may span multiple registers (in fact, it should always span exactly two registers, though yquant does not enforce this), and it allows for controls. However, refrain from combining *multiple* two-qubit targets *together* with controls. The control line will extend from the first to the last of

all registers involved in the operation, so that it is impossible to discern visually which registers should actually be swapped. Using multiple swaps without controls in one operation is fine, as well as a single controlled swap. The style /yquant/operators/every swap is installed.

Possible attributes: none

#### 5.21 x

Syntax: x <target> | <pcontrol> ~ <ncontrol>;

This is a Pauli  $\sigma_x$  gate  $|0\rangle\langle 1|+|1\rangle\langle 0|$ , denoted by a rectangle that contains the letter X. It may not span multiple registers, but allows for controls.

The style /yquant/operators/every x is installed.

Possible attributes: none

#### 5.22 xx

Syntax: xx <targets>;

This is a two-qubit symmetric flip gate, denoted by two joined open squares. It may span multiple registers (in fact, it should always span exactly two registers, though yquant does not enforce this), and it allows for controls. However, refrain from combining *multiple* two-qubit targets *together* with controls. The control line will extend from the first to the last of all registers involved in the operation, so that it is impossible to discern visually which registers form the two-qubit compounds. Using multiple gates without controls in one operation is fine, as well as a single controlled gate. The style /yquant/operators/every xx is installed.

Possible attributes: none

### 5.23 y

Syntax: y <target> | <pcontrol> ~ <ncontrol>;

This is a Pauli  $\sigma_y$  gate  $-i |0\rangle\langle 1| + i |1\rangle\langle 0|$ , denoted by a rectangle that contains the letter Y. It may not span multiple registers, but allows for controls.

The style /yquant/operators/every y is installed.

Possible attributes: none

#### 5.24 z

Syntax: z <target> | <pcontrol> ~ <ncontrol>; This is a Pauli  $\sigma_z$  gate  $|0\rangle\langle 0| - |1\rangle\langle 1|$ , denoted by a rectangle that contains the

letter Z. It may not span multiple registers, but allows for controls.

The style /yquant/operators/every z is installed.

Possible attributes: none

### 5.25 zz

Syntax: zz <targets>;

This is a two-qubit symmetric phase gate  $\mathbb{1}-2|11\rangle\langle 11|$ , denoted by two joined filled circles. It may span multiple registers (in fact, it should always span exactly two registers, though yquant does not enforce this), but does not allow for controls. The style /yquant/operators/every zz is installed.

Possible attributes: none

# 6 Examples

This section will contain lots of examples. On the left-hand side, the output is given, while the code to construct the example is on the right. All examples that are provided originate from the examples supplied with qasm, qcircuit, and quantikz. We will essentially follow their manuals example-by-example, which gives a nice comparison in how to achieve the given feature using these packages and yquant instead. All examples of course require inclusion of the yquant package in the preamble, and some also require braket.

# 6.1 qasm documentation

The qasm documentation most often names the registers in the way  $|register_{index}\rangle$ . This can be achieved by writing

```
qubit {$\ket{<name>_{\idx}}$} <name>[<len>];
```


but if you want to realize this naming scheme for all circuits in your document, it is more convenient to say

```
\yquantset{register/default name=$\ket{\reg_{\idx}}$}
```

in the preamble, as is done here.


```
test1 (create an EPR pair)  |q_0\rangle \cdot H  \lambda begin{tikzpicture} \\ \lambda begin{yquant} \\ qubit q[2]; \\ \\ h q[0]; \\ cnot q[1] | q[0]; \\ \end{tikzpicture} \\ \end{tikzpicture} \end{tikzpicture}
```








```
test3 (swap circuit) \begin{tikzpicture}
```




```
begin{yquant}
    qubit q[2];

    cnot q[1] | q[0];
    cnot q[0] | q[1];
    cnot q[1] | q[0];
    lend{yquant}
\end{tikzpicture}
```










# test6 (demonstrate multiple-qubit controlled single-q-gates)





# test7 (measurement of operator with correction)



```
|q_0
angle \ H H Q_0 V
```

```
\begin{tikzpicture}
  \begin{yquant}
    qubit q[2];

    h q[0];
    box {$U$} q[1] | q[0];
    h q[0];
    measure q[0];
    box {$V$} q[1] | q[0];
  \end{yquant}
\end{tikzpicture}
```

# test8 (stage in simplification of quantum teleportation)



```
\begin{yquant}
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   qubit { \{ \{ \{ q_{\{ idx \} \} \} = \} \} } }
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             \  \, \hookrightarrow \  \, \texttt{\  \, \  \, } \texttt{\  \, } \texttt{

    \else \ket0 \fi$} q[3];

|q_0\rangle = |\psi\rangle - - -
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 h q[1];
    |q_1\rangle = |0\rangle \cdot H
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   cnot q[1] | q[0];
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   cnot q[2] | q[1];
      |q_2\rangle = |0\rangle ——
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   cnot q[1] | q[0];
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 h q[0];
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 cnot q[2] | q[1];
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   z q[0] | q[2];
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           \end{yquant}
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              \end{tikzpicture}
```

\begin{tikzpicture}

Note that we left out two Hadamards at the end.

Other alternatives to the declaration would be to use three different registers that can be assigned a text individually.


# test9 (two-qubit gate circuit implementation of Toffoli)



```
|q_0\rangle = |q_0\rangle = |q_1\rangle = |q_2\rangle - \sqrt{X} = |q_2\rangle - |
```

# test10 (multi-qubit gates also demonstrates use of classical bits)





```
begin{tikzpicture}
    \begin{yquant}
      qubit {$\ket{q_0}$} q0;
      cbit {$c_1$} c1;
      qubit {$\ket{q_2}$} q2;

    h q0;
    box {$U$} (q0, c1);
    box {$S$} q2;
    box {$U$} (c1, q2);
    \end{yquant}
\end{tikzpicture}
```

Observe that here we chose the simplest solution and used three scalar registers, as the classical one is in between the quantum ones.

# test11 (user-defined multi-qubit ops)




```
\begin{array}{c|c} |q_0\rangle & \hline \\ |q_1\rangle & \hline \\ |q_2\rangle & \hline \end{array} \hspace{-1cm} U_{f(x)} \\ \hline H \\ U_{f(x,y)} \\ \hline \end{array}
```

Here we used the fact that a vector register can also be addressed as a whole. Instead of (q), we could have also written, e.g., (q[0]-q[2]) or enumerated all sub-registers in a comma-separated list.

# test12 (multi-qubit controlled multi-qubit operations)





```
\begin{tikzpicture}
  \begin{yquant}
    qubit q[3];


    h q[0];
    box {$U$} (q[1]-q[2]) | q[0];
    h q[0];
    box {$V$} (q[0]-q[1]) | q[2];
  \end{yquant}
\end{tikzpicture}
```

# test13 (three-qubit phase estimation circuit with QFT and controlled-U)



```
|j_{0}\rangle = |0\rangle \cdot H \quad H \quad |
|j_{1}\rangle = |0\rangle \cdot H \quad |
|j_{2}\rangle = |0\rangle \cdot H \quad |
|s_{0}\rangle \quad |
|s_{1}\rangle \quad |
|U^{4} \quad U^{2} \quad U \quad |
```

```
\begin{tikzpicture}
   \verb|\begin{yquant}|
      qubit {\frac{j_{\star j_{\star}}} = \text{ket0}} j[3];
      qubit s[2];
      h j;
      box {$U^4$} (s) | j[0];
      box {$U^2$} (s) | j[1];
      box {$U$} (s) | j[2];
      h j[0];
      box {$S$} j[1] | j[0];
      h j[1];
      box {$T$} j[2] | j[0];
      box {$S$} j[2] | j[1];
      h j[2];
      measure j;
   \end{yquant}
\end{tikzpicture}
```





# test15 ("D-type" measurement)



```
\begin{aligned} |q_0\rangle &= |\psi\rangle & - HZ_\theta \\ |q_1\rangle &= |+\rangle & - HZ_\theta \end{aligned}
```

### test16 (example from Nielsen paper on cluster states)



```
\begin{aligned} |q_0\rangle &= |\psi\rangle & \longrightarrow \\ |q_1\rangle &= |\psi\rangle & \longrightarrow \\ |q_2\rangle &= |\phi\rangle & \longrightarrow \\ |q_3\rangle &= |0\rangle & \longrightarrow \end{aligned}
```

We needed to include an align pseudo-gate to put the slash at the desired position. Usually, this would be sufficient to put the cnot and the slash gate directly under each other, as it is in the qasm example. However, the slash gate is special in that it does not need horizontal space and is put with only half of the usual operator separation into the circuit (for this reason, it can be put at the beginning of a wire without creating weird shifts with respect to the "unslashed" registers—it is put in the initial line that every wire even without an operation has). Hence, you should normally only use the slash gate as the very first gate in a circuit. It is not possible to construct the exact same appearance as in the qasm example. Note that discard currently just drops the wire directly after the last operation.

# test17 (example from Nielsen paper on cluster states)



```
\begin{aligned} |q_0\rangle &= |\psi\rangle \\ |q_1\rangle &= |+\rangle \end{aligned} \qquad H = \\ |q_2\rangle &= |+\rangle \qquad H = \\ |q_3\rangle &= |\phi\rangle \end{aligned}
```

# test18 (multiple-control bullet op)




```
\begin{aligned} |q_0\rangle &= |\psi\rangle \\ |q_1\rangle &= |+\rangle \\ |q_2\rangle &= |+\rangle \\ |q_3\rangle &= |\phi\rangle \end{aligned}
```

This non-standard gate is something that would have to be defined in an accompanying text; probably it is a generalization of zz,  $\mathbb{1}-2|1\cdots 1\rangle\langle 1\cdots 1|$ . We implemented it by carrying out a phase gate (which has a mandatory value attribute, which we left empty) and conditioned it on the rest.

### 6.2 qcircuit documentation

For a better orientation, we use the same section headings as the qcircuit manual. The manual uses unnamed registers a lot; often, we will use the yquant\* environment to make things more concise. As qcircuit uses a much large separation between the operators than yquant's default, we globally say \yquantset{operator/separation=3mm}.

#### 6.2.1 I. Introduction





Here, we chose to realize the equality using two tikzpictures with appropriately set baselines.

If mangling with the baselines becomes problematic, a different approach would be to use an outer tikzpicture with three nodes (left circuit, equals, right circuit); but the circuits themselves are tikzpictures again, and nesting those is dangerous (but may work). Instead they could have been put into \saveboxes and just used.

Finally, using nested tikzpictures for the outer nodes is not really necessary. Not using nodes but putting the two yquant\* environments in a TikZ scope with shift transformation would have also worked.









```
% \usetikzlibrary{fit, quotes}
\begin{tikzpicture}
  \begin{yquant}
     qubit {} msg[3];
      [name=inits]
     qubit {$\ket0$} syndrome[3];
     [name=scnot0]
     cnot syndrome[0] | msg[0];
     cnot syndrome[0] | msg[1];
     cnot syndrome[1] | msg[1];
     cnot syndrome[1] | msg[2];
     cnot syndrome[2] | msg[0];
     cnot syndrome[2] | msg[2];
     [name=smeas]
     dmeter {$M_{\symbol{\numexpr`a+\idx}}$} syndrome;
     ["Recovery"]
     box {$\symcal R$} (msg) | syndrome;
     discard syndrome;
   \end{yquant}
  \node[draw, dashed, fit=(inits-2) (scnot0-p0) (smeas-2), "Syndrome
   \end{tikzpicture}
```

In this case, an implicit register declaration would not have worked: we would have needed to define the first part of the syndrome register *before* the second part of the message register. But this would then have prevented us from extending the syndrome register.

This also is a first demonstration of how to access yquant objects from within TikZ. We name several elements that visually form the enclosing rectangle; then, we use the TikZ library fit to put a node around them all.

Then we see how to apply an operation to multiple registers in parallel while using the \idx macro to still give them a different text. Since \idx gives a numerical index (zero-based), we exploit the ASCII code (actually, this document is compiled in Unicode mode...) to turn this into a letter.


The example also demonstrates how to put a description next to a gate. In general, those descriptions should be realized using the TikZ feature label. Using the TikZ library quotes, the label is most easily specified. Since the label is not part of the valid arguments and also cannot be found in the /yquant path, it is automatically passed to /yquant/operator style.

# 6.2.2 IV. Simple Quantum Circuits





# A. Wires and gates






```
\begin{tikzpicture}
\begin{yquant*}
box {$U$} a;
box {$U^dagger} b;
\yquantset{every wire/.append}

⇒ style={->}}
\end{yquant*}
\end{tikzpicture}
```

Though yquant does not provide any direct mechanism to achieve such wire re-design, changing the wire style at an appropriate position does work. Setting the style beforehand would have made every connecting wire (including the initial ones) into arrows.


#### B. CNOT and other controlled single qubits gates







#### C. Vertical wires





There is no direct support for this construction, but as with the initialization of a vector registers, yquant allows to access the macro \idx within an operator value. This macro follows the same rules as the name suffix, i.e., it assigns indices (zero-based) to the target registers in top-to-bottom order, regardless of which order was specified in the target list. Since we instead want a one-based subscript, we need to add one. Note that if you want to output \idx directly or within an unexpandable expression, you don't need to take any action. However, here, \the is expandable; and since yquant needs to process all its output twice (first in order to determine the vertical spacing, second to actually typeset), you must manually take care that the command is not expanded prematurely by inserting \protect. Had you not done this, the subscript would have been "1" for both operators. Note this is not the case if

this macro is used upon creation of a register (as is evident by the fact that the previous examples that used \ifcase within the value did not need to say \protect\ifcase ... \protect\or ... \protect\fi). Probably we can avoid the need for protection in a future release....

### D. Labeling input and output states

```
\begin{tikzpicture}
\begin{yquant*}
qubit {$\ket1$} q[2];
cnot q[0] | q[1];
output {$\ket\idx$} q;
\end{yquant*}
\end{tikzpicture}
```




Here, three different styles for the initialization of multi-qubit labels are used. The second one (using a curly brace) corresponds to the default. It is overwritten for the first qubit, and to make this modification local, this is done in a group.


The third qubit pair uses an overall label and additionally individual labels on the lines. This is achieved by some trickery: the individual labels are given as initialization labels on the register; the global label is given as an init multi-qubit gate.

# 6.2.3 V. More Complicated Circuits: Multiple Qubit gates and Beyond

### A. Multiple qubit gates







This demonstrates how a register of type nobit might even be useful if the register is never used. We use box registers with disabled border to put the ellipsis dots in place.



*Note:* The behavior with a line cannot be reproduced without resolving to TikZ. However, as qcircut's manual admits, "such notation may be a bit confusing," so probably support will not be added.

#### B. Measurements and classical bits


The "tab" and "measure" type are not supported yet. Extracting a meter symbol on its own will not be supported. If you are interested in the code, have a look at yquant-shapes.tex and search for the yquant-measure shape.


```
\begin{tikzpicture}
\begin{yquant*}
\square \left\{ \text{shape=yquant-circle} \right\} \text{box {Codebit} a;} \text{box {$\chi$} b | a;} \text{discard a;} \text{measure b;} \text{end{yquant*}} \text{end{tikzpicture}}


Rectangles with rounded corners are not supported yet.
```






















### C. Non-gate inserts, forcing space, and swap



Here, the intermediate text was inserted by using a box without drawing. Another way would be to use an init command, although this is semantically wrong (probably).




Note how the register range – was used to denote all registers. We positioned the dots by first naming the relevant registers, so that the vertical position is at the coordinates ypos-0 and ypos-1; and then, we also named the cnot gates, so that we are able to discern the horizontal position.






#### D. Barriers





Now the **qcircuit** manual lists three circuits with barriers at different positions. They cannot be drawn with **yquant**; however, since neither of them is a valid circuit, this is of no concern.

### E. How to control anything






Note that it is not possible to draw a control to measurement (the measurement operations are explicitly defined not to accept controls): Either the measurement is performed or not (which transforms the register type), but a measurement conditioned on a quantum state is not possible. In principle, one could think of a measurement conditioned on a classical register (in which case the register type cannot change, as maybe the state stays quantum; the measurement operation then is similar to a complete dephasing). If there is need for this, please file a feature request.

### 6.2.4 VI. Bells and Whistles: Tweaking Your Diagram to Perfection


For options how to configure the circuits, refer to section 3.

# A. Spacing






# **B.** Labeling



initial labels needs some care and manual fine-tuning.

# C. Grouping






```
% \usetikzlibrary{fit}
\begin{tikzpicture}
   begin{yquant*}[register/separation=3mm]
     cnot a[2] | a[0];
     cnot a[2] | a[1];
      [name=left]
     h a[0], a[1];
     z a[2];
     cnot a[1] | a[0];
      [name=righttop]
     h a[0];
      [name=rightbot]
     h a[1] | a[2];
     hspace {2mm} -;
   \end{yquant*}
   \node[draw, dashed, fit=(left-0) (left-1) (righttop) (rightbot-0)] {};
\end{tikzpicture}
```


Note that \begin{yquant\*} must not be followed by a line break (unless masked by %) if options follow.

# 6.3 quantikz documentation

Again, our section headings will be the same as in the quantikz manual. And since quantikz also has even more space between the gates, we globally say \yquantset{operator/separation=4mm}.


# 6.3.1 II. A single wire








#### A. Measurements



#### B. Wires and arrows



This example demonstrates how to instruct the measure gate to use a different output type than the standard cbit.

In general, any macros that are used within a TikZ path or a yquant operation must not be fragile, or must be preceded with \protect. In this example, \\ is a



robust command (at least in newer kernels), so protection is not required. Since it may occur quite frequently that yquant is used within a center environment or in \centering mode (in which \\ is still fragile), yquant takes care of this (it actually robustifies \@centercr, which is the meaning of \\ in these surroundings).

In order to change the style of an individual wire, the proper \yquantset command must be placed directly before the wire is internally drawn (which happens when the next gate that needs a connecting line is drawn). Remember to use grouping so that the changes are local. However, the output wires are all drawn together, so it is not possible to individually change the style of a single output wire, only all of them.


```
\label{eq:linear_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_of_set_
```

Again, you see an example of how some commands need to be \protected when used in yquant options, and that you can indeed exploit all features of the quotes library.





# 6.3.2 III. Multiple Qubits





```
\begin{tikzpicture}
  \begin{yquant}
    qubit {$\ket0$} a;
    qubit {$\ket0$} b;

    h a, b;
    cnot b | a;
    box {$U$} a ~ b;
    zz (a, b);

    [after=a]
    qubit {} c;

    swap (a, c);
    box {$U$} c | a ~ b;
    \end{yquant}
\end{tikzpicture}
```


This example demonstrates the use of the after argument that instructs the register creation to begin the register only after the current position of another register that already exists.






```
\begin{tikzpicture}
   \begin{yquant*}
      [name=c]
      cnot a[0], a[2] | a[1];
      [name=m]
      measure a[1];
      discard a[2];
      \path[/yquant/every wire, /yquant/every qubit wire] (c-1) --
      \hookrightarrow (m.center |- c-1);
      box {$U$} a[0] | a[1];
      discard a[1];
   \end{yquant*}
\end{tikzpicture}
```

It is not possible for the double control line to directly exit the measurement gate. Also, if you discard a gate, this will prevent it from exiting from its last gate. yquant will not allow you (apart from manual drawing) to extend the wire to some arbitrary position, then drop it. But of course, as done here, you can always resort to the full power of TikZ.






#### 6.3.3 IV. Operating on many Qubits




Multi-qubits inputs are possible using the init command. The text assigned to a register declaration is always for an individual register.





yquant does not use a grid layout: operators are stacked next to each other. Therefore, there is no automatic centering of a column, though it could be emulated using hand-crafted hspace commands, as was done here (the Hadamard gate uses the /yquant/operator/minimum width, which is 5mm, while the large box has a width of 2cm, so that we need two 7.5mm spacings at the end, as the hspace pseudo-gate only inserts exactly the space you give, but not additional [twice] /yquant/operator/separation, as would be the case for a hypothetical zero-width gate). In fact, we don't even need the second hspace, since the two-qubit cnot will automatically enforce correct alignment.






```
\begin{tikzpicture}[braced/.style={decoration={brace, #1, pre=moveto, pre

    length=-1pt, post=moveto, post length=-1mm}, decorate},

    inner/.style={font=\footnotesize}]


   \begin{yquant} [register/separation=3mm]
      [name=a]
      qubit {} a[4];
      [x radius=1cm, name=u]
      box {$U$} (a[1]-a[3]) | a[0];
   \end{vquant}
   \draw[braced]
      ([xshift=2pt] a-1 - | u.west) -- ([xshift=2pt] a-2 - | u.west)
      node[inner, anchor=west, xshift=1pt, pos=.55] {$x$};
   \draw[braced=mirror]
      ([xshift=-2pt] a-1 -| u.east) -- ([xshift=-2pt] a-2 -| u.east)
      node[inner, anchor=east, xshift=-1pt, pos=.55] {$x$};
   \node[inner, anchor=west] at (a-3 -| u.west) {\smash{$y$}};
   \node[inner, anchor=east] at (a-3 -| u.east) {\smash{$y \oplus f(x)$}};
\end{tikzpicture}
```

There is no simple way to draw *within* a gate, though this is probably something that will be easier using subcircuits (planned feature). Instead, here the intricate parts were reproduced using TikZ: first, we make sure we assign a name to every relevant coordinate. Then we use some TikZ styles to draw the braces and nodes at the intersection of these coordinates. Here, we also make use of the moveto decoration transformation that comes with yquant and that allows to enlarge the braces slightly for a good overall appearance. Finally, as y has a much smaller height than  $y \oplus f(x)$ , we make sure this does not affect the vertical positioning; and also, as x has no ascender, we need to slightly position it off-mid for a good look.






### A. Different connections




This example for the first time demonstrates the declaration of a non-existing register and the setwire pseudo-gate that acts as a zero-width, no-content init gate.

# 6.3.4 V. Slicing




There is nothing like a slice all keyword, as yquant's underlying layout is not grid-based. Changing the style of slice captions simply means providing label options. This time, we used the label key instead of the shorter syntax



provided by the quotes library, which is of course also possible.



```
% \time {\it usetikzlibrary \{ quotes \}}
\begin{tikzpicture}[every label/.style={rotate=40, anchor=south west}]
   \begin{yquant}[operators/every barrier/.append style={blue, thick}]
      qubit {} a[3];
      h a[0];
      ["slice 1"]
      barrier (-);
      cnot a[1] | a[0];
      ["slice 2"]
      barrier (-);
      measure a[0];
      discard a[0];
      cnot a[2] | a[1];
      ["slice 3"]
      barrier (-);
      h a[1];
   \end{yquant}
\end{tikzpicture}
```





```
% \time {\it library \{quotes\}}
\begin{tikzpicture}[label distance=4mm]
   \begin{yquant}[operators/every barrier/.append style={red, thick,
   \rightarrow shorten <= -2.5mm, shorten >= -2.5mm}]
      qubit {$\ket0$} a;
      h a;
      ["1"]
      barrier (a);
      phase {[label distance=0pt]$\varphi$} a;
      ["2"]
      barrier (a);
      h a;
      ["3"]
      barrier (a);
      output {$\cos\frac\varphi2 \ket0 - i\sin\frac\varphi2 \ket1$};
   \end{yquant}
\end{tikzpicture}
```

Usually, the shorten keys do not have any effect on yquant operations, since the latter are all made up of nodes. However, the yquant-barrier shape

explicitly takes care of correctly handling them. It is the only one that does so. Since barriers usually end quite closely to the wires—and the default dashed style may make this worse—the shortening may often prove useful. Note that if the barriers are enlarged by means of negative shortenings, this will not affect the bounding box or internal register height calculations, and you must take care of appropriately shifting labels. Also note that we used much larger magnitudes in order to achieve a similar appearance as in quantikz. To avoid that the large distance also affects the phase gate badly, we locally reset the distance; for this, there are two ways. The easiest one is to make use of the fact that the value of the phase gate is passed directly as label argument, so that we can locally reset the distance. The other possibility would be to write


```
{
    \yquantset{/tikz/label distance=0pt}
    phase {$\varphi$} a;
}
```


since due to the aforementioned lack of support for a style that sets the options in TikZ, we must manually use a (grouped) \yquantset instruction for this. Note that whenever you change a TikZ style in a yquant environment, use the \yquantset macro, not \tikzset or \pgfkeys. Not only will the latter two not automatically restart the parser (so that you would have to issue \yquant after their use), but yquant has to process all its content twice in order to properly determine the register height. Only \yquantset will be properly captured and re-issued at the correct position when the content is actually typeset. Had we written \tikzset{label distance=0pt} \yquant, no effect at all would have been visible, since this command would only have taken effect in the first (invisible) round when yquant determines heights.

yquant does not provide a mechanism for vertical labels, but you may of course just insert line breaks at appropriate positions (and set the align property of the labels).

#### 6.3.5 VI. Spacing

### A. Local adjustment





```
\begin{tikzpicture}
\begin{yquant*}
    [x radius=1cm]
    x a;
    box {\hbox to 1cm{\hfil$X$\hfil}} a;
    hspace {1cm} a;
    x a;
    discard a;
    \end{yquant*}
\end{tikzpicture}

Here, we demonstrate two possibilities to enlarge a box: The first is by specify-
```


the qubit initializer takes. However, both approaches enlarge the *height* of the registers, i.e., add half of the specified amount to the top and the bottom.







ing its size in terms of the x radius or y radius keys beforehand. Those values serve as minimum sizes and would be extended if the text extended beyond the box. The second option is to just enlarge the text artificially by explicitly putting it into a fixed-width box. Note that in the first case, the *radius* is specified, i.e., the half-width, while in the second case, it is the *total* width (both times modulo the inner separation). Also note that the /yquant/operator/minimum width style is unsuitable for the given task: it would not change the visual width, only what yquant assumes its width to be.

# **B. Global Adjustment**












#### C. Alignment





Not specifying anything for the vertical alignment will lead to the common TikZ problem: the baseline will be at the bottom, which is particularly bad in this case due to the missing X gate. The /yquant/register/minimum height key does not help here, since it only affects yquant's internal handling, but not the bounding box calculated by TikZ. In the first example of the qcircuit documentation, we demonstrated how the desired task can easily be achieved in terms of baselines. We will now do the same with scopes instead.


$$\begin{array}{c} X \\ \hline \end{array} = \begin{array}{c} X \\ \hline \end{array} X$$


```
\begin{tikzpicture}[/yquant/register/minimum height=5mm]
  \begin{yquant*}
    x a[0];
    cnot a[1] | a[0];
  \end{yquant*}
  \path (current bounding box.east |- 0, 0) ++(1, 0) coordinate (shift);
  \begin{scope}[shift=(shift)]
    \begin{yquant*}
    cnot a[1] | a[0];
    x a;
  \end{yquant*}
  \end{yquant*}
\end{scope}
  \node at (current bounding box) {$=$};
\end{tikzpicture}
```

Here, we increased the minimum height so that in the left circuit despite the absence of the X gate, the second register has the same separation. We used


the meta-node current bounding box to avoid the need to manually specify hard-coded positions.

# 1. Perfecting Vertical Alignment










Of course, you may also use the features of the TikZ library calc to achieve the same shift.

## D. Scaling

\end{tikzpicture}




Here, we first scaled the circuit itself. However, since TikZ does not apply scaling to nodes (which means any operation) unless explicitly told so, we need to add the style to those.






#### 6.3.6 VII. Typesetting

#### A. Global Styling



Instead of setting /yquant/operators/every h, we could also have changed /yquant/operators/every box. Had we used /yquant/every operator, then the measurement would also have changed. Again, due to a TikZ limitation, it is not possible to change the position of labels on a per-style basis, only by using label options or a global setting.






```
\begin{tikzpicture}[thick]
  \begin{yquant*}[every operator/.prefix style={fill=white}]
  cnot a[1] | a[0];
  box {$R_z(-\theta\fracslash2)$} a[1];
  cnot a[1] | a[0];
  box {$R_z(\theta\fracslash2)$} a[1];
  measure a[1];
  \end{yquant*}
\end{tikzpicture}
```

Since the "thin" style is the default, we here present the opposite. Also note that by default, all operators are transparent, here we changed this by giving all of them a white background color (but as a style *prefix*, so that, e.g., black fillings overwrite this). Contrary to quantikz, this also fills the cnots. If you

only want to fill certain operators, you have to selectively target them using their appropriate styles.




yquant will make sure that "pass-through" lines are never obscured, even if, as in this case, the backgrounds are explicitly filled.

# **B. Per-Gate Styling**

```
% \usetikzlibrary{quotes}
\begin\tikzpicture\
  \usetikzlibrary{quotes}
\begin\tikzpicture\
  \usetikzlibrary{quotes}
\begin\tyquant*\
  [fill=red!20,
   \uperatorup font=\color\{cyan\}]
  h a;
  [green]
  phase {[green]$\beta$} a;
  ["$\ket\pm$"]
  measure a;
  discard a;
  \end\tikzpicture\
\end\tikzpicture\}
```








```
% \usetikzlibrary{shapes.symbols, fit}
\begin{tikzpicture}
   \begin{yquant}
      qubit {} data;
      qubit {$\ket0$} anc1[2];
     h data;
      cnot anc1 | data;
      [after=data]
      qubit {$\ket0$} anc2[2];
      [name=box, draw=none]
      box {\phantom{noise}} (data, anc1);
      cnot anc2[0] | data;
      cnot anc2 | anc1[0];
      cnot anc2[1] | anc1[1];
     measure anc2;
   \end{yquant}
   \node[starburst, cyan, fill=yellow, draw=red,
         line width=2pt, inner xsep=-4pt, inner ysep=-5pt, fit=(box)]
         \end{tikzpicture}
```

TikZ shapes cannot simply be used with yquant. Any yquant shape must be aware of the keys x radius and y radius that control its width and height. Additionally, yquant shapes must implement the circuit anchor (which can usually be let to the center anchor), and they must implement projection anchors. Those objects, which are a yquant addition to TikZ allow yquant to determine where precisely the wires at the individual positions are supposed to begin and end. yquant draws its elements sequentially; hence, a wire that comes into an operator will be hidden by anything the operator draws on top of it; but outgoing wires will in turn draw on the operator. To avoid the issues, we construct an invisible box operator and name it; outside of the yquant environment, we fit the special TikZ shape on top of it.

# C. Boxing/Highlighting Parts of a Circuit







```
SWAP
% \usetikzlibrary{quotes, backgrounds}
\begin{tikzpicture}
   \begin{yquant*}
      ha;
      [name=left]
      cnot b | a;
      cnot a | b;
      [name=right]
      cnot b | a;
      h b;
   \end{yquant*}
   \scoped[on background layer]
      \node[fit=(left-0) (left-p0) (right-0) (right-p0),
            draw, dashed, rounded corners, fill=blue!20,
            inner xsep=6pt, inner ysep=10pt,
            "\textsc{swap}" below] {};
\end{tikzpicture}
```

In this example, we need to refer to names, but want to fill the background before those nodes are actually available. Hence, we use the layering mechanism of TikZ and put the node on the background layer. Alternatively, we could have drawn on top and used opacity to still make visible what is behind; but in general, whenever you can avoid to use opacities, do avoid it; it adds overhead at the renderer and may give sub-optimal result when printing since the viewer has to reduce all elements to non-overlapping parts.


yquant does not support the fancy nearest-neighbor swap gate that quantikz has. It would however not be very difficult to implement this particular shape and make it available.

#### 6.3.7 VIII. Otherwise undocumented features

\end{yquant}

\end{tikzpicture}

ysep=.5pt, inner xsep=0pt] {};




Here, we included quantikz, which provides the wave shape, then introduced a register that will contain this wave (and enlarged it sufficiently). After the circuit is drawn, we fit the wave along. Since the name assigned to a register without any text actually is of a coordinate shape, we need to enlarge the height of the wave by providing a slightly increased inner ysep. Additionally, quantikz sets a negative inner xsep, which is probably required for its grid layout; but yquant positions exactly, so we also need to reset this.

\node[wave, fit=(wave) (current bounding box.east |- wave), inner



# 6.3.8 X. Troubleshooting





### 7 Wishlist

This section contains some thoughts on future improvements and features.

#### • Subcircuit support.

A subcircuit is a quantum circuit on its own that is put into a box within other circuits. It has input, output, and also internal wires. Subcircuits may be declared on-the-fly if they are used only once, but there should also be the option to globally declare subcircuits and use them at any time. As with ordinary quantum circuits, everything in a subcircuit should be allowed to have a name. If the subcircuit itself is then also named, those inner names should be made available (prefixed with the subcircuit's name), to the outer circuit. Subcircuits may also contain subcircuits. While the number of input registers should match, a subcircuit may have more, less or different output registers. The language needs to be extended to somehow allow for this. Subcircuits will typically be multi-qubit elements that, at least if internal wires are used, may significantly increase the required height for an individual register. Hence, the internal height calculations must be adapted. This will be particularly problematic if the subcircuit targets non-adjacent wires.

#### • Better handling of non-adjacent wires.

While this would be a nice feature, an implementation would hard: How should the individual shapes behave for non-adjacent wires? Two boxes, connected by a wire, as used in one qcircuit example, is a simplistic design that quickly fails for more complicated or larger shapes.

#### · Subranges.

It would be nice to also have support for ranges within vector registers, such as a[1-3] or a[-5].

#### • Whitespaces in ranges.

At the moment, whitespace handling in range specifiers is somewhat restricted. Better not to use whitespaces.

#### • Styling the wires.

It is currently relatively hard to selectively style wires. While individual wire segments can be targeted by changing the appropriate wire styles before the operation that would draw the ingoing wire, it must then be reset and it is cumbersome to do this for all wire segments of a register. Additionally, styling the final output wires individually is not possible. For this, it would be advantageous to allow a wire style on a per-register basis.

#### • Support for other languages.

It would be particularly nice to introduce a language mode. While the yquant language will always provide the set of everything yquant can do at the moment, it would be nice if yquant can automatically detect OpenQASM and parse its content correctly. OpenQASM is much more limited than yquant and, being a language designed for actual execution of the circuits, does not provide means to change visual appearance. Probably some yquant additions to OpenQASM would be ok, as long as they only complement the original language? Also, OpenQASM support would probably require subcircuits.

Another nice feature would be to support qasm. Also here, the feature set is much more limited and it would probably be hard to implement an automatic detection, the user would have to specify the language by hand.

### Vertical layout.

Sometimes, long quantum circuits on a portrait page can be better represented in a vertical layout. Also if lots of explanations are to be added, this becomes problematic in the horizontal version. In principle, yquant's approach could allow for a simple key switch that changes horizontal to vertical. Currently, this is largely unsupported by all quantum circuit packages except for qpic.