

FEB 20, 2023

Sidoli Phosphoenrichment From Clean Dry Peptides

Edwin Yoo¹

¹johns hopkins



Edwin Yoo

ABSTRACT

Sidoli Phosphoenrichment From Clean Dry Peptides

MATERIALS

- Loading buffer: 80% Acetonitrile, 5% TFA and 1 M Glycolic acid (76 mg/mL) Washing buffer 1: 80% Acetonitrile, 1% TFA
- Washing buffer 2: 20% Acetonitrile, 0.2% TFA
- Elution buffer: 40 μL Ammonia solution (28%) in 980 μL H2O, pH 11,3
- Titanium Dioxide (TiO2) beads, e.g. GL Sciences catalog # GL-5010-21315

OPEN ACCESS

DOI:

dx.doi.org/10.17504/protocol s.io.n2bvj8jxngk5/v1

Protocol Citation: Edwin Yoo 2023. Sidoli Phosphoenrichment From Clean Dry Peptides. **protocols.io** https://dx.doi.org/10.17504/protocols.io.n2bvj8jxngk5/v1

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's working

Created: Feb 19, 2023

Last Modified: Feb 20, 2023

PROTOCOL integer ID:

77263

1 Obtain trypsinized peptides that are clean and dried (ie. completed desalting or S-trap).


Note

Can do this protocol carefully on deep well 96 well plate to multiplex. Need to aspirate supernatant from bottom corner of the deep well plate as to avoid aspirating titanium.

- Dilute your peptide solution at least 10 times with loading buffer (alternatively if you have 100 μL sample you can add 50 μl water, 50 μL 100% TFA, 800 μL Acetonitrile and 76 mg Glycolic acid to make the sample up to the proper loading buffer). If completely dry, can just resuspend with 100 ul loading buffer.
- ${\bf 3}$ Add 0.6 mg TiO2 beads per 100 μg peptide solution. Make up enough master mix of bead suspension.

Note

Titanium beads are heavy and sink to the bottom of tube so need to keep vortexing to keep solutions homogenous.



- Place the tubes on the shaker (highest shaking) at room temperature for 5-10 min Centrifuge to pellet the beads (table centrifuge <15 sec)
- 5 Remove the supernatant
- Wash the beads with 70-100 μL loading buffer mix for 15 sec, transfer to another eppendorff tube and then centrifuge to pellet the beads (the transfer is performed due to the fact that peptides and phosphopeptides stick to surfaces and can be eluted in the last elution step)
- 7 Wash with 70-100 μ L washing buffer 1 mix for 15 sec and then centrifuge to pellet the beads. Remove supernatant.

- $\begin{tabular}{ll} \textbf{8} & Wash with 50-100 ~\mu L washing buffer 2-mix for 15 sec and then centrifuge to pellet the beads. \\ & This step is important to remove peptides that bind in a HILIC mode to TiO2. Remove supernatant. \\ \end{tabular}$
- 9 Dry the beads for 5-10 min in the vacuum centrifuge or on the table.
- Elute the phosphopeptides with 50 μ L Elution buffer mix well and leave the solution and the beads for 5-10 min to allow an efficient elution
- Centrifuge the solution for 1 min, recover the supernatant (as it contains the phosphopeptides) and dry it in a SpeedVac centrifuge. Ready for injection.