

Aug 06, 2024



# Competent Transformation

DOI

dx.doi.org/10.17504/protocols.io.5jyl82w47l2w/v1

Miguel Estévez-Gay<sup>1</sup>

<sup>1</sup>Universitat de Girona



### Miquel Estévez-Gay

Universitat de Girona

# OPEN ACCESS



DOI: dx.doi.org/10.17504/protocols.io.5jyl82w47l2w/v1

Protocol Citation: Miquel Estévez-Gay 2024. Competent Transformation. protocols.io

https://dx.doi.org/10.17504/protocols.io.5jyl82w47l2w/v1

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits

unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's

working

Created: August 06, 2024

Last Modified: August 06, 2024

Protocol Integer ID: 104804

#### **Abstract**

Transform a Plasmid into previously obtained Competent E.coli Cells.



# Safety warnings



1 Competent Cells are fragile. Please do not use Vortex and work with aseptic conditions



- 1 Melt in ice and aliquot of 100μL competent E-coli DH5α or BL21(DE3).
- 2 Preheat  $\perp$  500  $\mu$ L LB or SOC medium (37°C).
- 3 Add 50-100µg DNA into competent cells and mix softly. This is usually 1-2µl from minipreps. I recommend using 10µl if the DNA comes from PCR and/or DpnI digestion.



4 Incubate (5) 00:20:00 in ice.

20m

5 Incubate without shaking at \$\circ\$ 42 °C for \( \cdot \) 00:01:00 .

1m

6 Incubate 00:02:00 in ice.

2m

7 Add 🚨 500 µL LB or SOC pre-heated media. This must be done under Laminar Flux Cabin

8 Incubate (5) 01:00:00 (5 800 rpm, 37°C in shaker thermal block.

1h

- 9 Prepare Amp or Kan plates.
- 10 Add Δ 100 μL competent cells into each plate and plate. Mix using sterile glass balls under laminar flux cabin.

11 Incubate 37 °C Overnight

T

12 Next day, store the plates parafilmed in the fridge. Can be stored for several weeks.