

AUG 09, 2023

Preparation of soluble and insoluble mitochondrial protein fractions for mass spectrometry analysis

Louise Uoselis¹

¹Lazarou Lab, WEHI



Louise Uoselis WEHI

ABSTRACT

Preparation of soluble and insoluble mitochondrial protein fractions from HeLa cells for mass spectrometry analysis.





DOI:

dx.doi.org/10.17504/protocol s.io.kxygx394kg8j/v1

Protocol Citation: Louise Uoselis 2023. Preparation of soluble and insoluble mitochondrial protein fractions for mass spectrometry analysis. **protocols.io**

protocois.io

https://dx.doi.org/10.17504/protocols.io.kxygx394kg8j/v1

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's working

Created: Aug 09, 2023


Last Modified: Aug 09,

2023

PROTOCOL integer ID:

86208

Keywords: ASAPCRN



- Using a pipette, carefully remove \bot 57 μ L of the supernatant from the insoluble protein fraction, and place into a clean microfuge tube (which will function as the waste collection tube for all samples).
- **9** Repeat steps 6 8, which will total 2 washes
- Repeat step 6. You should now have two tubes for each sample (soluble and insoluble protein fractions), and one waste tube.
- Thaw aliquots of recombinant Ag85A on ice, and add 180 ng of Ag85A to each insoluble protein fraction, and 171 ng of Ag85A to each soluble fraction.
- Equilibrate all samples to room temperature and then add 2x SDS solubilization buffer to a final concentration of 1x (2x: 10% w/v SDS, 200 mM HEPES pH 8.5). Vortex each samples for ~ 5 seconds to mix.
- Sonicate all samples in a waterbath sonicator set to 5 21 °C for 00:10:00

Add TCEP to a final concentration of [M] 10 millimolar (mM) and chloroacetamide to a final concentration of [M] 40 millimolar (mM) to each sample, vortex each sample for ~5 seconds to mix, and incubate samples at \$\mathbb{E}\$ 37 °C for \cdots 00:45:00 (standing).

Note

Make sure chloroacetamide is made up fresh from powder

10m

45m

- Acidify each sample by adding phosphoric acid to a final concentration of 1.2%/sample (ensure pH <4. More phosphoric acid can be added if the pH is not low enough at 1.2%/sample)
- Add binding buffer ([M] 100 millimolar (mM) triethylammonium bicarbonate, 90% v/v methanol pH 7.1 with phosphoric acid) to each sample at a ratio of 1:7, sample volume to binding buffer.
- 17 Vortex each sample for ~5 sec to mix
- Load \triangle 400 μ L of each sample into a S-Trap Mini column, and centrifuge at Room temperature for \bigcirc 00:00:30 . Discard the flow through.
- Repeat step 18 until the full volume of each sample has been loaded on its column.
- Wash each column by adding ∠ 400 µL of binding buffer, centrifuging at € 6500 rcf at Room temperature for ⊙ 00:00:30 , and discarding the flow through.
- 21 Repeat step 20 three times, for a total of 4 washes.
- Move the columns to a 1.5 mL LoBind microfuge tube (Eppendorf) and add Δ 125 μL of digestion buffer directly to the column filter (digestion buffer: [M] 50 millimolar (mM) triethylammonium bicarbonate supplemented with sequencing grade trypsin at a concentration of 1 ug trypsin to 50 ug of starting protein (which will differ between soluble and insoluble samples)).

30s

- Centrifuge samples at 1000x rcf for 00:00:30 at room temperature, and pipette the digestion buffer flow through directly back onto the column filter. Move the columns to clean 2.0 mL LoBind microfuge tubes.
- Seal each sample to the LoBind microfuge tube with parafilm, and incubate samples overnight for at least 16:00:00 at 37 deg C (static incubation)

Day 2 25 Remove the parafilm and add Δ 80 μL of digestion buffer without trypsin (50 mM triethylammonium bicarbonate) to each sample. Centrifuge samples at 3200 rcf for 00:01:00 at Room temperature. Leave the flow through in the collection tube. 26 Add Δ 80 μL of 0.2% v/v formic acid to each sample, and centrifuge at 3200 rcf for 00:01:00 at room temperature. Leave the flow through in the collection tube.

- Add A 80 µL of 50% v/v acetonitrile/0.2% v/v formic acid to each sample, and centrifuge a 6500 rcf for 00:01:00.
- 28 Remove and discard the S-Trap columns from each sample.
- 29 Lyophilise the total eluate from each sample, seal the samples with parafilm and store at \$\circ\$ -80 °C until needed for downstream processing.

30s