

Jul 17, 2024 Version 2

() (

One-pot native barcoding of amplicons v4 (LoCost) V.2

DOI

dx.doi.org/10.17504/protocols.io.kxygxebydv8j/v2

Josh Quick¹, Lauren Lansdowne¹

¹University of Birmingham

Josh Quick: Original protocol author - thank you!



Josh Quick

University of Birmingham

OPEN ACCESS



DOI: dx.doi.org/10.17504/protocols.io.kxygxebydv8j/v2

External link: http://lab.loman.net/protocols/

Protocol Citation: Josh Quick, Lauren Lansdowne 2024. One-pot native barcoding of amplicons v4 (LoCost). protocols.io https://dx.doi.org/10.17504/protocols.io.kxygxebydv8j/v2Version created by Josh Quick

License: This is an open access protocol distributed under the terms of the <u>Creative Commons Attribution License</u>, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's

working

Created: April 11, 2024

Last Modified: July 17, 2024

Protocol Integer ID: 98065

Abstract

This one-pot native barcoding protocol was developed in conjunction with Oxford Nanopore Technologies, New England Biolabs and BCCDC.



Attachments



One-pot native barco...

64KB

Safety warnings



See SDS (Safety Data Sheet) for safety warnings and hazards.



1 In a new PCR strip-tube/plate set up the following reaction for each sample:

	Component	Volum e
	PCR dilution from previous step	3.3 µL
Γ	Ultra II End Prep Reaction Buffer	1.2 µL
Γ	Ultra II End Prep Enzyme Mix	0.5 µL
Γ	Nuclease-free water	5 μL
	Total	10 μL

Note

Make a master mix of end-preparation reagents and nuclease-free water and aliquot into strip-tube/plate to improve reproducability.

2 Incubate at room temperature for 00:15:00 Incubate at \$\mathbb{L}\$ 65 °C for \(\frac{1}{2} \) 00:15:00 Incubate on ice for 00:01:00

3 In a new PCR strip-tube/plate set up the following reaction for each sample:

Component	Volum e
End-preparation reaction mixtur e	0.75 μ L
NBXX barcode	1.25 μ L
Blunt/TA Ligase Master Mix	5 μL
Nuclease-free water	3 µL
Total	10 μL



Note

Use one native barcode from the EXP-NBD104 (1-12), EXP-NBD114 (13-24) or EXP-NBD196 per sample. Use 12 or more barcodes per library or there will be insufficient total material to achieve good yields.

If processing <11 samples, increase quantities in the above reaction to allow for sufficient

for sequencing. For example: if processing 6 samples, double the component volumes for a final reaction volume of 20µL for each sample.

4 Incubate at room temperature for 00:20:00

Incubate on ice for 00:01:00

Note

The 65°C incubation is to inactivate the DNA ligase to prevent barcode cross-ligation when reactions are pooled in the next step.

5 In a new A 1.5 mL Eppendorf tube pool all one-pot barcoding reactions together.

Note

If processing <24 samples pool the total volume from all barcodes. if processing 48 samples pool \perp 5 μ L from each native barcoding reaction. If processing 96 samples pool 4 2.5 µL from each native barcoding reaction so as not to exceed a pool volume of $\mathbb{Z}_{240 \text{ µL}}$ which would make the clean-up volume too large.

6 Add 0.4x volume of SPRI beads to the sample tube and mix gently by either flicking or pipetting. For example add Δ 96 μL SPRI beads to Δ 240 μL pooled one-pot barcoding reactions.



Note

0.4x volume of SPRI is sufficient to bind 400 bp amplicons in the presence of ligation buffer, do not use 1x as this will result in an excessive large bead pellet.

- 7 Mix by vortexing and pulse centrifuge to collect all liquid at the bottom of the tube. Incubate for 00:05:00 at room temperature.
- 8 Place on magnetic rack and incubate for 600:02:00 or until the beads have pelleted and the supernatant is completely clear. Carefully remove and discard the supernatant, being careful not to touch the bead pellet.
- 9 Add 🚨 250 µL SFB and resuspend beads completely by pipette mixing. Pulse centrifuge to collect all liquid at the bottom of the tube and place on the magnet. Remove supernatant and discard.

Note

SFB will remove excess adapter without damaging the adapter-protein complexes. Do not use 70% ethanol as in early clean-ups.

10 Repeat steps 11.9 to perform a second SFB wash. Pulse centrifuge and remove any residual SFB.

Note

You do not need to allow to air dry with SFB washes.

11 Add 4 200 µL of room-temperature [M] 70 % volume ethanol to bathe the pellet. Carefully remove and discard ethanol, being careful not to touch the bead pellet.

Note

Only perform 1x 70% ethanol wash



- Pulse centrifuge to collect all liquid at the bottom of the tube and carefully remove as much 12 residual ethanol as possible using a P10 pipette.
- 13 With the tube lid open incubate for 00:01:00 or until the pellet loses it's shine (if the pellet dries completely it will crack and become difficult to resuspend).
- 14 Resuspend pellet in A 30 µL [M] 10 millimolar (mM) Tris pH 8.0, mix gently by either flicking or pipetting and incubate for 00:02:00.
- 15 Place on magnet and transfer sample to a clean 4 1.5 mL Eppendorf tube ensuring no beads are transferred into this tube.