



Sep 23, 2022

♠ L3 stage C. elegans dissociation for FACS isolation and RNA-seq analysis of intestine-specific cells

In 1 collection

Robert TP Williams¹, Erin Osborne Nishimura¹

¹Colorado State University, Fort Collins



dx.doi.org/10.17504/protocols.io.14egn7zwmv5d/v1

Osborne Nishimura Lab



ABSTRACT

This protocol is for generating a single cell suspension suitable for isolation of intestine-specific cells through Fluorescence Activated Cell Sorting (FACS) from L3 stage *C. elegans*. This protocol utilizes treatment with SDS-DTT solution and Pronase E to disrupt the cuticle. Worms are mechanically homogenized with a dounce homogenizer.

DOI

dx.doi.org/10.17504/protocols.io.14egn7zwmv5d/v1

PROTOCOL CITATION

Robert TP Williams, Erin Osborne Nishimura 2022. L3 stage C. elegans dissociation for FACS isolation and RNA-seq analysis of intestine-specific cells. **protocols.io**

https://protocols.io/view/l3-stage-c-elegans-dissociation-for-facs-isolation-b363qrgn





FUNDERS ACKNOWLEDGEMENT

National Institutes of Health

Grant ID: R35GM124877

Bridge to Doctorate at Colorado State University

Grant ID: 1612513

National Science Foundation

Grant ID: 2143849

Webb-Waring Biomedical Research Award

Grant ID: E.O.N.

COLLECTIONS (i)

Protocol collection: Dissociation and FACS isolation of embryonic and postembryonic C. elegans intestine cells for RNA-seq analysis

KEYWORDS

C. elegans, intestine, FACS, single cell suspension, cell dissociation, L3 stage

LICENSE

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

CREATED

Jan 21, 2022

LAST MODIFIED

Sep 23, 2022

PROTOCOL INTEGER ID

57275

PARENT PROTOCOLS

Part of collection

Protocol collection: Dissociation and FACS isolation of embryonic and post-embryonic C. elegans intestine cells for RNA-seq analysis

MATERIALS TEXT

Strains:

- FACS control C. elegans strain, i.e. N2
- FACS sorting *C. elegans* strain, i.e. JM149 *cals71*[elt-2p::GFP::HIS-2B::unc-54 3'UTR + rol-6(su1006)]

Reagents:

L15-10 solution

- Leibovitz's L-15 Medium (Thermo 21083027)
- Fetal Bovine Serum (heat inactivated) (Thermo 10438026)
- 100X Penicillin Streptomycin solution (Thermo 15140148)
- Sucrose powder

Stock solutions for egg buffer

- 2M NaCl
- 2M KCl
- -1M CaCl2
- 1M MgCl2
- 1M HEPES pH 7.2

Enzymes

- Pronase E, Protease from Streptomyces griseus (Sigma P8811-1G)

Consumables:

- standard 1.5 ml tubes
- Stericup 0.2 micron filter (Fisher S2GPU05RE)
- 20-micron mesh filter (Fisher Scientific NC1004201)
- 35-micron nylon mesh filter caps (Stellar Scientific FSC-FLTCP)
- 5 ml sterile polypropylene round-bottom tube (STEMCELL Technologies 38057)
- Bio-Rad TC20 automated cell counting slide (Bio-rad 1450011)

Equipment:

- Fixed angle rotor centrifuge (Eppendorf 5424)
- Swinging bucket rotor refrigerated centrifuge (eppendorf 5810R)
- 15 ml tube and 1.5 ml tube adapter (eppendorf 022638704, eppendorf 022638742)
- Fluorescent microscope
- Nutating mixer
- Bio-Rad TC20 automated cell counter
- 2ml dounce homogenizer with pestle A (Sigma-Aldrich D8938)

Before beginning

1 Prepare reagents in advance

L15-10 Buffer: Mix 500 ml Leibovitz's L-15 Medium, 50 ml Fetal Bovine Serum (heat inactivated), 50 ul of 100x Penicillin-Streptomycin solution and 7.7 g sucrose. Filter with 0.2 micron pore filter. Store at 4°C.

Egg Buffer: Mix 29.5 ml of 2M NaCl, 12 ml of 2M KCl, 1 ml of 1M CaCl2, 1 ml of MgCl2, 12.5 ml of 1M HEPES-NaOH pH 7.2 and 435 ml molecular grade water. Filter with 0.2 micron pore filter.



3

Citation: Robert TP Williams, Erin Osborne Nishimura L3 stage C. elegans dissociation for FACS isolation and RNA-seq analysis of intestine-specific cells https://dx.doi.org/10.17504/protocols.io.14eqn7zwmv5d/v1

Store at 4°C.

Pronase E solution (15 mg/ml): Weigh 150 mg of Protease from Streptomyces griseus (Sigma P8811-1G) into a 15 ml tube. Dissolve the enzyme in 10 ml of Egg Buffer. Nutate the solution for approximately 10 minutes until dissolved. Prepare 1 ml aliquots in 1.5 ml tubes. Store aliquots at -20°C.

2 On day of protocol:

Cool swinging bucket centrifuge to 4°C
Thaw pronase aliquots at room temperature
Place L15-10 and egg buffer on ice
Wash and sterilize dounce homogenizer and pestle A (1ml H20, 1ml 70% EtOH)

3 Starting material:

Worm suspension in 15 ml tube (material generated from <u>this protocol</u>) Strains: N2, fluorescent sorting strain

Perform this protocol on both strains in parallel

Note: The volumes for chemical and enzymatic treatments in this protocol require an L3 pellet less than 200 uL. If L3 pellet exceeds 200 ul, utilize 2x the L3 pellet volume.

Harvest L3 worms

- 4 Harvest the synchronized L3 worms by washing the plates with fresh M9
- Pass the worm suspension through a 20 micron filter. All L3 stage worms will be retained on the filter, while any contaminating worms younger than the L3 stage will pass through the filter. This step will also quickly remove a majority of contaminating E. coli.
- 6 Invert the filter and collect the retained L3 worms into a fresh 50 ml tube
- 7 Transfer the filtered L3 worms to a 15 ml tube
- 8 Pellet the worms in a 15 ml tube for 1 min at 2,000 rcf. Discard the supernatant and repeat M9 washes until the supernatant is free of visible E. coli.

SDS-DTT Treatment



4

9	Once the worm suspension is free of E. coli, centrifuge worm suspension at 2,000 rcf for 1 minute	
10	Resuspend the worm pellet in 1 ml of M9 and transfer to a 1.5 ml tube.	
11	Pellet the worms again at 2000 rcf for 1 minute.	
12	Transfer 10 ul of L1 worm pellet to 1ml of Qiazol and store at -80°C for downstream RNA analysis	
13	Resuspend the worm pellet in 200 ul of fresh SDS-DTT solution	
14	Incubate for 2 min room temperature NOTE: - Worms should look ruffled, and pharynx should change from thin and elongated to short and round - Incubation exceeding 2 min will damage the sample	
15	Quench reaction by adding 800 ul of ice cold egg buffer	
16	Pellet worms at 13,000 rcf for 15 seconds at 4°C	
17	Decant the supernatant and replace with 1 ml of ice-cold egg buffer	
18	Repeat the egg buffer wash for a total of 5 washes	
Pronase E Treatment		
A protocols in		

 $\textbf{Citation:} \ \ \textbf{Robert TP Williams, Erin Osborne Nishimura L3 stage C. elegans dissociation for FACS isolation and RNA-seq analysis of intestine-specific cells $\frac{\text{https://dx.doi.org/10.17504/protocols.io.14egn7zwmv5d/v1}{\text{https://dx.doi.org/10.17504/protocols.io.14egn7zwmv5d/v1}}$

i protocols.io 6		
	29	Harvest the cells
	28	Visually confirm worm dissociation by viewing a 2 ul sample of worm slurry on a fluorescent microscope
	27	Perform 100 strokes with dounce pestle A to generate a worm slurry
	Cell dis	sociation Transfer the worm suspension to a 2 ml glass dounce homogenizer
	25	Resuspend the worms in 1ml of L15-10
	24	Pellet the worms at 13,000 rcf for 15 seconds at 4°C
	23	Decant the supernatant and resuspend the worms in 1 ml of L15-10
	22	Pellet the worms at 13,000 rcf for 15 seconds at 4°C
	21	Quench the Pronase E treatment by adding 1 ml of L15-10
	20	Incubate for 30 minutes at room temperature nutating to digest the cuticle
	19	Resuspend the SDS-DTT treated worms in 200 ul of 15 mg/ml Pronase E

29.1 Transfer worm slurry to 1 ml centrifuge tube

29.2

Pellet undissociated worms at 20 rcf for 1 minute at 4°C in swinging bucket centrifuge

NOTES:

- This step will separate the dissociated cells from intact worms
- Cells will remain in the supernatant
- Intact and partially dissociated worms will remain in the pellet
- Ensure your cell type of interest is not lost during this step.
- Visually confirm fluorescent cells **are present** in the supernatant.
- Visually confirm fluorescent cells are not present in the pellet.
- You may need to reduce the centrifuge speed and/or time if fluorescent cells are in the pellet of this step.
- 29.3 Aspirate 1 ml of the cell-containing supernatant. Keep the pipette away from the pelleted worm debris.
- 29.4 Dispense the cell suspension though a 35-micron nylon mesh filter into a 5 ml flow cytometry tube
- 30 Resuspend remaining worm slurry in 1ml of L15-10
- For the sorting strain, perform an additional round of dissociation and cell harvest (Steps 26-30). You will perform a total of two to three homogenization cycles, until few intact worms remain.

Total cell suspension volumes:

- Control strain = 1ml
- Sorting strain = 2-3ml
- 32 Transfer 70 ul of cells to 1 ml of Qiazol and store at -80°C for downstream RNA analysis
 - Continue to step 31
 - Retain the remaining ~2ml of cells for FACS



Measure approximate cell concentration

- 33 Load 10 ul of cell suspension to a Bio-Rad TC20 automated cell counting slide. Also can use a hemocytometer.
- 34 This protocol should yield between $2 imes10^6$ to $4 imes10^6$ total cells
- 35 Dilute the sample to $1 imes 10^6 rac{\mathrm{cells}}{\mathrm{ml}}$ if above this concentration with L15-10
- 36 Microscopically confirm fluorescent cells are present in the cell counting slide
- If the total cell yield is less than $1 imes 10^6\,$ cells and many intact worms remain, repeat the SDS-DTT, Pronase E and dounce homogenization steps
- 38 Move on to FACS protocol