

MAR 17, 2023

# OPEN ACCESS

#### DOI:

dx.doi.org/10.17504/protocol s.io.5qpvobp6bl4o/v1

**Protocol Citation:** michela.d eleidi, María José Pérez J. 2023. Single cell dissociation of brain organoids.

### protocols.io

https://dx.doi.org/10.17504/protocols.io.5qpvobp6bl4o/v1

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

**Protocol status:** Working We use this protocol and it's working

Created: Apr 27, 2022

Last Modified: Mar 17, 2023

### **PROTOCOL** integer ID:

61516

**Keywords:** brain organoids, cell dissociation, Papain Dissociation System

### Single cell dissociation of brain organoids

In 6 collections

michela.deleidi<sup>1</sup>, María José Pérez J.<sup>1</sup>

<sup>1</sup>German Center for Neurodegenerative Diseases (DZNE), Tübingen, 72076 Germany



Hariam Raji

**ABSTRACT** 

This protocol details about single cell dissociation of brain organoids.

**ATTACHMENTS** 

405-879.docx

**MATERIALS** 

### Kit:

Papain Dissociation System.

Papain Dissociation System Worthington Biochemical Corporation Catalog #LK003150

### Reconstitute powders.

- Add 🛕 5 mL Earle's medium into Papain Vial (1 Vial/2 organoids).
- Add 🗸 500 µL Earles's medium into DNAse vial.
- Add <u>A 35 mL</u> Earle´s medium into Inhibitor vial (1 vial/10 organoids).

## Single cell dissociation of brain organoids

27m

Mix Δ 500 μL DNAse with Δ 5 mL Papain.





Note

Note: MIX GENTLY.

- 2 Transfer single or pooled organoid to 60 mm dish.
- Aspirate excess media, add  $\perp$  2.5 mL Papain + DNAse solution.



- 4 With a razor blade mince organoid (<1 mm).
- 5 Transfer plate to an orbital shaker \$\( 5 \) 70 \( rpm, 00:30:00 \) (inside incubator).
- 6 With 1-mL pipette dissociate pieces (Mix up-down 30 times).
- 7 Put in orbital shaker 👏 00:20:00

20m

9 Remove samples from the orbital shaker. With a 1-mL tip, mix up-down 30 times.



- Take Δ 2 mL (upper part) into new tube using a 40 μm cell strainer. Wait 1-3 min to debris to settle.
- 11 Transfer cell suspension to the inhibitor tube. Invert to mix 5 times.



Centrifuge 300 rpm, Room temperature, 00:07:00



- **®**
- 14 Filter the resuspended cells (  $\angle$  900  $\mu$ L ) with a 30  $\mu$ m cell strainer.
- 15 Count the cells for the final suspension and dilute. Resuspend at 1000 cells/ $\mu$ l in 0.04% BSA-PBS.