



Aug 29, 2022

© pCP20 transformation to remove Kanamycin cassette

Saul Moore¹

¹Imperial College London, MRC London Institute of Medical Sciences
Saul Moore: This protocol was carried out by Cassandra Backes of the Host-Microbe Co-Metabolis
m laboratory

1 Works for me Share

dx.doi.org/10.17504/protocols.io.81wgbydxovpk/v1

Behavioural Genomics



DISCLAIMER

DISCLAIMER - FOR INFORMATIONAL PURPOSES ONLY; USE AT YOUR OWN RISK

The protocol content here is for informational purposes only and does not constitute legal, medical, clinical, or safety advice, or otherwise; content added to <u>protocols.io</u> is not peer reviewed and may not have undergone a formal approval of any kind. Information presented in this protocol should not substitute for independent professional judgment, advice, diagnosis, or treatment. Any action you take or refrain from taking using or relying upon the information presented here is strictly at your own risk. You agree that neither the Company nor any of the authors, contributors, administrators, or anyone else associated with <u>protocols.io</u>, can be held responsible for your use of the information contained in or linked to this protocol or any of our Sites/Apps and Services.

ABSTRACT

Transformation with pCP20 to remove the Kanamycin cassette from Keio *E. coli* BW215113 single gene deletion mutants - Cassandra Backes (Host-Microbe Co-Metabolism Laboratory, MRC-LMS)

DOI

dx.doi.org/10.17504/protocols.io.81wgbydxovpk/v1

PROTOCOL CITATION

Saul Moore 2022. pCP20 transformation to remove Kanamycin cassette. **protocols.io**

https://protocols.io/view/pcp20-transformation-to-remove-kanamycin-cassette-cfv9tn96



1

•

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

CREATED

Aug 28, 2022

LAST MODIFIED

Aug 29, 2022

PROTOCOL INTEGER ID

69281

MATERIALS TEXT

Making TSS broth (for final volume 10 mL): Make fresh!

- ·10% (w/v) Polyethylene Glycol (PEG) 3350* on media shelf; add 1 g
- ·LB broth add 9 mL
- ·50 mM Mg2+ (MgSO₄ or MgCl₂) use 1M stock of MgSO₄ used for NGM; add 500 uL
- ·Sterilise-filter into new tube
- ·5% (v/v) DMSO -chemical metal chest; add 500 uL

Making TSS enhanced buffer (for final volume of 10 mL):

- ·Add 8.2 mL of dH20 to 30 mL tube
- ·100mM KCl (to prepare 1M stock: 1.491 g in 20 mL of H20); add 1 mL
- ·30mM CaCl₂- use 1M stock for NGM; add 0.3 mL
- ·50mM MgSO4 use 1M stock for NGM; add 0.5 mL
- ·Vortex well and filter-sterilise into 2 mL tubes
- ·Keep in fridge
- *There are other molecular weights of PEG, so look at label carefully and choose one with 3350 on it!

DISCLAIMER:

DISCLAIMER - FOR INFORMATIONAL PURPOSES ONLY; USE AT YOUR OWN RISK

The protocol content here is for informational purposes only and does not constitute legal, medical, clinical, or safety advice, or otherwise; content added to protocols.io is not peer reviewed and may not have undergone a formal approval of any kind. Information presented in this protocol should not substitute for independent professional judgment, advice, diagnosis, or treatment. Any action you take or refrain from taking using or relying upon the information presented here is strictly at your own risk. You agree that neither the Company nor any of the authors, contributors, administrators, or anyone else associated with protocols.io, can be held responsible for your use of the information contained in or linked to this protocol or any of our Sites/Apps and Services.

1	Make buffer and broth the day before and keep them in the fridge
2	Day before: Grow O/N cultures of the strains of interest. Can also prepare buffers (see materials).
3	Dilute overnight culture in LB broth at an OD = 0,2 and grow until OD595nm = 0.5 – 0.8 (mid-log phase). UNTIL NOW, KEEP CULTURES ON ICE
4	Spin down culture(s): transfer first to 15 mL falcon, spin 4500 RPM, 10 min, 4°C
5	In the meantime, label 2 mL tubes with strain names and add 80uL TSS buffer and 1 - 5 uL of pDNA (50-75ng). vortex and keep on ice for 10 min.
6	Remove supernatant from 14 mL tubes and resuspend pellet in 1mL TSS broth (cold). Resuspend gently and keep on ice.
7	Then transfer cells to a 2 mL tube.
8	Add 200uL of bacterial culture in TSS broth to the 2 mL tubes containing pDNA in TSS buffer , Mix gently by pipetting.
9	Incubate for 20 min on ice.
10	Add 1mL LB.

11	Shake at 30°C for 1 hour 700 rpm.
12	Spin down (4500 RPM, 5 min), resuspend pellet in 300uL LB.
13	Spread 50 and 150ul on a plate and incubate at 30C in Chloramphenicol plates!
14	Keep remaining transformation mix at 4°C.
15	Check plates next day for single colonies, and confirm by PCR/Sequencing.