



Jul 01, 2021

From low cost plant HMW DNA extraction to MinION sequencing

Julien Serret¹, marie.couderc ¹, Cedric Mariac¹, Laurencealbar ¹, Francois Sabot¹

¹Institut de Recherche pour le Développement

	2 Works for me	Share	dx.doi.org/10.17504/protocols.io.bu3vnyn6					
Julien Serret Institut de Recherche pour le Développement								

ABSTRACT

This low cost protocol is efficient to extract high molecular weight DNA from several tropical plants to prepare LSK109 libraries for Nanopore sequencing. Pulsed-field gel electrophoresis reveals a DNA size range from 40 to 350 Kb for four species of rice, Paspalum, date palm and *Ocotea obtusata*. Sequencing on MinION Nanopore flow cells yielded from 3.3 to 25.3 Gb with reads N50 values ranging from 15.4 to 31.3 Kb.

DOI

dx.doi.org/10.17504/protocols.io.bu3vnyn6

PROTOCOL CITATION

Julien Serret, marie.couderc, Cedric Mariac, Laurencealbar, Francois Sabot 2021. From low cost plant HMW DNA extraction to MinION sequencing. **protocols.io**

https://dx.doi.org/10.17504/protocols.io.bu3vnyn6

KEYWORDS

HMW DNA extraction, tropical plant, Nanopore

LICENSE

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

CREATED

May 17, 2021

LAST MODIFIED

Jul 01, 2021

PROTOCOL INTEGER ID

50005

Plant materiel sampling 10s

1 Collect up to 5 g of fresh young leaves in a 50ml clean tube.
Grind sample with liquid nitrogen, mortar and pestel to a fine powder.

An analytical grinder (A15, IKA, Germany) can also be used for $2x \odot 00:00:10$.

Tissue lysis 3h

3r Add **□15 mL** of freshly prepared MATAB lysis buffer (100mM Tris pH8, 1.4M NaCl, 20mM EDTA ph8, 1% PEG6000, 2% MATAB, 1mM DTT).

Homogenize slowly by inversion.

Citation: Julien Serret, marie.couderc, Cedric Mariac, Laurencealbar, Francois Sabot (07/01/2021). From low cost plant HMW DNA extraction to MinION sequencing. https://dx.doi.org/10.17504/protocols.io.bu3ynyn6

Incubate at $~~0.65~^{\circ}C~$ for ~~0.1:30:00~ and mix by gentle inversion every ~~0.0:15:00~.

DNA purification 1h 30m

3

 Chloroform:Isoamyl alcohol 24:1 Sigma

1h 30m

Add **15 mL** of

Aldrich Catalog #C0549

and homogenize slowly

manually or with horizontal shaker 🗁 5 rpm, Room temperature , 00:12:00 .

Centrifuge **34000 rpm, 20°C, 00:20:00** and carefully transfer the supernatant to a clean 50 ml tube by using a 1000µl pipette tip cut at the extremity.

Optionnal:

If the supernatant is not clear, add 114 mL of

Aldrich Catalog #C0549

and agitate slowly manually or with

horizontal shaker 🚐 **5 rpm, Room temperature , 00:12:00** .

Centrifuge **4000** rpm, 20°C, 00:20:00 and carefully transfer the supernatant to a clean 50 ml tube by using a 1000µl pipette tip cut at the extremity.

Add 16 µl of 4mg/ml Promega Catalog #A7973

, slowly homogenize and incubate

© 00:30:00 at **§ Room temperature** .

 Chloroform:Isoamyl alcohol 24:1 Sigma

Add 13 mL of Aldrich Catalog #C0549

and agitate slowly

manually or with horizontal shaker \$\to\$5 rpm, Room temperature, 00:12:00 .

Centrifuge **4000 rpm, 20°C, 00:20:00** and carefully transfer the supernatant to a clean 50 ml tube by using a 1000µl pipette tip cut at the extremity..



Clear supernatant after centrifugation

DNA precipitation

15m

15m

4 /

protocols.io
2
07/01/2021

Citation: Julien Serret, marie.couderc, Cedric Mariac, Laurencealbar, Francois Sabot (07/01/2021). From low cost plant HMW DNA extraction to MinION sequencing. https://dx.doi.org/10.17504/protocols.io.bu3vnyn6

Add [M]10 % volume of 3M Sodium acetate pH5.2 and [M]70 % volume of

Aldrich Catalog #190764

Homogenize by very slowly inverting the tube until DNA precipitate appears.



DNA precipitate appears after homogeneization

Glass hook DNA and transfer into a 2 ml Eppendorf tube containing 1 ml 70% EtOH.

Then, air dry the DNA precipitate © 00:02:00 .

Transfer the DNA precipitate into $\Box 300 \ \mu I$ of ultrapure water in a 1.5ml Eppendorf tube.

Let the DNA resuspend **Overnight** at § 4 °C

DNA clean-up 15m

5 15m

To avoid DNA shearing, always cut tip extremities using a clean razor blade before pipetting.

Resuspend the AMPure XP magnetic beads equilibrated at room temperature by vortexing.

In a 2ml Eppendorf tube, add **□150 μl** of **⊗** AMPure XP magnetic beads to **□150 μl** of DNA.

Homogenize by gently flicking the tube and incubate \bigcirc **00:10:00** at $\$ **Room temperature**.

Spin down and pellet on the magnet.

Carrefully pipette off the supernatant and wash twice with $\Box 500 \ \mu I$ of fresh 70% ethanol.

Remove the tube from the magnet and add $=150 \mu l$ of ultrapure water.

Incubate at § 65 °C until the beads are completely resuspended (approximately 2x © 00:00:30).

Help resuspension by gently flicking the tube.

DNA quantification

6 Quantify 1µl of DNA using a Qubit fluorometer.

Check HMW using Pulsed-Field Gel Electrophoresis

7 Molecular weight of extracted DNA was assessed by PFGE by loading 20 μl of DNA (21.5 μg to 25.5 μg of

protocols.io
3
07/01/2021

Citation: Julien Serret, marie.couderc, Cedric Mariac, Laurencealbar, Francois Sabot (07/01/2021). From low cost plant HMW DNA extraction to MinION sequencing. https://dx.doi.org/10.17504/protocols.io.bu3vnyn6

□ Lambda Ladder PFG Marker - 50 gel lanes New England

into 1% agarose gel


Biolabs Catalog #N0340S

and using the following parameters for migration:

Pulse time: initial = 5, final = 120

Run time = 18 h V/cm = 5 Angle = 120 Temp = 14°

mA end of run = 255



Short read elimination

8 Perform short read elimination with a 25Kb cut-off by following the Circulomics SRE kit (SKUSS-100-101-01) instructions.

Incubate **Overnight** at § 4 °C in elution buffer before Qubit quantification and library preparation.

Citation: Julien Serret, marie.couderc, Cedric Mariac, Laurencealbar, Francois Sabot (07/01/2021). From low cost plant HMW DNA extraction to MinION sequencing. https://dx.doi.org/10.17504/protocols.io.bu3vnyn6

```
SQK-LSK109 library preparation
                                          23m
       SQK-LSK109 library preparation is performed according to
        ⊠Ligation Sequencing Kit Oxford Nanopore
        Technologies Catalog #SQK-LSK109
                                                                                                protocol with several
        modifications:
                                                                                                             25m 45s
                      DNA repair & end-prep
                       In a 1.5ml Eppendorf DNA LoBind tube mix:
                        □47 μl DNA sample (9μg of extracted DNA with volume adjusted with 50/50 Ultrapure water/TE
                        ■3.5 µl NEBNext FFPE DNA Repair Buffer
                                ■ NEBNext FFPE DNA Repair Mix - 24 rxns New England
                        ■2 μl Biolabs Catalog #M6630S
                        ■3.5 µl Ultra II End-prep Reaction Buffer
                        □3 µl Ultra II End-prep Enzyme Mix
                       Mix by gently flicking the tube, and spin down.
                       Using a thermal cycler, incubate at § 20 °C for © 00:08:00 and § 65 °C for © 00:05:00 .
                       Resuspend the AMPure XP magnetic beads equilibrated at room temperature by vortexing.
                       Add ⊒50 µI of ⊠AMPure XP magnetic beads to the end-prep reaction and mix by gently flicking
                       the tube.
                       Incubate © 00:10:00 at § Room temperature.
                       Meanwhile, prepare 500 µl of 70% ethanol using nuclease-free water.
                       After the incubation, spin down the sample and pellet on a magnet. Keep the tube on the magnet, and
                       pipette off the supernatant.
                       Wash the beads twice with 200 µl of freshly-prepared 70% ethanol.
                       Spin down and place the tube back on the magnet to pipette off the residual ethanol.
                       Remove the tube from the magnet and resuspend the pellet in \Box 62 \mu I nuclease-free water.
                       Incubate © 00:02:00 at & Room temperature and © 00:00:30 at & 65 °C . Gently flick the
                       tube and incubate © 00:00:15 more at § 65 °C .
                       Pellet the beads on a magnet until the eluate is clear and colourless.
                       Remove and retain \Box 62 \mu I of eluate into a clean 1.5ml Eppendorf DNA LoBind tube.
                       Quantify 11 µl of eluted sample using a Qubit fluorometer.
                                                                                                                 38m
               9.2 Adapter ligation
                       In a 1.5ml Eppendorf DNA LoBind tube, mix:
                       □61 µl DNA sample from the previous step
                       ■25 µl Ligation Buffer (LNB)
                       □10 µl NEBNext Quick T4 DNA Ligase
                       ■5 µl Adapter Mix (AMX)
                       Mix by gently flicking the tube, and spin down.
                       Incubate the reaction for © 00:18:00 at § 20 °C
```

```
Add 50 µl of AMPure XP magnetic beads to the end-prep reaction and mix by gently flicking
                        Incubate © 00:10:00 at & Room temperature.
                        Spin down the sample and pellet on a magnet. Keep the tube on the magnet, and pipette off the
                        supernatant.
                        Wash the beads by adding 250 µl of Long Fragment Buffer (LFB) at room temperature. Remove
                        the supernatant and repeat the wash step.
                        Spin down and place the tube back on the magnet to pipette off the residual LFB.
                        Remove the tube from the magnet and resuspend the pellet in \Box 16 \mu I of Elution Buffer (EB).
                        Incubate © 00:05:00 at & Room temperature and © 00:05:00 at & 37 °C.
                        Pellet the beads on a magnet until the eluate is clear and colourless.
                        Remove and retain 16 µl of eluate into a clean 0.5ml Eppendorf DNA LoBind tube.
                        Quantify \square 1 \mu I of eluted sample using a Qubit fluorometer.
MinION sequencing
                                 5m
 10
        Split the 16µl library into two 8µl in 0.5ml Eppendorf DNA LoBind tube. Store one tube at 8 4 °C until use.
                                                                                                                       5m
               10.1
                       Day 1 - First Load
                        In the second tube, add to the 8µl library:
                        ■4 µl Elution buffer (EB)
                        ■37.5 µl Sequencing buffer (SQB)
                        25.5 μl Loading beads (LB), mixed immediately before use.
                        Using MinION mk1C device, perform the flow cell check. (FLO-MIN106D - Spot-ON Flow Cell R9 version)
                        Prepare the priming mix by adding 30 µl of Flush tether (FLT) directly into a fresh Flush buffer
                        (FB) tube.
                        Mix by vortexing.
                        After opening the priming port, check for a small air bubble under the cover. Draw back a small volume
                        remove any bubbles (a few µl):
                        - Set a P1000 pipette to 200 μl
                        - Insert the tip into the priming port
                        - Turn the wheel until the dial shows 220-230 µl, or until you can see a small volume of buffer entering
                        the
                        pipette tip.
                        Load 2800 μl of the priming mix into the flow cell via the priming port, avoiding the introduction of
                        bubbles. Wait for © 00:05:00.
                        Remove again any bubbles:
                        - Set a P1000 pipette to 200 μl
```

Resuspend the & Room temperature equilibrated & AMPure XP magnetic beads by vortexing.

- Insert the tip into the priming port
- Turn the wheel until the dial shows 220-230 $\mu\text{l},$ or until you can see a small volume of buffer entering the

pipette tip.

Gently open the SpotON sample port.

Load an additional 200 µl of the priming mix into the still open priming port.

Mix the prepared library gently by pipetting up and down just prior to loading.

Slowly, add $-75 \, \mu l$ of the library into the SpotON sample port.

Make sure the priming port is still open during this step and the library should easily fall into the sample port.

Close the priming port and replace the SpotON sample port cover.

Close the lid of the MinION device.

Start the sequencing experiment by setting a 96h run.

10.2 Day 3 - Second Load

After 48h running, pause the sequencing run.

Perform the flow cell washing step according to the ONT protocol (EXP-WSH003).

The wash kit allows to revert "unavailable pores" into "active pores".

This procedure provides the opportunity to maximise the flow cell yield.

At the end of this protocol, re-prime the flow cell as indicated in the 10.1 step.

In the 8µl library tube stored at 4°C, add the following:

□4 μl Elution buffer (EB)

■37.5 µl Sequencing buffer (SQB)

25.5 μl Loading beads (LB), mixed immediately before use.

Load on the flow cell as the 10.1 step.

Resume the sequencing run.

10.3


After 72h running, if translocation speed falls below 250 bases per seconde, pause the run and refuel:

After opening the priming port, check for a small air bubble under the cover. Draw back a small volume to

remove any bubbles (a few μ I):

- Set a P1000 pipette to 200 µl
- Insert the tip into the priming port
- Turn the wheel until the dial shows 220-230 $\mu\text{l},$ or until you can see a small volume of buffer entering the pipette tip.

 Load 150 µl of Flush Buffer (FB). Close the priming port and resume the run.



Mux scan result.

Visualisation of the reverting of unvailable pores into single pores after performing the wash step after 2 days.

Results

11

Species	Sample	Flow cell ID	SRE treatment	Number of reads	N50 reads	Median reads	Mean quality	Number of nucleotides sequenced
Oryza barthii	B88	FC1	Yes	4,90E+05	23 613,00	14 779,00	10,70	8,26E+09
Oryza barthii	TB65	FC2	No	2,09E+06	17 226,00	1 805,00	9,80	1,21E+10
Oryza barthii	Ob546	FC3	Yes	3,72E+05	28 222,00	15 865,00	10,60	7,15E+09
Oryza barthii	Ob569	FC4	No	1,22E+06	23 393,00	3 728,00	10,10	1,20E+10
Oryza glaberrima	Og20	FC5	Yes	4,77E+05	29 040,00	15 192,00	10,90	9,23E+09
0	Og132_MG12	FC6	Yes	4,92E+05	28 339,00	14 483,00	10,70	8,96E+09
Oryza glaberrima			Yes	1,25E+05	25 522,00	14 119,00	10,40	2,15E+09
On the state of the state of	Tog5672	FC7	No	1,87E+06	15 467,00	857,00	10,00	6,22E+09
Oryza glaberrima			No	7,40E+05	16 967,00	864,00	9,10	2,69E+09
0	Tog7291	FC8	No	7,05E+05	21 544,00	3 438,00	10,00	6,12E+09
Oryza glaberrima			No	5,31E+05	16 276,00	3 010,00	10,20	3,75E+09
Oryza sativa	ChomrongDanh	FC9	No	1,09E+06	28 860,00	2 356,00	10,40	1,01E+10
Oryza sativa	DJ123	FC10	Yes	7,25E+05	23 913,00	13 554,00	10,60	1,17E+10
Oryza Saliva			Yes	2,95E+05	17 083,00	10 385,50	10,40	3,57E+09
Oryza sativa	IUPLR17	FC11	Yes	3,56E+05	31 321,00	13 871,00	10,40	6,59E+09
Oryza sativa	Llanura11	FC12	Yes	8,57E+05	25 609,00	14 692,00	10,80	1,52E+10
Oryza sativa	Nerica4	FC13	No	1,51E+06	24 898,00	2 618,00	9,90	1,29E+10
0	NericaL19	FC14	No	5,81E+05	24 116,00	1 281,00	9,20	3,36E+09
Oryza sativa		FC15	Yes	5,46E+05	26 490,00	13 457,00	10,70	9,18E+09
Oryza sativa	Sahel108	FC16	No	1,86E+06	18 414,00	5 169,00	10,10	1,75E+10
Oryza sativa	Tequing	FC17	Yes	5,77E+05	28 130,00	14 673,00	10,60	1,07E+10
Paspalum notatum	Q4117	FC18	Yes	2,02E+06	21 655.00	8 170.00	10.90	2.53E+10

Output illustration of different species sequecing. (SQK-LSK109, Flow cell R9 version, minION mk1c)