

achary R Healy<sup>1</sup>, David Murdoch<sup>1</sup>, Alicia Cooper-Volkheimer<sup>1</sup>

Duke University, Division of Pulmonary and Critical Care Medicine

Cellular Senescence Network (SenNet) Method Development Community

AUG 17, 2023



valerie.bekker



#### **ABSTRACT**

This protocol describes the Intracellular Staining (ICS) Senescence Flow Cytometry Panel



#### **MATERIALS**

#### Reagents & Materials:

s.io.rm7vzxxk5gx1/v1

**Protocol Citation:** Zachary ■ **BSB Plus:**BD Cat #566385 R Healy, David Murdoch, Alicia Cooper-Volkheimer 2023. U54 SCENT Intracellular Staining (ICS) Senescence Flow Cytometry Panel. **protocols.io** 

https://dx.doi.org/10.17504/p rotocols.io.rm7vzxxk5gx1/v1

Pipettes and Tips for 1-1000uL dx.doi.org/10.17504/protocol ■ 96 Well Round Bottom Plates: Costar Cat #3799

■ Bullet Tubes: Costar Cat #4401

TruStain FcX: BioLegend Cat #422302

■ Monensin: BD Cat # 51-2092KZ, Store undiluted at 4°C.

GolgiPlug - Brefeldin A Solution ("BFA"): BD Cat #555029, Store @ 4°C

■ **dPBS:** Invitrogen Cat #: 41190-250

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's working

Created: Aug 17, 2023

Last Modified: Aug 17,

2023

**PROTOCOL** integer ID:

86602

# **FBS Aliquot Prep**

- **1 FBS** (hiFBS): Gemini Bio Products Cat #100-106 1L Prepare FBS Aliquots:
  - 1.1 Thaw heat-inactivated FBS (hiFBS):
    - Thaw a 500mL Bottle of FBS at 4°C. This may require more than overnight so the 500mL Bottle may be removed 2 or 3 days prior to use. Do not leave the FBS at room temperature overnight.
  - 1.2 Aliquot the 500mL FBS Bottle in 50mL aliquots (a total of ten 50mL hi-FBS Aliquots)
  - 1.3 Label the aliquots with Batch#, Expiration Date, Aliquot Date
  - 1.4 Store 50mL aliquots @ -20°C until expiration date or for up to 2 freeze/thaw cycles

#### **FACS Wash**

- 2 FACS Wash w/ EDTA (D-PBS with 0.5% FBS + 2 mM EDTA): Invitrogen Cat # 41190-250
- 2.1 Remove 4.5mL PBS from a 500mL bottle

2.2 Add 2.5mL of thawed FBS 2.3 Add 2mL of 0.5M EDTA solution (Catalog #: E7889-100ML) 2.4 Label the bottle with preparer's initials and expiration date (one month from preparation) 2.5 Store @ 4°C Pen-Strep-Glut (PSG) 3 Pen-Strep-Glut (PSG) (L-Glutamine-Penicillin-Streptomycin Soln): Sigma Cat#: G6784-100ML 3.1 Thaw 100mL bottle 3.2 Aliquot into 10mL into 15mL conicals (total of ten 15mL conicals)

https://dx.doi.org/10.17504/protocols.io.rm7vzxxk5gx1/v1

Label the aliquots with Batch#, Expiration Date, Aliquot Date

3.3

**3.4** Store @ -20°C

# **R10FBS Media Preparation**

4	R10FBS Media	Preparation (	("R10")

- **4.1** Remove 55mL RPMI from a 500mL bottle of RPMI
- 4.2 Add 50mL aliquot of thawed, hiFBS
- 4.3 Add 5mL aliquot of thawed Pen-Strep-Glut
- **4.4** Label the bottle with preparer's initials and expiration date (one month from preparation)

# Cytofix/Cytoperm

5 Cytotix/Cytoperin Solution (YOX) with Golgistop (monensin): ED Biosciences Cat # 554715

Kit Contents:

■ 125mL 10X Perm/Wash Buffer

- 100mL Cytofix Solution
- 0.7mL GolgiStop (monensin)

#### To prepare 1X Perm Wash:

1. Dilute 10X BD Perm/Wash buffer in distilled H2O to make a 1X solution prior to use

# **Formaldehyde Solution**

6 1% Formaldehyde Solution ("1% Fix") ("PFA")

#### Reagents:

- 10% Formalin
- PBS
- 6.1 Add 5 mL 10% Formalin to a sterile 50 mL centrifuge conical tube
- **6.2** Add 45 mL PBS
- 6.3 Label the bottle with reagent name, initials & expiration date (one month from preparation)
- **6.4** Store 1% Fix at Room Temperature (18-25°C) for up 1 month

# **PepMixes**

- 7 PepMixes:
  - PepMix CEFX Ultra SuperStim Pool MHC-II Subset, JPT Technologies Cat #:PM-CEFX-3
  - PepMix CEF Pool (extended), JPT Technologies Cat #: PM-CEF-E-1
- 7.1 Resuspend peptide pellet [25ug] in 50uL of DMSO [500ug/mL]

- Add 10uL DMSO at a time, with vortexing to resuspend
- 7.2 Aliquot and store at -20°C until day of use
- 7.3 On day of use, use 0.45uL per test

### **Protocol**

#### 8 Overview

<u>Day 1:</u> Thaw cells and distribute to 2 plates. Rest plates at 37C/5% CO2 for >6 hours <u>Overnight:</u> Stim for 6 hours

<u>Day 2:</u> 1 Stim + 1 Unstim plate stain for surface and ICS then acquire flow data Time experiment steps according to lab and anticipated acquisition schedule

#### 8.1 <u>Day 1 – Thawing</u>

- 1. Prepare 20ml of R10 in 50mL conical tube per sample (1-4 vials per tube)
- 2. Warm the R10 for 30 min at 37C prior to use
- 3. Place cryovials in a 37C bath for 3-5 sec at a time. Withdraw, examine and repeat (usually 3-4 rounds) until small, pea-sized amount of ice remains
- 4. Spray with 70% EtOH and wipe off before returning to the hood
- 5. To each cryovial, add 1ml of R10 dropwise to each cryovial
- 6. Transfer the 2ml PBMC sample from the cryovials into the 50ml conicals
- 7. Invert 3x to mix
- 8. Centrifuge at 350g for 10 min
- 9. Pour off the supernatant, do not shake to allow some volume to remain

- 10. Gently swirl the 50mL conical in remaining volume to loosen pellet
- 11. Add 10mL pre-warmed R10 and resuspend by pipetting 10 times. Mix sample carefully but thoroughly to break up any cell clumps.
- 12. Centrifuge at 350g for 10 min
- 13. Pour off the supernatant, do not shake to allow some volume to remain
- 14. Gently swirl the 50mL conical in remaining volume to loosen pellet
- 15. Add 10mL pre-warmed R10 and resuspend by pipetting 10 times. Mix sample carefully but thoroughly to break up any cell clumps

#### 16. **COUNTING & VIABILITY:**

- a) Perform a cell count using the Countess II to determine PBMC viability & recovery
- b) Add 10uL Trypan Blue to well of mixing plate
- c) Add 10uL Cells, pipette up and down
- d) Remove 10uL of cell mix and dispense into Countess slide
- e) Wait 30 sec
- f) Calculate total cells and viability
- g) Insert into Countess II to calculate total cells and viability

#### 8.2 Overnight – Stim

- 1. Cells have been plated at 2x10<sup>6</sup> cells/well in 200uL R10 and rested for >6hours
- 2. For all wells (Stim and Unstim), add BFA/Monensin at
- a. BFA: 0.23 uL per test
- b. Monensin: 0.16 uL per test
- c. CD107a antibody: 0.313uL per test
- 3. For Stim plates, add CEF PepMix at
- a. PepMix CEFX Ultra SuperStim Pool MHC-II Subset: 0.45uL per test
- b. PepMix CEF Pool (extended): 0.45uL per test
- 4. Gently plate by vortexing at medium speed for 3 sec
- 5. Incubate cells at 37° C, 5% CO2 for 6 hours
- 6. At 6 hours (9am), wrap plate in Parafilm and place in 4C refrigerator and proceed with staining

A   B   C   D	
---------------	--

A	В	С	D
Stim Mixes	# Tubes:	16	16
	uL per test	Stim	UnStim
BFA	0.23	4.232	4.232
Monensin	0.16	2.944	2.944
CEFX ultra MHC II	0.45	8.28	-
CEF Pool Ext (MHC I)	0.45	8.28	-
CD107a	0.313	5.7592	5.7592
R10	23.5	432.4	432.4
Total	25.103		
Add 25uL Mix to 200uL Cells for total 225uL			

## 8.3 <u>Day 2 - Stain</u>

- Keep everything as cold as much as possible
- Keep everything covered as much as possible; work in dark or incandescent light

#### Surface staining:

- 1. Remove plates from refrigerator
- 2. Centrifuge 400g x 3 min
- 3. Flick off supernatant and vortex gently
- 4. Add 47.5uL FACS wash to each well
- 5. Add 2.5uL TruStain FCX blocking to each well
- 6. Incubate 4C for 15 min
- 7. Prepare Surface Stain Mix in PBS with 10uL BSB Plus, set aside

- 8. Add 50uL of Surface Stain Mix in PBS to each well and gently mix
- 9. Incubate in 4C fridge for 30 min, covered in foil
- 10. Add 100uL cold FACS wash & mix by pipetting up and down x3
- 11. Centrifuge 400g x 3 min
- 12. Flick off supernatant and vortex gently
- 13. Add 200uL cold FACS wash to each well
- 14. Centrifuge 400g x 3 min
- 15. Flick off supernatant and vortex gently

#### Intracellular cytokine staining (ICS):

Surface / ICS Stain Steps:							
Reagent	Init						
Surf Stain Mix	50uL						
FACS Wash	100uL						
FACS Wash	200uL						
CytoFix/CytoPerm	100uL						
1X Perm Wash	100uL						
1X Perm Wash	200uL						
ICS Stain Mix	50uL						
1X Perm Wash	150uL						
1X Perm Wash	200uL						
1X Perm Wash	200uL						
1% PFA	200uL						

- 16. Add 100uL BD Cytofix/Cytoperm solution to each well.
- a. **NOTE:** mix well with cells
- 17. Incubate on ice for 20 min, covered in foil
- a. **NOTE:** do not over-incubate (Cytofix is toxic to cells)
- 18. Prepare ICS Stain Mix in 1X Perm Wash with 10uL BSB Plus, set aside
- 19. Add 100uL cold 1X Perm Wash solution

- 20. Centrifuge 400g x 3 min
- 21. Flick off supernatant and vortex gently
- 22. Add 200uL cold 1X Perm Wash solution
- 23. Centrifuge 400g x 3 min
- 24. Flick off supernatant and vortex gently
- 25. Add 50uL of the ICS Mix in Perm Wash to each well and gently mix
- 26. Incubate at 4° in refrigerator x 30 min, covered in foil
- 27. Add 150uL cold 1X Perm Wash solution
- 28. Centrifuge 400g x 3 min
- 29. Flick off supernatant and vortex gently
- 30. Add 200uL cold 1X Perm Wash solution
- 31. Centrifuge 400g x 3 min
- 32. Flick off supernatant and vortex gently
- 33. Add 200uL cold 1X Perm Wash solution
- 34. Centrifuge 400g x 3 min
- 35. Flick off supernatant and vortex gently
- 36. Add 200uL 1% PFA
- 37. Transfer samples to bullet tubes, cover with aluminum foil, store at 4°C, & acquire within 6 hours

Α	В	С	D	E	F	G	Н	I	J	
Staining Step	Specific ity	Fluor	Vendor	Cat#	Clone	Isotype	Conc ug/m L	MRA uL	Titere d uL	

A	В	С	D	E	F	G	Н	I	J
Stim	CD107	PE	BL	328608	H4A3	lgG1 k	400	5	0.313
Surface	KLRG1	BV421	BL	367706	SA231A 2	lgG2a k	100	5	1.25
Surface	CD45R A	Pacific Blue	BL	304118	H100	lgG2b k	500	1	0.5
Surface	CD8	BV570	BL	301038	RPA- T8	lgG1 k	100	5	2.5
Surface	CD127	BV605	BL	351334	A019D5	lgG1 k	100	5	2.5
Surface	CD56	BV650	BL	362532	5.1H11	lgG1 k	100	5	1.25
Surface	CCR7	BV711	BL	353228	G043H7	lgG2a k	100	5	5
Surface	CD27	BV750	BL	302850	0323	IgG1 k	100	5	2.5
Surface	PD1	VioBright 515	Milten yi	130- 120-386	REA116 5	rHu IgG1		2	2
Surface	NKG2A	PE- Vio615	Milten yi	130- 120-035	REA110	rHu IgG1		2	1
Surface	CD16	PerCP- Cy5.5	BL	302028	3G8	lgG1 k	200	5	2.5
Surface	CD38	PerCp- eFluor71 0	TF	46- 0388-42	НВ7	IgG1 k	120	5	5
Surface	CD19	SparkNIR 685	BL	302270	HIB19	IgG1 k	100	5	1.25
Surface	CD14	SparkNIR 685	BL	367150	63D3	lgG1 k	200	5	0.156
Surface	Zombie nIR	Zombie nIR	BL	423105	-	-	-	1	0.4

A	В	С	D	E	F	G	Н	I	J
Surface	HLA- DR	APC- Fire810	BL	307674	L243	lgG2a k	50	5	2.5
ICS	CD3	BV480	BD	566105	UCHT1	lgG1 k	200	5	2.5
ICS	CD4	PerCP	BD	550631	L200	lgG1 k	6.3	20	5
ICS	IFN-g	PE-Cy7	BL	502528	4S.B3	lgG1 k	50	5	0.313
ICS	IL-2	APC	BL	500310	MQ1- 17H12	Rat IgG2a k	25	5	0.313
ICS	TNFa	Alexa700	BL	502928	MAb11	lgG1 k	100	5	0.63