

Sep 25, 2024



Protocol for Gibson Assembly

DOI

dx.doi.org/10.17504/protocols.io.n92ld8m48v5b/v1

Carolina Lopez¹

¹Washington University



Cecilia Escudero

wustl





DOI: dx.doi.org/10.17504/protocols.io.n92ld8m48v5b/v1

Protocol Citation: Carolina Lopez 2024. Protocol for Gibson Assembly. protocols.io

https://dx.doi.org/10.17504/protocols.io.n92ld8m48v5b/v1

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's

working

Created: May 28, 2024

Last Modified: September 25, 2024

Protocol Integer ID: 100759

Abstract

Procedure for cloning using Gibson Assembly



Isolation of Purified Vector:

Gibson Assembly technology uses homologous recombination to assemble adjacent DNA fragments that share end-terminal homology. The optimal length of the homologous fragment ends region depends on

the number and length of the fragments in the assembly reaction.

2 1. Digest Vector with Restriction Enzymes:

Component	Volume (uL)
DNA Plasmid	X uL for 10 ug of Plasmid
10x Cutsmart Buffer	5
Enzyme 1	2.5
Enzyme 2	2.5
Nuclease Free H20	40-X

- 2. Incubate for 303:00:00 at 37°C.
- 3. Add \perp 10 µL of 6x loading buffer to reaction
- 4. Make 1% low melt-agarose gel.
 - a) Mix 1 g of Agar with 🚨 100 mL of TAE Buffer.
 - b) Microwave to boil agarose and let cool until you can touch bottle, but gel is not solid.
 - c) Add 🚨 1.5 µL of EtBr to agarose and pour into DNA gel mold with 10 well comb.
 - d) Let gel solidify.
- 5. Load $\stackrel{\perp}{_}$ 60 μL of reaction into well of gel
- 6. Run gel for 00:45:00 at 120V.
- 7. Visualize band with UV light and cut out section of gel with band and place in tube.
- 8. Purify Band from gel with QIAquick Gel Extraction kit (Qiagen, 28704)
 - a) Weigh gel fragment in \bot 1.5 mL tube (this will be volume with 100mg gel = 100uL)
 - b) Add 3 volumes of Buffer QG to 1 volume gel.
 - c) Incubate at 🖁 50 °C for 🚫 00:10:00 . Vortex every 2-3 min to help break up gel.
 - d) Add 1 gel volume of isopropanol to the sample and mix.
 - e) Place Qiaquick column into collection tube and add sample mixture to column.
 - f) Let incubate for (5) 00:01:00 .
 - g) Centrifuge for 00:01:00 at max speed at Room temperature. Discard Flowthrough.
 - h) Add \perp 750 μ L of PE buffer to column.
 - i) Centrifuge for 00:01:00 at max speed at Room temperature. Discard Flowthrough.

4h

- j) Centrifuge for 00:01:00 at max speed at Room temperature to dry column.
- k) Place column into new labeled \perp 1.5 mL tube and add \perp 35 μ L of NF H₂0.
- I) Centrifuge for 00:01:00 at max speed at Room temperature to elute DNA.
- m) Measure DNA concentration with the Nanodrop.
- n) Vector Concentration:

Generation of PCR Product:

3 1. Set up PCR Reaction:

25m

	Volume (uL)
SpfI Fwd (10uM)	1
NotI Rev (10uM)	1
dNTPs	1
Plasmid (20ng)	1
Buffer	5
MgCl2	3
H2O	38

2. Run PCR Conditions:

- a) \$\colon 95 \circ \circ \circ 00:02:00
- b) \$\\ \ 95 \circ\$ 00:00:30
- c) \$\cdot 60 \cdot \cdot \cdot \cdot 00:00:30
- d) \$\ 72 \circ \) \(\frac{1}{2} \) 00:02:00
- e) Repeat step 2-4 35 times
- f) 🖁 72 °C **(*)** 00:10:00
- g) 🖁 4 °C hold

1% agarose gel to make sure there is a correct PCR product.

- 4. Add \perp 5 µL of Cutsmart buffer and \perp 1 µL of DpnI to the reaction and incubate at
 - \$\cdot 37 °C for ♠\cdot 00:05:00 \cdot \c
- 5. Purify Band from gel with QIAquick Gel Extraction kit (Qiagen, 28704)
 - a) Add \perp 135 µL of Buffer QG to \perp 45 µL PCR reaction.
 - b) Add \perp 45 µL of isopropanol to the sample and mix.
 - c) Place Qiaquick column into collection tube and add sample mixture to column.
 - d) Let incubate for 00:01:00 .

- e) Centrifuge for 00:01:00 at max speed at Room temperature. Discard Flowthrough.
- f) Add 🚨 750 µL of PE buffer to column.
- g) Centrifuge for 00:01:00 at max speed at Room temperature. Discard Flowthrough.
- h) Centrifuge for 00:01:00 at max speed at Room temperature to dry column.
- i) Place column into new labeled \perp 1.5 mL tube and add \perp 35 μ L of NF H₂0.
- j) Centrifuge for 600:01:00 at max speed at Room temperature to elute DNA.
- k) Measure DNA concentration with the Nanodrop.
- I) PCR Product Concentration:

Gibson Assembly with HIFI DNA Assembly Mix (NEB, E2621S).

2h 24m

4 1. Calculate the molar ratios of Vector and PCR product used

2h 24m

- a) https://nebiocalculator.neb.com/#!/ligation
- b) I usually use 1 vector: 2 PCR ratio
- 2. Mix

Component	Volume(uL)	
Vector (50ng)	X	
PCR Insert	Y	
NEB builder	10 uL	
H20	10-X-Y	
Total Volume	20uL	

A	В	С	D	E	F	G
Component	Length of D NA (bp)	Molar ratio	ng of DNA	Volume of 50ng/ul sol ution		
Vector	3015	1	50	1 ul		
PCR Fragm ent	500	2	16.58	0.33 ul		
H20				8.67 ul		

- 3. Incubate for (5) 01:00:00 at \$\colon 50 \cdot 0 \cdot 0.
- 4. Transform Product into E. coli
 - a) Add \perp 2 μ L of product to \perp 50 μ L of TOP10 cells.
 - b) Incubate for 00:20:00 on ice.
 - c) Heat shock bacteria in 42 °C waterbath for 00:01:00 .



- d) Incubate on Ice for 👏 00:03:00 .
- e) Add \perp 100 μ L of SOC media and shake in warm room for \bigcirc 01:00:00 .
- f) Plate bacteria onto LB-Antibiotic Plate. And incubate overnight in 🖁 37 °C warm room.