

Oct 02, 2024



# High-throughput Smart-seq3

DOI

#### dx.doi.org/10.17504/protocols.io.ewov196jolr2/v1

Kai-Hui Sun<sup>1</sup>, Hsiu-Chun Chuang<sup>1</sup>

<sup>1</sup>Gilead



#### Kai-Hui Sun

Gilead, Gilead

# OPEN ACCESS



DOI: dx.doi.org/10.17504/protocols.io.ewov196jolr2/v1

Protocol Citation: Kai-Hui Sun, Hsiu-Chun Chuang 2024. High-throughput Smart-seq3. protocols.io

https://dx.doi.org/10.17504/protocols.io.ewov196jolr2/v1

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits

unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's

working

Created: September 25, 2024

Last Modified: October 02, 2024

Protocol Integer ID: 108293

Keywords: single-cell RNA sequencing, single-cell TCR sequencing, smart-seq3, high-throughput smart-seq3

#### Abstract


We built upon the Smart-seq3 protocol to develop the high-throughput Smart-seq3 (HT Smart-seq3) workflow, an automated workflow with a detailed and optimized protocol.



### **Materials**

- List of oligos: refer to the published Smart-seq3 protocol V3 (https://www.protocols.io/view/smart-seq3-protocolbcq4ivyw.pdf)
- Details of reagents were listed in each key step.

### Protocol materials





# Single Cell Collection via FACS

Prepare Cell Lysis Buffer Master Mix on the same day as single cell collection via FACS, and keep it 3 On ice .

A	В	С	D	E
Master mix co mponent	Cat # (Vendo r)	Stock conc.	Reaction con c.	Volume (ul) p er well
Poly-ethylene glycol 8000	89510-250G-F (Sigma)	50%	5%	0.4
Triton X-100	T8787-50ML (Sigma)	10%	0.1%	0.04
Recombinant RNAse inhibit or	2313A (Takar a Bio)	40U/ul	0.5U/ul	0.05
Smart-seq3 Ol igo-dT-30VN	Integrated Dn a Technologie s (IDT)	100uM	0.5uM	0.02
dNTPs	R0182 (Therm o Fisher Scien tific)	25mM/each	0.5mM/each	0.08
Nuclease-free water	AM9930 (Invit rogen)			3.41
Total				4

- 2 Dispense 4 µL Cell Lysis Buffer Master Mix into each well of the 96-well plates using **Mantis**. Keep the plates sealed and **§** On ice prior to FACS.
- 3 Before loading the 96-well plate onto FACS, perform a quick spin-down and then sort single cells directly into wells containing Cell Lysis Buffer.
- 4 After completion of single cell collection, seal the 96-well plate, perform a quick spin-down, and place it on dry ice before transferring to storage at 4 -80 °C.

# Cell Lysis

10m

2m

5 Remove the 96-well plates from the 4 -80 °C freezer and incubate them in a thermocycler at 

10m

**Reverse Transcription** 

2h 30m



6 Prepare Reverse Transcription (RT) Master Mix, and dispense 4 1  $\mu$ L RT Master Mix into each well of the 384-well plates using Mantis.

A	В	С	D	E
Master mix comp onent	Cat # (Vendo r)	Stock conc.	Reaction con c.	Volume (ul) p er well
Tris-HCl, pH 8.3	T1083 (Tekno va)	1M	25mM	0.1
NaCl	AM9759 (Invit rogen)	1M	30mM	0.12
MgCl2	AM9530G (Invitrogen)	100mM	2.5mM	0.1
GTP	R1461 (Therm o Fisher)	100mM	1mM	0.04
Dithiothreitol (DT T)	707265ML (T hermo Fisher Scientific)	100mM	8mM	0.32
Recombinant RN Ase inhibitor	2313A (Takar a Bio)	40U/ul	0.5U/ul	0.05
Smart-seq3 TS0	Integrated Dn a Technologie s (IDT)	100uM	2uM	0.08
Maxima H-minus RT enzyme	EP0751 (Ther mo Fisher)	200U/ul	2U/ul	0.04
Nuclease-free wa ter	AM9930 (Invit rogen)			0.15
Total				1

7 After completion of cell lysis at step 5, use Integra VIAFLO to transfer the lysates from four 96well plates into one 384-well plate pre-filled with RT Master Mix at step 6, and then mix well.

1m

8 Seal the plate, perform a quick spin-down, and then incubate it in a thermocycler as follows:

2h 15m





### cDNA Amplification

2h 30m

9 Prepare **PCR Master Mix**, and keep it **&** On ice .

A	В	С	D	E
Master mix co mponent	Vendor	Stock conc.	Reaction con c.	Volume (ul)
Kapa HiFi Hot Start buffer	KK2502 (Roch e)	5X	1X	2
DNA polymera se	KK2502 (Roch e)	1U/ul	0.02U/ul	0.2
dNTPs	R0182 (Therm o Fisher Scien tific)	25mM/each	0.3mM/each	0.12
MgCl2	AM9530G (Inv itrogen)	100mM	0.5mM	0.05
Smart-seq3 fo rward primer	Integrated Dn a Technologie s (IDT)	100uM	0.5uM	0.05
Smart-seq3 re verse primer	Integrated Dn a Technologie s (IDT)	100uM	0.1uM	0.01
Nuclease-free water	AM9930 (Invit rogen)			3.57
Total				6

10 After completion of RT at step 8, perform a quick spin-down, and then dispense 4 6 µL PCR 2m Master Mix into each well of the 384-well plate using Mantis.

11 Seal the plate, perform a quick spin-down, and then incubate it in a thermocycler as follows:

2h 15m

**\$** 98 °C for **♦** 00:03:00

18-25 cycles of:

- \$ 98 °C for ♠ 00:00:20
- \$\cdot 65 °C for \cdot 00:00:30
- **\$** 72 °C for ♠ 00:04:00
- **3** 72 °C for (5) 00:05:00

Hold at 🖁 4 °C

cDNA Purification



12 Program Integra VIAFLO to perform cDNA purification as follows:

30m

- 1. Add 🚨 6 μL 🛛 🔯 Ampure XP beads Beckman Coulter Catalog #A63881 (0.6X) to each well of the 384-well plate and mix by pipetting up and down.
- 2. Incubate 00:05:00 at 8 Room temperature .
- 3. Place on magnet until the solution clears.
- 4. Remove the supernatant.
- 5. Wash twice with  $\stackrel{\blacksquare}{\bot}$  30  $\mu$ L freshly prepared 80% ethanol.
- 6. Remove the ethanol, and air dry for 00:02:00 .
- 7. Add 🚨 11 µL nuclease-free water and mix by pipetting up and down.
- 8. Incubate (5) 00:05:00 at 8 Room temperature .
- 9. Place on magnet until the solution clears.
- 10. Transfer 🚨 10 μL purified sample to a new 384-well plate.
- 11. Store at 🖁 -20 °C .

### cDNA Quantification

10m

13 Use 🔀 Qubit® dsDNA HS Assay Kit Thermo Fisher Scientific Catalog #Q32854 modified protocol to perform cDNA quantification as followed:

- 1. Prepare the **Qubit Working Solution**: Dilute the Qubit **O** dsDNA HS Reagent at a ratio of 1:200 in Qubit ® dsDNA HS Buffer
- 2. Prepare Standards: Create a series of standards at concentrations of 0, 1.25, 2.5, and 5 ng/ μL by performing serial dilutions of QubitTM 1X dsDNA HS Standard #2, which has a concentration of 10 ng/µL. This will allow for accurate quantification during the assay.
- 3. Dispense Working Solution: Using an Integra VIAFLO, dispense 34 µL of the prepared Qubit R working solution into each well of the black, flat-bottom 384-well plates (Corning, Catalog#3820)
- 4. Add **Standards**: In a separate plate, add 1 µL of each prepared **standard** to the corresponding wells. This will enable the creation of a standard curve for quantifying the cDNA concentration.
- 5. Add cDNA Samples: Add 1 µL of cDNA sample to each well of the plate containing the **Qubit** (R) working **solution**. Ensure that samples are added to the correct wells to maintain accurate results.



- 6. Measure Fluorescence: Use a **SpectraMax microplate reader** to measure the fluorescence of the samples. Set the excitation wavelength to 485 nm and the emission wavelength to 525 nm. Record the fluorescence intensity for each well.
- 7. Calculate cDNA Concentration: Analyze the fluorescence data to calculate the cDNA concentration in the samples using the standard curve generated from the known standards

### cDNA Normalization

10m

Calculate and normalize each sample to [M] 100 pg/ul using nuclease-free water as follows:

10m

- 1. Prepare a new 384-well plate for cDNA normalization by dispensing calculated volumes of nuclease-free water (diluent) into each well using **Mantis**.
- 2. Transfer 🚨 1 µL purified cDNA into this new 384-well plate prepared above.

# **Library Generation**

5m

- Use Nextera XT DNA Library Preparation Kit Illumina, Inc. Catalog #FC-131-1096 with our modified protocol to perform library generation.
- 15.1 Prepare **Tagmentation Master Mix**, and dispense Δ 3 μL into a new 384-well plate using **Mantis**.

2m

A	В	
Mater mix co mponent (Kit)	Volume (ul)	
Tagment DNA buffer (TD)	2	
Amplicon tag ment mix (AT M)	1	
Total	3	

15.2 Add Δ 1 μL normalized cDNA ([M] 100 pg/ul]) to **Tagmentation Master Mix**, and mix by pipetting up and down using **Integra VIAFLO**.

1m

15.3 Seal the plate, perform a quick spin-down, and then incubate it in a thermocycler as follows:



\$ 55 °C for (\*) 00:05:00 Hold at 4 °C

15.4 Add Add I µL Neutralize tagment buffer (NT) using Mantis, mix and perform a quick spin-5m down, followed by incubation for 60 00:05:00 at 8 Room temperature.

15.5 Dispense 🗸 3 µL | Nextera PCR Master Mix (NPM) using Mantis, followed by adding 3m ■ 2 µL UDIs (1:1 dilution) and mixing using Integra VIAFLO.

15.6 Seal the plate, perform a quick spin-down, and then incubate it in a thermocycler as follows:

9m 40s

**₽** 72 °C for **№** 00:03:00 **\$** 95 °C for ♠ 00:00:30

14 cycles of:

- \$\circ\$ 95 °C for (\circ\$) 00:00:10
- \$ 55 °C for (\*) 00:00:30
- **\$** 72 °C for ♠ 00:00:30

\$\ 72 °C for \( \cdot \) 00:05:00

Hold at 4 °C

# Pooled Library Purification

15m

16 Pool libraries with different UDIs to perform library purification as follows:

- 1. Take 🛮 🗸 2 µL from each library with a different UDI from the plates in step 15, and pool them together for purification.
- 2. Add 0.6:1 X Ampure XP beads **Beckman Coulter Catalog #**A63881 to final volume of the pooled libraries, mix by pipetting up and down.
- 3. Incubate 000:05:00 at 8 Room temperature .
- 4. Place on magnet until the solution clears.
- 5. Remove the supernatant.
- 6. Wash twice with 4 1000 µL freshly prepared 80% ethanol.
- 7. Remove the ethanol, and air dry for 00:05:00.
- 8. Add <u>A</u> 26 µL nuclease-free water and mix by pipetting up and down.
- 9. Incubate 0.00:05:00 at 8 Room temperature .
- 10. Place on magnet until the solution clears.



- 11. Transfer 4 25 µL purified sample to a new Eppendorf tube.
- 12. Store at 🖁 -20 °C .

## Library Quality Control

- 17 Measure the concentration of pooled library using
  - Qubit® dsDNA HS Assay Kit Thermo Fisher Scientific Catalog #Q32854 , and determine the size using
  - BioAnalyzer High Sensitivity Chip Agilent Technologies Catalog #5067-4626

### Sequencing

18 Sequence the pooled library on an Illumina sequencer (Illumina, San Diego, CA, USA) using paired-end (PE) 150 bp reads, with a target of 1-2 million reads per sample.

### Protocol references

- 1. Hagemann-Jensen M, Ziegenhain C, Chen P, Ramskold D, Hendriks GJ, Larsson AJM, Faridani OR, Sandberg R: Singlecell RNA counting at allele and isoform resolution using Smart-seq3. Nat Biotechnol 2020, 38(6):708-714.
- 2. Michael Hagemann-Jensen CZ, Ping Chen, Daniel Ramsköld, Gert-Jan Hendriks, Anton J.M Larsson, Omid R. Faridani, Rickard Sandberg: Smart-seq3 Protocol V.3. In. protocols.io; 2020.