

AUG 08, 2023

Preparation of soluble and insoluble mitochondrial protein fractions for mass spectrometry

Louise Uoselis¹

¹Lazarou Lab, WEHI



Louise Uoselis WEHI

ABSTRACT

Preparation of soluble and insoluble mitochondrial protein fractions from HeLa cells for mass spectrometry





Protocol Citation: Louise Uoselis 2023. Preparation of soluble and insoluble mitochondrial protein fractions for mass spectrometry. protocols.io https://protocols.io/view/prep aration-of-soluble-andinsoluble-mitochondrialcybmxsk6

License: This is an open access protocol distributed under the terms of the Creative Commons
Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's working

Created: Aug 08, 2023

Last Modified: Aug 08,

2023

PROTOCOL integer ID:

86093


25m Day 1 1 Thaw mitochondrial stocks on ice, and aliquot out one tube of A 60 µg of mitochondria for each sample. 2 10m Centrifuge samples at 10,000x rcf for 00:10:00 at 4 deg C, and carefully aspirate the supernatant 15m 3 Add A 60 µL of ice cold 0.5% TX-100 in PBS, vortex each sample for ~5 seconds, and leave samples to incubate on ice for 15 min. At the conclusion of the 00:15:00 lysis incubation, vortex each sample for ~5 sec again. 10m 4 Centrifuge the samples at 12,000x rcf for 00:10:00 at 4 deg C 5 Using a pipette, carefully remove A 57 µL of the supernatant (representing 95% of the lysis volume) and place this sample into a clean microfuge tube on ice, being sure not to disturb any pellets that have formed on the bottom of the tube. The volume removed represents the 'soluble' protein fraction. The tube containing the pellet represents the 'insoluble' protein fraction. 6 Add A 57 µL of 0.5% TX-100 in PBS to each insoluble protein fraction by pipetting on the side of the tube. Gently flick each tube to rinse the sides of the tube. 10m 7 Centrifuge the insoluble protein fractions at 12,000x rcf for 00:10:00 at 4 deg C. 8 Using a pipette, carefully remove A 57 µL of the supernatant from the insoluble protein fraction, and place into a clean microfuge tube (which will function as the waste collection tube for all samples).

9 Repeat steps 6 - 8, which will total 2 washes 10 Repeat step 6. You should now have two tubes for each sample (soluble and insoluble protein fractions), and one waste tube. 11 Thaw aliquots of recombinant Ag85A on ice, and add 180 ng of Ag85A to each insoluble protein fraction, and 🗸 171 ng of Ag85A to each soluble fraction 12 Equilibrate all samples to room temperature and then add 2x SDS solubilization buffer to a final concentration of 1x (2x: 10% w/v SDS, 200 mM HEPES pH 8.5). Vortex each samples for ~ 5 seconds to mix. 10m 13 Sonicate all samples in a waterbath sonicator set to ~21 deg C for 00:10:00 45m 14 Add TCEP to a final concentration of 10 mM and chloroacetamide to a final concentration of 40 mM to each sample, vortex each sample for ~5 seconds to mix, and incubate samples at 37 deg C for 00:45:00 (standing). NOTE: make sure chloroacetamide is made up fresh from powder 15 Acidify each sample by adding phosphoric acid to a final concentration of 1.2%/sample (ensure pH <4. More phosphoric acid can be added if the pH is not low enough at 1.2%/sample) 16 Add binding buffer (100 mM triethylammonium bicarbonate, 90% v/v methanol pH 7.1 with phosphoric acid) to each sample at a ratio of 1:7, sample volume to binding buffer. 17 Vortex each sample for ~5 sec to mix

- 18 Load A 400 µL of each sample into a S-Trap Mini column, and centrifuge at 6,500x rcf at room temperature for 30 sec. Discard the flow through. 19 Repeat step 18 until the full volume of each sample has been loaded on its column. 30s 20 Wash each column by adding A 400 µL of binding buffer, centrifuging at 6,500x rcf at room temperature for 00:00:30 , and discarding the flow through. 21 Repeat step 20 three times, for a total of 4 washes. 22 Move the columns to a 1.5 mL LoBind microfuge tube (Eppendorf) and add 🗓 125 µL digestion buffer directly to the column filter (digestion buffer: 50 mM triethylammonium bicarbonate supplemented with sequencing grade trypsin at a concentration of 1 ug trypsin to 50 ug of starting protein (which will differ between soluble and insoluble samples)). 23 30s Centrifuge samples at 1000x rcf for 00:00:30 at room temperature, and pipette the digestion buffer flow through directly back onto the column filter. Move the columns to clean 2.0 mL LoBind microfuge tubes. 24 16h Seal each sample to the LoBind microfuge tube with parafilm, and incubate samples overnight for at least (5) 16:00:00 at 37 deg C (static incubation)
- Seal each sample to the LoBind microfuge tube with parafilm, and incubate samples overnight for at least 16:00:00 at 37 deg C (static incubation)

 Day 2

 Remove the parafilm and add 80 µL of digestion buffer without trypsin (50 mM triethylammonium bicarbonate) to each sample. Centrifuge samples at 3,200x rcf for



- Add \triangle 80 μ L of 0.2% v/v formic acid to each sample, and centrifuge at 3,200x rcf for \bigcirc 00:01:00 at room temperature. Leave the flow through in the collection tube.
- 1m
- Add \triangle 80 μ L of 50% v/v acetonitrile/0.2% v/v formic acid to each sample, and centrifuge at 6,500x rcf for \bigcirc 00:01:00 .
- Remove and discard the S-Trap columns from each sample.
- 29 Lyophilise the total eluate from each sample, seal the samples with parafilm and store at -80 deg C until needed for downstream processing.