

May 09, 2024



# TAB-PAINT imaging of alpha-synuclein fibrils using Nile Red

DOI

# dx.doi.org/10.17504/protocols.io.n2bvj31mwlk5/v1

Ezra Bruggeman<sup>1</sup>

<sup>1</sup>University of Cambridge

ASAP Collaborative Rese...



# Ezra Bruggeman

University of Cambridge

# OPEN ACCESS



DOI: dx.doi.org/10.17504/protocols.io.n2bvj31mwlk5/v1

**Protocol Citation:** Ezra Bruggeman 2024. TAB-PAINT imaging of alpha-synuclein fibrils using Nile Red. **protocols.io** <a href="https://dx.doi.org/10.17504/protocols.io.n2bvj31mwlk5/v1">https://dx.doi.org/10.17504/protocols.io.n2bvj31mwlk5/v1</a>

# Manuscript citation:

POLCAM: Instant molecular orientation microscopy for the life sciences
Ezra Bruggeman, Oumeng Zhang, Lisa-Maria Needham, Markus Körbel, Sam Daly, Matthew Cheetham, Ruby Peters, Tingting Wu, Andrey S.
Klymchenko, Simon J. Davis, Ewa K. Paluch, David Klenerman, Matthew D. Lew, Kevin O'Holleran, Steven F. Lee. **bioRxiv**2023.02.07.527479, doi: <a href="https://doi.org/10.1101/2023.02.07.527479">https://doi.org/10.1101/2023.02.07.527479</a>

**License:** This is an open access protocol distributed under the terms of the <u>Creative Commons Attribution License</u>, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working
We use this protocol and it's
working

Created: January 09, 2024

Last Modified: May 09, 2024

Protocol Integer ID: 93187

**Keywords:** ASAPCRN, Single-molecule, Single molecules, Microscopy, Imaging, Fluorescence, Fluorescence microscopy, POLCAM, Nile Red, TAB-PAINT, PAINT, Alpha-synuclein fibrils



Funders Acknowledgement: Aligning Science Across Parkinson's

Grant ID: ASAP-000509

# **Abstract**

This is a protocol for the preparation of a sample of alpha-synuclein fibrils on a PLL-coated cover glass for TAB-PAINT imaging with Nile Red. This protocol was used to generate the data shown in **Figure 3** of the following publication:

■ Bruggeman *et al.*, POLCAM: Instant molecular orientation microscopy for the life sciences. bioRxiv 2023.02.07.527479 (Feb **2023**), doi: <a href="https://doi.org/10.1101/2023.02.07.527479">https://doi.org/10.1101/2023.02.07.527479</a>



# Protocol 1d 0h 55m

Prepare alpha-synuclein fibrils by diluting alpha-synuclein monomer [M] 70 micromolar (μΜ) in PBS (with 0.01% NaN<sub>3</sub>) and incubating at 37 °C in a shaker (200 rpm) for over 24:00:00 . You can store the fibrils at 4 °C for later use.

- Argon plasma clean cover glass (VWR collection, 631-0124) for 00:30:00 in a plasma cleaner (Expanded Plasma Cleaner, PDC-002, Harrick Plasma).
- 3 In the meantime:
  - Filter phosphate-buffered saline (PBS) using a 0.02 µm syringe filter (6809-1102, Whatman).
  - Dilute Nile Red in filtered PBS to a concentration of [M] 1 nanomolar (nM)

### Note

If you purchase Nile Red in solid form, we recommend preparing a 1 mM solution of Nile Red in DMSO and freezing small aliquots for later use. For each experiment, always use a new aliquot of Nile Red to prepare the 1 nM dilution, as the dye doesn't store well at low concentrations.

- 4 Create a PLL-coated sample well on the cover glass:
- 4.1 Create a sample well on the cleaned cover glass by sticking a frame-seal slide chamber (9x9 mm, SLF0201, Bio-rad) on the glass.
- 4.2 Pipet Δ 70 μL of 0.01% PLL (0.01% poly-L-lysine solution, P4707, Sigma-Aldrich) into the well and wait for 00:15:00. The PLL will coat the surface of the cover glass.

### Note

Always use a freshly thawed aliquot of PLL. You can aliquot the PLL and store it in a -80 °C freezer.

4.3 Use a pipet to remove the excess PLL from the well and immediately replace it with of filtered PBS.

15m

1d

30m



- 4.4 Use a pipet to remove the excess filtered PBS from the well and replace with 4 70 µL filtered PBS. Gently pipet up and down in the corners of the well. Repeat this step 2 more times.
- 5 Add fluorescent beads for lateral drift correction:
- 5.1 Remove the excess PBS from the well using a pipet.
- 5.2 Using a pipet, add Δ 50 μL of 0.1 μm diameter TetraSpeck Microspheres (0.1 μm, fluorescent blue/green/orange/dark red, T7279, Invitrogen) into the well.

#### Note

The concentration of TetraSpeck Microspheres (0.1 µm, fluorescent blue/green/orange/dark red, T7279, Invitrogen) will vary between batches from the vendor. You will likely need to test out a few dilutions to find the concentration that results in the right amount of microspheres per field of view.

5.3 Gently pipet up and down a few times and wait for 00:05:00.

5m

- 5.4 Use a pipet to remove the excess solution from the well and replace with 4 70 µL filtered PBS. Gently pipet up and down in the corners of the well. Repeat this step 2 more times.
- 6 Use a pipet to remove the excess PBS from the well, add \( \Delta \) 50 uL of alpha-synuclein fibrils and pipet up and down a few times in each corner of the sample well and wait for **(?)** 00:05:00

5m

## Note

A 1:2 dilution of the fibrils is usually a good starting point, i.e. a 35 mM equivalent monomer concentration.

- 7 Remove excess solution using a pipet and add 🛴 50 µL of filtered PBS to the well.
- 8 Remove excess solution again and replace by \$\Delta\$ 50 \(\mu\L\) of \$\[[m]\] 1 nanomolar (nM) Nile Red.



9 Image the sample straight away and make sure it doesn't dry out during imaging.