

AUG 26, 2023

• Immunolabeling and PI staining Drosophila melanogaster germaria

shelbilrussell¹

¹Assistant Professor, Department of Biomolecular Engineering, University of California Santa Cruz



shlrusse

ABSTRACT

Protocol for staining (Wolbachia-infected) Drosophila ovaries for immunolabeling germarium proteins.





Protocol Citation: shelbilrus sell 2023. Immunolabeling and PI staining Drosophila melanogaster germaria. **protocols.io**

https://protocols.io/view/imm unolabeling-and-pi-stainingdrosophila-melanogacy74xzqw

License: This is an open access protocol distributed under the terms of the Creative Commons
Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's working

Created: Aug 26, 2023

Last Modified: Aug 26,

2023

PROTOCOL integer ID:

87004

1 Make devitellinizing (DV) solution

a. Measure and add to a 1.5 ml eppendorf tube in the fume hood:

10x PBS 100 ul

dH20 400 ul

32% EM-grade paraformaldehyde 500 ul **opened < 10 days ago**

NP40 detergent 5.0 ul

- ~ 1 mL DV solution
- b. Vortex this until NP40 is no longer visible as a blob on the side of the tube.

2 Dissect ovaries

- a. Set up dissecting dish, filling each well with 1xPBS
- b. Label 1.5 ml eppendorf tube for each sample and fill with ~1 ml of 1x PBS
- c. Knock out flies on CO2 pad
- d. Sort flies for target genotypes (if needed)
- e. Dissect ovaries in PBS in 3 minutes or less to prevent "aggregation effects". Note: This amounts to only 5-10 flies of one genotype.
- f. Gently separate ovarioles with pins.
- g. Transfer ovaries to tube of 1x PBS

3 Fix ovaries

- a. Briefly spin down ovaries (at ~2500xg) and remove 1x PBS
 Note: ovaries may be on the side of tube be careful to not disturb
- b. In the fume hood, add 600 uL heptane to each tube and start timer
- c. Add 200 uL of DV solution
- d. Mix vigorously by hand for 1 min, or until emulsion forms between two phases.
- e. Place on rotator for remaining 19 min
- 4 Rinse and treat with RNAseA (to degrade RNA for PI-DNA staining)
 - a. When ~30 seconds remain on the time, centrifuge ovaries briefly (at ~2500xg) to pellet
 - b. In the fume hood, remove and dispose the gunky top phase first, being careful to not disturb the pellet. When in doubt, remove less and add an extra wash.
 - c. Add \sim 1.2 mL 1x PBS-T (1% Triton X-100), centrifuge, pipette, and dispose residual heptane and fixative.
 - d. Repeat rinse once more quickly.
 - e. On third addition of fresh 1x PBS-T, incubate for 10 minutes prior to centrifuging and removal of buffer. Repeat two more times for a total of 5 washes.

Thaw frozen RNAseA (10mg/ml) at room temperature

- f. After removing the final 1x PBS-T, add RNAseA
- g. Incubate overnight at room temperature

5 Remove RNAse A

- a. Centrifuge and remove and store RNAseA at -20C, marking use Note: RNAseA aliquots are good for up to 10 uses, with freezes in between
- b. Rinse 2x briefly and then wash 4x for 10 min each in PBS-T

6 Block tissue

7	Bind	primary	antibody
,			

- a. Suspend in PBS-T containing primary antibody at proper dilution (__:___).
- b. Incubate overnight at 4C.

8 Remove primary antibody

- a. Centrifuge and remove primary antibody, discarding used solution
- b. Rinse 2x briefly and then wash 4x for 10 min each in PBS-T

9 Bind secondary antibody

- a. Resuspend in secondary antibody solution at proper dilution (__:___)
- b. Incubate overnight at 4C.

10 Remove secondary antibody

- a. Centrifuge to remove secondary antibody, discarding used solution.
- b. Rinse 2x briefly and then wash 4x for 10 min each in PBS-T.

11 Stain DNA with propidium iodide (PI)

After the removal of the last wash, add 60-100 uL of PI mounting medium to each tube.

Flick to coat all oocytes in medium and spin down with the microcentrifuge to pull solution to bottom.

Incubate overnight at room temperature or at 4C over the weekend.

12 Mount oocytes

Spin down oocytes and remove as much PI-containing mounting medium as possible.

Resuspend in 30 uL 70% glycerol in 1xPBS.

Using a p1000 tip, transfer each set of ovaries to a clean microscope slide.

Use pins to separate ovaries into ovarioles and eggs - position mature eggs around perimeter, in a circle.

Carefully lay coverslip over samples *do not move coverslip after placement (to avoid distorting oocytes).

Manage the amount of mounting media under slide:

If too much, wick excess with a kimwipe

If too little, add carefully with a tip to edge (allowing only what is required to fill area to wick out)

Paint edges of coverslip with nail polish to seal sample. Allow to fully dry in a dark drawer.

Store at -20C prior to imaging. Image within a month.