



Nov 27, 2020

Nano-OTS V.2


Ida Hoijer¹, Josefin Johansson², Sanna Gudmundsson³, Chen-Shan Chin⁴, Ignas Bunikis², Susana Häggkvist², Anastasia Emmanouilidou², Maria Wilbe², Marcel Den Hoed², Marie-Louise Bondeson², Lars Feuk², Ulf Gyllensten², Adam Ameur²

¹SciLifeLab, Uppsala University; ²Uppsala University; ³Broad Institute of Massachusetts Institute of Technology and Harvard; ⁴Foundation for Biological Science

1

Works for me

This protocol is published without a DOI.



ABSTRACT

This is a protocol that detects Cas9 off-target sites *in vitro* using nanopore sequencing¹. The protocol is a modified version published by Gilpatrick et al $(2020)^2$. Guide RNAs have been designed using CHOPCHOP (https://chopchop.cbu.uib.no/).

- 1. Höijer, I., et al. (2020). "Amplification-free long read sequencing reveals unforeseen CRISPR-Cas9 off-target activity." bioRxiv: 2020.2002.2009.940486.
- 2. Gilpatrick, T., Lee, I., Graham, J.E. *et al.* Targeted nanopore sequencing with Cas9-guided adapter ligation. *Nat Biotechno* **38**, 433–438 (2020). https://doi.org/10.1038/s41587-020-0407-5

EXTERNAL LINK

https://www.biorxiv.org/content/10.1101/2020.02.09.940486v1

EXTERNAL LINK

https://www.biorxiv.org/content/10.1101/2020.02.09.940486v1

PROTOCOL CITATION

Ida Hoijer, Josefin Johansson, Sanna Gudmundsson, Chen-Shan Chin, Ignas Bunikis, Susana Häggkvist, Anastasia Emmanouilidou, Maria Wilbe, Marcel Den Hoed, Marie-Louise Bondeson, Lars Feuk, Ulf Gyllensten, Adam Ameur 2020. Nano-OTS. **protocols.io**

https://protocols.io/view/nano-ots-bp5rmg56

Version created by Ida Hoijer

EXTERNAL LINK

https://www.biorxiv.org/content/10.1101/2020.02.09.940486v1

KEYWORDS

Nano-OTS, Cas9, off-target sequencing, OTS, CRISPR-Cas9, ONT, nanopore sequencing, MinION

LICENSE

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

CREATED

Nov 27, 2020

LAST MODIFIED

Nov 27, 2020

PROTOCOL INTEGER ID

44945

MATERIALS TEXT

MATERIALS

■ NEBNext Quick Ligation Module - 20 rxns New England

Biolabs Catalog #E6056S

Biolabs Catalog #N0440S

Coulter Catalog #A63880

🛭 🛭 Alt-R® S.p. HiFi Cas9 Nuclease

V3 IDT Catalog #1081060

Technologies Catalog #SQK-LSK109

Technologies Catalog #1072532

⊠TE pH 8.0 (1X TE Solution) **IDT**

Technologies Catalog #11-01-02-05

⊠ Nuclease Free Duplex Buffer **IDT**

Technologies Catalog #11-01-03-01

Quick CIP New England

Biolabs Catalog #M0525S

Biolabs Catalog #M0273S

⊠TE pH 7.5 **IDT**

Technologies Catalog #11-01-02-02

⊠ CutSmart® Buffer **New England**

Biolabs Catalog #B7204S

₩ High Pass Plus Gel Cassettes sage

science Catalog #BPLUS10

ABSTRACT

This is a protocol that detects Cas9 off-target sites *in vitro* using nanopore sequencing¹. The protocol is a modified version published by Gilpatrick et al (2020)². Guide RNAs have been designed using CHOPCHOP (https://chopchop.cbu.uib.no/).

- 1. Höijer, I., et al. (2020). "Amplification-free long read sequencing reveals unforeseen CRISPR-Cas9 off-target activity." bioRxiv: 2020.2002.2009.940486.
- 2. Gilpatrick, T., Lee, I., Graham, J.E. *et al.* Targeted nanopore sequencing with Cas9-guided adapter ligation. *Nat Biotechno* **38**, 433–438 (2020). https://doi.org/10.1038/s41587-020-0407-5

Shearing of genomic DNA

Add 0.45x AMPure XP beads to the sample and incubate at 2000 rpm using a vortex mixer for 10 min. 2.1 Place the tube on a magnetic rack until the beads collect on the side of the tube and the solution appears to be clear. Slowly pipette off the supernatant and discard. Be careful not to disturb the beads. Wash the beads using 70% freshly prepared ethanol. 22 - Fill the tube with the ethanol - Do not disurb the bead pellet - Wait 30 seconds and pipette off the ethanol and discard 2.3 Repeat step 2.2 Remove any residual ethanol. 2.4 - Spin the tube briefly and put back on the magnetic rack - Pipette off any remaining ethanol using a P10 pipette 2.5 Add 32 µl Low TE buffer and incubate at 2000 rpm using a vortex mixer for 5 min to elute the sample. Place the tube on the magnetic rack until the beads collect on the side of the tube and the solution 2.6 appears clear. Slowly pipette off the supernatant and transfer to a new eppendorf tube. Quality control of fragmented DNA Measure concentration of the sample using Qubit and fragment size using Bioanalyzer, Tape station or FEMTO Pulse. Size selection of sheared DNA Perform size selection with a 10 kb cut-off using the BluePippin and the High pass plus gel casette with the "15 kb High Pass Plus Marker U1" casette definition (the 10 kb cut-off is not supported by Sage Science). Add 0.45x AMPure XP beads to the sample and incubate at 2000 rpm using a vortex mixer for 10 min. 5.1 Place the tube on a magnetic rack until the beads collect on the side of the tube and the solution appears to be clear. Slowly pipette off the supernatant and discard. Be careful not to disturb the beads. 5.2 Wash the beads using 70% freshly prepared ethanol. - Fill the tube with the ethanol

Shear 5-10 µg of HMW genomic DNA to 20 kb using Megaruptor 2.

- Do not disurb the bead pellet
- Wait 30 seconds and pipette off the ethanol and discard
- 5.3 Repeat step 5.2
- 5.4 Remove any residual ethanol.
 - Spin the tube briefly and put back on the magnetic rack
 - Pipette off any remaining ethanol using a P10 pipette
- 5.5 Add 24 µl Low TE buffer and incubate at 2000 rpm using a vortex mixer for 5 min to elute the sample.
- 5.6 Place the tube on the magnetic rack until the beads collect on the side of the tube and the solution appears clear. Slowly pipette off the supernatant and transfer to a new eppendorf tube.

Preparing the Cas9 ribonucleoprotein complexes (RNPs)

- 6 Resuspend crRNAs and tracrRNA to a final concentration of 100 mM in TE pH 7.5.
- 7 Pool all crRNAs used in the same experiment equimolarly by combining 1 μl of each crRNA in a new eppendorf tube. Unused crRNa mix can be stored at -70°C.
- 8 Anneal crRNA and tracrRNA. In a 0.2 ml tube (preferably low-bind) combine:
 - 8 μl Duplex buffer
 - 1 μl crRNA pool (100 μM)
 - 1 μl tracrRNA (100 μM)

Inclubate at 95° C for 5 min in a thermocycler. Remove the tube from the thermocycler and let it cool down to room temperature (\sim 5 min). Place the tube on ice.

9 Assemble the RNPs. Add the following components to a new 1.5 ml eppendorf tube:

5 μl annealed crRNA-tracrRNA 5 μl 10x NEB CutSmart buffer 39.6 μl nuclease-free water 0.4 μl HiFi Cas9 (62 μM)

Incubate at room temperature for 30 min, then place on ice.

While the RNPs are incubating, proceed to the next step.

Dephosphorylation of sheared and size selected DNA

- 10 3 μg of sheared and size selected DNA is needed for this step. Bring the sample to 24 μl using nuclease-free water if needed.
- 11 Add the following components in a 0.2 ml thin-walled PCR tube:

 $3 \mu l$ 10x NEB Cut Smart buffer 24 μl sheared and size selected DNA (3 μg)

Mix gently by flicking the tube, spin down.

Add 3 μ I CIP to the tube.

Incubate at 37°C for 10 min, 80°C for 2 min and then hold at 20°C on a thermocycler.

Cas9 digestion and a-tailing

- 12 Make a 10 mM dATP solution by combining 1 μl 100mM ATP and 9 μl nuclease-free water. Do not keep the solution for future experiments.
- Make a 1x NEB Cut Smart solution by combining 1 μ l 10x NEB Cut Smart Buffer and 9 μ l nuclease-free water. Do not keep the solution for future experiments.
- 14 Add the following components to the PCR tube containing the dephosphorylated DNA sample:

30 µl dephosyphorylated DNA 7 µl 1x NEB Cut smart buffer 3 µl RNPs 1 µl 10 mM dATP 1 µl NEB Taq polymerase

Mix carefully by inverting the tube, spin down.

Incubate at 37°C for 15 min, 72°C for 5 min and hold at 4°C. Then place the tube on ice.

Adapter ligation

- 15 Carefully transfer the contents of the 0.2 ml PCR-tube to a new 1.5 ml eppendorf tube.
- 16 Add the following compontents to a separate 1.5 ml eppendorf tube. It is important to add the adapter mix (AMX) last.

20 µl ligation buffer (LNB) 3 µl nuclease-free water 10 µl NEBNext Quick T4 DNA ligase 5 µl adapter mix (AMX)

Mix thoroughly by pipetting.

- 17 Add 20 μl of the adapter ligation mix to the Cas9 digested and dA-tailed DNA sample. Mix gently by flicking the tube. Do not spin down at this stage.
- 18 Immediately after mixing, add the remaining adapter ligation mix. Mix gently by flicking the tube, spin down.

Inclubate at room temperature for 10 min.

AMPure XP bead purification

19 Add 1 volume (80 μ l) of TE pH 8.0 to the adapter ligated sample. Mix gently by flicking the tube.

20 Add 0.3x (48 μl) AMPure XP beads to the sample. Mix by gentle inversion.

Incubate at room temperature for 10 min. Do not agitate the sample.

- 21 Spin down the sample and place on a magnetic rack until the beads collect on the side of the tube and the solution appears to be clear. Pipette off the supernatant and discard. Be careful not to disturb the pellet.
- 22 Wash the beads by adding 250 μl long fragment buffer (LFB). Resuspend the beads by flicking the tube and place back on the magnetic rack.

When the solution appears clear, pipette off the supernatant and discard.

- 23 Repeat step 22.
- 24 Remove any residual buffer.
 - Spin the tube briefly and put back on the magnetic rack
 - Pipette off any remaining buffer using a P10 pipette
- 25 Remove the tube from the magnetic rack and add 13 µl elution buffer (EB) to elute the sample.

Incubate at room temperature for 10 min. Do not agitate the sample.

Place the tube on the magnetic rack until the beads collect of the side of the tube and the solution appears clear. Pipette off 12 μ I of the supernantant and transfer to a new 1.5 ml eppendorf tube. Place on ice.

Sequencing on the MinION

- 27 Open the priming port on the MinION flow cell. Draw back a small volume to remove any bubbles by:
 - Set a P1000 to 200 μl
 - Insert the tip into the priming port
 - Turn the wheel of the pipette until the dial shows 220-230 μ l, or until you can see a small volume of buffer in the pipette tip
- 28 Add 30 µl of flush tether (FLT) directly to the flush buffer (FLB). Mix by pipetting.

Load 800 µl of the priming mix to the priming port. Avoid the introduction of bubbles. Wait 5 min.

29 Add the following components to a new 1.5 ml eppendorf tube:

25 µl sequencing buffer (SQB) 13 µl loading beads (LB) 12 µl DNA library

- 30 Complete the flow cell binding by:
 - Gently open the SponON sample port cover
 - Load 200 µl of the priming mix to the priming port. Avoid the introdution of bubbles.
- 31 Mix the prepared library gently by pipetting just prior to loading.

 $Add\ 50\ \mu I\ of\ the\ library\ SpotON\ sample\ port\ in\ a\ dropwise\ fashion.\ Ensure\ each\ drop\ flows\ into\ the\ port\ before\ adding$

the next one.

 $32 \quad \text{Start the sequncing run through the MinKNOW software.} \\$

Data analysis

33 Align the reads using minimap2. Use the mapped reads for detection of off-target sites using our custom tool Insider:

https://github.com/UppsalaGenomeCenter/InSiDeR