

OCT 06, 2023

# OPEN ACCESS



#### DOI:

dx.doi.org/10.17504/protocol s.io.yxmvmnpm6g3p/v1

**Protocol Citation:** Zhichao Chen 2023. FLOUR-seq. protocols.io https://dx.doi.org/10.17504/p rotocols.io.yxmvmnpm6g3p/v

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License. which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

**Protocol status: Working** We use this protocol and it's working

Created: Apr 26, 2022

Last Modified: Oct 06, 2023

https://dx.doi.org/10.17504/protocols.io.yxmvmnpm6g3p/v1

### FLOUR-seq

### Zhichao Chen<sup>1</sup>

<sup>1</sup>BGI Genomics



Zhichao Chen

#### **ABSTRACT**

We presented three barcoded technologies (BD Rhapsody) that are accessible to most researchers: high-throughput single-cell ONT full-length RNA sequencing (FLOUR-seq). FLOUR-seq combines BD Rhapsody and nanopore sequencing to detect the RNA panorama (including nascent, mature, and degrading RNAs) in cells. The ultralong three barcodes can be discriminated using nanopore technology with 70% debarcoding efficiency and can detect the RNA panorama.

Oct 6 2023

## mouse testis cell dissociation

1d

1 The mouse testis were dissociated to single cells refer to Adult mouse testis cell dissociation (on ice).

1d

## **Priming and treating the BD Rhapsody Cartridge**

20m

2 Prime and treat the BD Rhapsody Cartridge (Cat. No. 400000847).

20m

Α	В	С	D	E
Ste p	Regent to load	Volume (μL)	P1200M pipette mode	Incubation at room temp.
1	100% ethyl alcohol	700	Prime/Treat	-
2	Air	700	Prime/Treat	-
3	Room temp. Cartridge Wash Buffer 1 (Cat. No. 650000060)	700	Prime/Treat	1min
4	Air	700	Prime/Treat	-
5	Room temp. Cartridge Wash Buffer 1 (Cat. No. 650000060)	700	Prime/Treat	10min
6	Air	700	Prime/Treat	-
7	Room temp. Cartridge Wash Buffer 2 (Cat. No. 650000061)	700	Prime/Treat	<4h

# Loading cells in cartridge

22m

3 Dilute 20000 cells with cold Sample Buffer (Cat. No. 650000062) to 650 μL.

5m

4 Load cartridge with materials listed using the P1200M pipette:

A	В	С
Material to load	Volume (μL)	Pipette mode

A	В	С	
Air	700	Prime/Treat	
MSet P1200M pipette MPipet-mix the cell su	MSet P1200M pipette to Cell Load mode. MPipet-mix the cell suspension with a manual P1000 pipette.		
Cell suspension	575	Cell Load	

Incubate at room temperature (15°C to 25°C) for 15 minutes. During 15 minute incubation, prepare Cell Capture Beads(Cat. No. 650000089).

15m

### Preparing, loading and washing Cell Capture Beads

12m

6 Place Cell Capture Bead tube on magnet for 1 minute, and remove storage buffer.
Remove tube from magnet, and pipet 650 μL cold Sample Buffer (Cat. No. 650000062) into tube.

2m

7 Set P1200M pipette to Prime/Treatmode. Load cartridge with materials listed using the P1200M pipette:

1m

A	В	С
Material to load	Volume (μL)	Pipette mode
Air	700	Prime/Treat
Set P1200M pipette to Bead Load mode.  Use a manual P1000 to gently pipet-mix beads in cold Sample Buffer (Cat. No. 650000062). Immediately load.		

8 Incubate the cartridge at room temperature (15°C to 25°C) for 3 minutes.

3m

Place cartridge on the plate shaker plate adapter. Shake the cartridge at room temperature (15°C to 25°C) at 1,000 rpm for 15 seconds.

1m

Return cartridge to Express instrument, and wait 30 seconds.

A	В	С
Material to load	Volume (μL)	Pipette modea
Air	700	Wash
Cold Sample Buffer (Cat. No. 650000062)	700	Wash
Air	700	Wash
Cold Sample Buffer (Cat. No. 650000062)	700	Wash

# **Lysing cells**

7m

Add 75.0  $\mu$ L 1 M DTT (Cat. No. 650000063) to one 15 mL Lysis Buffer bottle (Cat. No. 650000064). Briefly vortex lysis mix, place on ice.

2m

Move the left slider to **LYSIS** on Express instrument. Set P1200M pipette to **Lysis** mode. Set P1200M pipette to **Lysis** mode.

5m

A	В	С
Material to load	Volume (μL)	Pipette mode
Lysis Buffer with DTT	550	Lysis

Incubate at room temperature (15°C to 25°C) for 2 minutes.

## **Retrieving Cell Capture Beads**

9m

Place the 5 mL LoBind Tube in Express instrument drawer. Ensure P5000M pipette is set to **Retrieval** mode. Move the front slider to **BEADS** on Express instrument.

2m

Move the left slider to **RETRIEVAL**. Leave Retrieval magnet in down position for 30 seconds.

Aspirate 5,000  $\mu$ L Lysis Buffer with DTT with the P5000M pipette. Press down on P5000M pipette to seal against the gasket. Move the left slider to the middle position (**0**), andimmediatelyload 4,950  $\mu$ L Lysis Buffer with DTT.

Remove pipette from gasket, and purge tip. Move the front slider to **OPEN**, and place the 5 mL LoBind Tube on large magnet with 15 mL tube adapter (V&P Scientific Cat. No. VP 772FB-1A) for 1 minute.

2m

### **Washing Cell Capture Beads**

8m

After 1 minute incubation leaving the 5 mL tube containing retrieved Cell Capture Beads on large magnet, remove all but ~1 mL of supernatant without disturbing beads.

1111

17 Remove tube from magnet. Gently pipet-mix beads, and transfer them to a new 1.5 mL LoBind Tube.

1m

Place tube on magnet for ≤2 minutes, and remove supernatant. Avoid leaving Lysis Buffer or bubbles in tube. Lysis Buffer might cause the reverse transcription reaction to fail.

2m

Remove tube from magnet and pipet 1.0 mL of cold Bead Wash Buffer (Cat. No. 650000065) into tube. Pipet-mix.

1m

Place tube on 1.5 mL tube magnet for  $\leq$ 2 minutes, and remove supernatant.

2m

Remove tube from magnet, and pipet 1.0 mL cold Bead Wash Buffer (Cat. No. 650000065) into tube. Pipet-mix, and place on ice.

lm

## cDNA synthesis and template switching

22 In a new 1.5-mL LoBind tube, pipet the following reagents.

#### 10m

### cDNA/Template switching mix

А	В
Component	Volume (μL)
RT Buffer	40
dNTP	20
RT 0.1 M DTT	10
Bead RT/PCR Enhancer	12
RNase Inhibitor	10
Reverse Transcriptase	10
Nuclease-free water	92
Total	194

Gently vortex mix, briefly centrifuge, and place back on ice.

23 Place the tube of washed Cell Capture Beads on a 1.5-mL tube magnet for≥2 minutes. Remove the

supernatant and pipet 194 µL of cDNA mix into the beads. Pipet-mix.

24 Incubate the bead suspension on the thermomixer at 1,200 rpm and 42°C for 30 minutes.

30m

5m

Place tube on 1.5 mL tube magnet for  $\leq$ 2 minutes, and pipet supernatant to a new tube. Remove tube from magnet, and pipet 200  $\mu$ L the following reagents into tube.

A	В
Component	Volume (μL)
10x Exonuclease I reaction buffer (BD Express, Cat. No. 650000071)	20

A	В
Exonuclease I (BD Express, Cat. No. 650000072)	10
Nuclease-free water	170

Place tube on 1.5 mL tube magnet for ≤2 minutes, and remove supernatant. Wash the beads twice with 1x RT buffer.

10m

Resuspend the beads with the saved supernatant in step 25, add 3  $\mu$ L of template switch oligo (100 uM5' A AGC AGT GGT ATC AAC GCA GAG TAC rG rG +G 3'), and incubate on the thermomixer for 15 minutes at 1,200 rpm and 42°C. Add 2  $\mu$ L of 1 M MgCl2 to the reaction mix, and incubate on the thermomixer for another 15 minutes at 1,200 rpm and 42°C.

35m

Briefly spin the tube with the bead suspension. Place the tube on the magnet for≤1 minute until clear. Remove the supernatant.

2m

Remove the tube from the magnet, and pipet 200  $\mu$ L of cold Bead Resuspension Buffer into the tube. Pipet- mix.

2m

# **Performing PCR1**

2h 14m

Place the tube beads in Bead Resuspension Buffer on a 1.5-mL magnet for≤1 minute. Remove the supernatant. Suspend the beads with following PCR reaction mix:

10m

A	В	С
Component	Volume (μl )	Final Conc
KAPA HiFi HotStart 2x ReadyMix	100	1x
Universal Oligo (BD Express, 650000074)	6	0.3 μΜ
TSO PCR primer (10μM)	6	0.3μΜ
Nuclease-free water	up to 200μl	

Universal Oligo: 5'-ACACGACGCTCTTCCGATCT-3'

TSO PCR primer: 5'-AAGCAGTGGTATCAACGCAGAGTAC-3'

- Ensuring that the beads are fully resuspended, pipet 25  $\mu$ L of PCR reaction mix with beads into each of 8 0.2-mL PCR tubes.

1h 30m

2m

**32** Program the thermal cycler as follows.

11

1

1

Annealing

Extension

extension

Final

Hold

А	В	С	D
Step	Cycles	Temperature	Time
Hot start	1	95°C	3 min
Denaturation		98°C	20 s

3 min

4 min

2 min

 $\infty$ 

Pipet-mix and combine the four reactions into a new 1.5-mL LoBind tube. Place the 1.5-mL tube on the magnet for≤1 minute. Pipet the supernatant into the new 1.5-mL LoBind tube without disturbing the beads.

2m

Purify the amplified products by 0.7x Agencourt AMPure XP Beads(Beckman Coulter).

62°C

72°C

72°C

4°C

30m

# **Performing PCR2**

1h 10m

Prepare the PCR mix by combining and mixing the following components:

Α	В	С
Component	Volume (µl )	Final Conc
KAPA HiFi HotStart 2x ReadyMix	500	1x

A		В	С
Library Forward Primer (BD Express,91-1085)		3	0.3 μΜ
TSO lengthen primer (10µM)		3	0.3μΜ
PCR1 produc	et (50ng)		
Nuclease-fre	e water	up to 100μl	

TSO lengthen primer: 5'-CGACATGGCTACGATCCGACAAGCAGTGGTATCAACGCAGAG-3'

Library Forward primer: 5'-

AATGATACGGCGACCACCGAGATCTACACTATAGCCTACACTCTTTCCCTACACGACGCTCTTCCG ATCT-3'

**36** Program the thermal cycler as follows.

30m

A	В	С	D
Step	Cycles	Temperature	Time
Hot start	1	95°C	2 min
Denaturation		98°C	20 s
Annealing	5	62°C	20 s
Extension		72°C	4 min
Final extension	1	72°C	2 min
Hold	1	4°C	$\infty$

Purify the amplified products by 0.7x Agencourt AMPure XP Beads(Beckman Coulter).

30m

## **Nanopore sequencing**

3d

Prepared sequencing using Oxford Nanopore Technologies SQK-LSK109 and sequenced on ONT PromethION platforms.

3d