

VERSION 3 OCT 31, 2023

# OPEN ACCESS



#### DOI:

dx.doi.org/10.17504/protocol s.io.261ge4y4jv47/v3

Protocol Citation: Coline Royaux, Nicolas Rabet, Céline Bonillo 2023. PCR protocol for gene COXI neo-caledonian freshwater micro-crustaceans. protocols.io https://dx.doi.org/10.17504/protocols.io.261ge4y4jv47/v3V ersion created by Coline Royaux

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

**Protocol status:** Working We use this protocol and it's working

# PCR protocol for gene COXI neo-caledonian freshwater micro-crustaceans V.3

Coline Royaux<sup>1,2,3</sup>, Nicolas Rabet<sup>1,2,3</sup>, Céline Bonillo<sup>1,2,3</sup>

<sup>1</sup>Sorbonne Université; <sup>2</sup>Muséum National d'Histoire Naturelle; <sup>3</sup>UMR BOREA



# Coline Royaux

Université Pierre et Marie Curie (Paris VI), Muséum National...

#### **ABSTRACT**

This PCR protocol has been used to amplify the Cytochrome Oxydase I gene of neocaledonian genera *Boeckella*, *Lynceus*, *Eulimnadia* and *Streptocephalus* with several primers. Created: Oct 31, 2023

Last Modified: Oct 31, 2023

## **PROTOCOL** integer ID:

90195

**Keywords:** COI, PNDB, crustaceans, freshwater

1 Prepare the mix for the PCR depending on the quantity of DNA samples you want to amplify

#### Note

The quantities per well and for 96 DNA samples (with a 4 volumes margin) are detailed in the sub-steps

#### Safety information

Be careful to take enough margin to avoid a lack of reagent and, if possible, do a positive and a negative control

#### Note

Very few micropipettes are able to dose such a small amount so you'll have to make your mix for several wells at a time.

So, for 96 DNA samples with a 4 volume margin (100 volumes), mix

□ 1244 μL distilled water , □ 200 μL DNA buffer for Taq polymerase ,

🗸 100 μL DMSO 📌 🗸 100 μL BSA 🕺 🗸 80 μL DNTP and 🔼 12 μL Taq polymerase

Add your primers to the mix, A 0.32 µL selected H primer [M] 10 picomolar (pM) and A 0.32 µL selected L primer [M] 10 picomolar (pM) for each well. This mix is hereafter named "final reagent mix".

## **Safety information**

You may have to use different primers in your wells depending on the individual and the gene you want to amplify. If so, distribute the intermediary mix in as much tubes as primer pairs you want to use and add your primers in the proper quantity to make your final reagent mix. Don't forget to add margins in each mix for each different pair of primers you use.

#### Note

So, for 96 DNA samples with a 4 volume margin (100 volumes) and if you use the same primers for all 96 wells, add  $\blacksquare$  32  $\mu L$  selected H primer and

Δ 32 μL selected L primer

In each well, deposit  $\Delta$  18  $\mu$ L of the final reagent mix and  $\Delta$  2  $\mu$ L genomic DNA unless for the negative control.


For the positive control, use the DNA of the species on which the primer has been designed.

- 3 Close the PCR plate with a heated aluminium foil and centrifuge it enough to make sure the reagents are all in the bottom of the well.
- 4 To amplify targeted DNA sequences, place your plate in the thermocycler, set and launch the cycle as described in the following sub-steps
- 4.1 00:05:00 at \$\mathbb{8}\$ 94 °C

5m

- **4.2** 40 cycles of the following steps:
  - (5) 00:00:30 at (1) 94 °C

2m



# 4.3 © 00:08:00 at \$\ 72 \cdot \)

- 4.4 Infinite timing at \$\ \begin{aligned} 20 \ \cdot \
- To know if your amplifications worked properly, you now have to proceed to a gel electrophoresis of your PCR products
- **5.1** To prepare the gel,

## Safety information

This step is to be made under an extractor hood with gloves, a blouse and glasses as BET is highly mutagenic and carcinogenic

mix  $\bot$  0.8 mg agarose and  $\bot$  40 mL TAE buffer , heat the preparation in the microwave for a few moments until it is homogeneous (you can agitate the preparation). Wait until the preparation is cold enough to touch its container and add  $\bot$  0.8 µL BET .

- Four the preparation in a mold and let the gel polymerize with a bar to form wells to deposit your PCR products
- **5.3** Deposit the gel in the electrophoresis tank

- 5.5 Start electrophoresis in TAE buffer for 00:15:00 at 200 Volts

15m

**5.6** Look at your gel under Ultra Violet light to see the results