

SEP 21, 2023

Virus and Prokaryote Enrichment in Coral DNA Metagenomes

Natascha

Varona¹, Bailey Wallace¹, Cynthia Silveira¹

¹University of Miami Department of Biology



amz

ABSTRACT

Tissue preparation and DNA extraction protocol for enrichment of viruses and prokaryotes in DNA metagenomes of corals.

IMAGE ATTRIBUTION

Cynthia Silveira





DOI:

dx.doi.org/10.17504/protocol s.io.q26g7p1y3gwz/v1

Protocol Citation: Natascha Varona, Bailey Wallace, Cynthia Silveira 2023. Virus and Prokaryote Enrichment in Coral DNA Metagenomes. protocols.io

https://dx.doi.org/10.17504/protocols.io.q26g7p1y3gwz/v1

License: This is an open access protocol distributed under the terms of the Creative Commons
Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's working

Created: Aug 29, 2023

Oct 21 2023

Last Modified: Sep 21,

2023

PROTOCOL integer ID: 87107

Keywords: coral, bacteria, virus, bacteriophage, metagenome

MATERIALS

10X DNase Buffer:

- [м] 100 millimolar (mM) Tris-HCl (pH 7.5)
- [M] 25 millimolar (mM) MgCl₂
- [м] 5 millimolar (mM) CaCl₂
- Fresh or thawed ~1cm³ coral sample
- Sterile mortar and pestle
- Sterile forceps
- 🔼 1.5 mL centrifuge epi tubes
- Δ 0.02 μm filtered and autoclaved artificial seawater (ASW)
- 425-600 μm acid-washed glass beads (Sigma CAT#G9268)
- 4 15 mL conical centrifuge tubes
- Vortex
- Centrifuge
- Pipettes
- DNase [M] 10000 U/mL
- 100X EDTA [M] 0.5 Molarity (m)
- Sterile A 10 mL Luer-LokTM syringes
- 8 μm pore size, 25mm flat filters (Whatman, Nucleopore Track-Etched Polycarbonate (CAT#110614))
- Sterile 25mm filter holders with Luer-LokTM connection (Swinnex CAT#SX0002500)
- AmiconTM Ultra-15 Centrifugal Filter Units (MilleporeSigmaTM CAT#UFC910008)
- NucleoSpin[®] Tissue Kit (MACHEREY-NAGEL Inc. REF:740952.10/.50/.250)

BEFORE START INSTRUCTIONS

- Glass beads must be washed with 0.1 N HCl
- Incubator set to 🖁 56 °C & 🖁 70 °C
- Check if Buffer B5 and Proteinase K were prepared according to section 3 of NucleoSpin[®] Tissue Kit Manual.

Sample Preparation

3h

1 Collect a coral sample of approximately 1cm³ containing coral tissue, mucus, and skeleton. Use

- a fresh sample if possible. If not, flash-freeze the sample and keep it at responsible. If not, flash-freeze the sample and keep it at responsible. If not, flash-freeze the sample and keep it at responsible. If not, flash-freeze the sample and keep it at responsible.
- Weigh and record coral fragment weight.
- 3 Crush the coral sample using a sterile mortar and pestle until the skeleton and tissue fragments are the size of coarse sand. Do not overdo this step. Transfer the fragments, along with the mucus (coral homogenate), to a 2 mL microcentrifuge tube.
- Vortex at speed 3 for 00:05:00 min to dislodge tissue and mucus.
 - * To avoid lysis of bacterial cells, do not vortex the sample at higher speeds or longer durations than described.
- 6 Pulse-centrifuge the sample (3-5 seconds at 3.200 x g).
- 7 Collect supernatant and transfer to a clean 15 mL microcentrifuge tube.
- 8 Bring sample up to $\boxed{1 \text{ mL}}$ with sterile ASW.
- Add \bot 100 μ L of 10X DNase Buffer and \bot 2 μ L of DNase 10,000 U/mL for a final concentration of 20 U/mL. Mix by gently inverting the tube.

- 11 Stop DNase activity by adding \angle 10 μ L of 100X EDTA.
- Bring sample volume up to 4.5 mL with sterile ASW.
- Transfer the sample to a 10 mL syringe and push through an 8.0 μm, 25 mm flat filter, collecting the flowthrough in a clean 15 mL centrifuge tube.
 - \star If the sample clogs the filter, replacing the 8.0 μ m filter may be necessary. In this case, pull back on the syringe plunger to recollect the sample in the syringe before transferring it to a new filter.
 - * In the case of samples with excessive mucus, you may further dilute the sample with sterile ASW prior to filtering.
- 14 Transfer flowthrough to an AmiconTM Ultra-15 Centrifugal Filter Unit.
- Centrifuge at room temperature for \bigcirc 00:30:00 min at \geq 2600 x g

30m

DNA Extraction

1h 12m

1. Add Δ 200 μL Buffer T1 and Δ 20 μL of Proteinase K from the NucleoSpin[®] Tissue Kit to the AmiconTM filter unit.

- 17 Rinse one side of the filter with the lysis buffer 3-5 times using a pipette.
- Securely close the AmiconTM filter unit and incubate for 01:00:00 hour at 56 °C, being sure to place the tube in a position where the rinsed side of the filter remains covered in the Buffer T1 & Proteinase K mixture.
 - * Some Amicon**TM** filter unit lids may not seal properly. Check for leaks before placing in the incubator. Seal with parafilm if necessary.
- Repeat steps 17 and 18 on the other side of the filter.
- 20 Add \pm 210 μ L Buffer B3 to the Amicon TM filter unit and vortex to mix.
- 21 Incubate for 00:10:00 min at 70 °C

10m

- Add Δ 210 μL ethanol (100%) to the AmiconTM filter unit and vortex to mix.
- Proceed with steps 5-7 of the NucleoSpin $^{\mathbb{R}}$ Tissue Kit Standard protocol for human or animal tissue and cultured cells.
- On step 8 of the NucleoSpin[®] Tissue Kit, perform the following:

2m

- a. Place the NucleoSpin[®] Tissue Column into a 1.5 mL microcentrifuge tube (not provided in kit)
- b. Add $\boxed{ \bot}$ 50 μL PCR-grade water
- c. Incubate at room temperature for 00:01:00

- d. Centrifuge for 00:01:00 min at 11000 x g
- e. Repeat steps b, c, & d once, for a final volume of 100 uL