



May 04, 2022

Shipping protocols

Gabriel J J. Barrero¹, Abraham Palmer¹, Oksana Polesskaya¹

¹UCSD, Palmer lab

1

≪

dx.doi.org/10.17504/protocols.io.bp2l617edvqe/v1

CGORD

Gabriel J. Barrero

Shipping tissue protocol

DOI

dx.doi.org/10.17504/protocols.io.bp2l617edvqe/v1

Gabriel J J. Barrero, Abraham Palmer, Oksana Polesskaya 2022. Shipping protocols . **protocols.io**

https://dx.doi.org/10.17504/protocols.io.bp2l617edvqe/v1

protocol ,

Apr 26, 2022

May 04, 2022

61472

Collection

1 Collection

1.1 Put the spleen into a pre-labeled 2 mL microcentrifuge tube (for example, Fisher Scientific cat#05-408-138). Add approximately 0.5 mL saline solution in the tube with the spleen to prevent dry-freezing of tissue, but make sure that the tube is not over-filled.

If your rats have been implanted with an RFID chip, try to find this chip during dissection and put it directly into the tube with the spleen. We will read both



1

the barcode and RFID chip to confirm the sample identity


.

1.2 For tube labels use "Cryo Babies" for laser printers (Diversified Biotech cat# LCRY-1700), they withstand long-term storage in & -80 °C without peeling off the tubes.





1.3 •Store samples in cardboard boxes clearly labeled with the PI name, date (or at least year), tissue (e.g. "spleen") and project title. Example:JHOU-HS ratsU01-Spleen-Box02_25Feb2019



1.4 For a genotyping backup tissue sample, cut off ~ 5 mm of the tail tip and store at your lab. Use 2 mL tube labeled with the barcode and rat ID, add saline to prevent sample desiccation. Store at § -80 °C long-term.

shipping

2 Shipping

- 2.1 Send spleens in the cardboard box (not plastic, they can break during shipping) labeled with the Project, type of tissue, box number, and the date (e.g. JHOU_HS rats-Spleen_Box02_25Feb2019).
- 2.2 Use a secondary container (plastic bag or just wrap with paper) in case box is broken during shipment.
- 2.3 Use at least 10 kg (20 lb) dry ice for shipping. If you have a choice, use pellets. If you use slabs, make sure that there is no free space in the shipping box, so slabs cannot move freely and crash things.
- 2.4 Use Styrofoam box that is surrounded by a cardboard box. Choose boxes with thick walls. For example, ULINE S-13392 or ULINE S-11357.
- 2.5 ·Send by FedEx overnight on Monday or Tuesday, check for holidays.
- 2.6 At the time of shipping, send the manifest to the Center that contains a list of samples, box ID, collection date, and comments (if any), we will use it to update the database