

AUG 08, 2023

# Preparation of soluble and insoluble mitochondrial protein fractions for immunoblotting

# Louise Uoselis<sup>1</sup>

<sup>1</sup>Lazarou Lab, WEHI



Louise Uoselis WEHI

## **ABSTRACT**

Preparation of soluble and insoluble mitochondrial protein fractions from HeLa cells for immunoblotting.





**Protocol Citation:** Louise Uoselis 2023. Preparation of soluble and insoluble mitochondrial protein fractions for immunoblotting. **protocols.io** 

https://protocols.io/view/prep aration-of-soluble-andinsoluble-mitochondrialcybjxskn

License: This is an open access protocol distributed under the terms of the Creative Commons
Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

**Protocol status:** Working We use this protocol and it's working

Created: Aug 08, 2023

Last Modified: Aug 08,

2023

**PROTOCOL** integer ID:

86091

### **Keywords: ASAPCRN**

1

#### Note

All steps are performed on ice, unless specified

Thaw mitochondrial stocks on ice, and take two aliquots of 15 ug of mitochondria each for each sample (one aliquot will be the 'total' sample fraction, and one aliquot will represent the 'fractionation' sample).

2 Centrifuge samples at 10,000x rcf for 00:10:00 at 4 deg C, and carefully aspirate the supernatant

10m

Add  $\perp$  15 µL of ice cold 0.5% TX-100 in PBS, vortex each sample for ~5 seconds, and leave samples to incubate on ice for  $\bigcirc$  00:15:00 . At the conclusion of the 15 min lysis incubation, vortex each sample for ~5 sec again.

15m

- 4 Set aside one fraction from each sample for processing downstream (referred to as the 'total' fraction).
- 5 Centrifuge the remaining tube of each sample at 12,000x rcf for 00:10:00 at 4 deg C

10m

- Using a pipette, carefully remove A 14.24 µL of the supernatant (representing 95% of the lysis volume) and place this sample into a clean microfuge tube on ice, being sure not to disturb any pellets that have formed on the bottom of the tube. The volume removed represents the 'soluble' protein fraction. The tube containing the pellet represents the 'insoluble' protein fraction.
- 7 Add  $\bot$  14.24  $\mu$ L of 0.5% TX-100 in PBS to each insoluble protein fraction by pipetting on the side of the tube. Gently flick each tube to rinse the sides of the tube.
- 8 Centrifuge the insoluble protein fractions at 12,000x rcf for 00:10:00 at 4 deg C.

10m

- Using a pipette, carefully remove  $\boxed{\bot}$  14.24  $\mu L$  of the supernatant from the insoluble protein fraction, and place into a clean microfuge tube (which will function as the waste collection tube for all samples).
- Repeat steps 7 9, which will total 2 washes
- 11 Repeat step 7. You should now have three tubes for each sample (representing the total, soluble and insoluble protein fractions), and one waste tube.
- Bring all samples to room temperature. To the total and insoluble samples, add  $\Delta$  5  $\mu$ L of 4x SDS loading dye (4x: 20% w/v SDS, 400 mM DTT, 40% v/v glycerol, 200 mM Tris-Cl pH 6.8). To the soluble fraction, add  $\Delta$  4.75  $\mu$ L of 4x SDS loading dye.

#### Note

The precise quantities of loading dye added are very important, as they influence how the SDS-PAGE gel will run later on

- 13 Vortex each sample for ~3 seconds
- Boil all samples at 99 deg C for 00:10:00 shaking at max speed

10m

- Let samples cool to room temperature, and centrifuge quickly to bring all liquid to the bottom of the tubes. Vortex the samples again for ~3 sec to ensure homogeneity.
- Sonicate all samples in a waterbath sonicator set to ~21 deg C water temperature for



- 17 Remove all samples from the sonicator, vortex samples for  $\sim$ 3 sec to mix.
- Load  $\underline{\mathbb{Z}}$  19  $\mu L$  from each sample on an SDS-PAGE gel and proceed to run/transfer the gel as standard.