

MAR 06, 2023

Sigma GeneElute total RNA extraction from fungal tissue

Alexander J Bradshaw¹

¹Natural History Museum of Utah



Alexander J Bradshaw

ABSTRACT

RNA extraction from fungal tissue using the Sigma GeneElute total RNA kit.

OPEN ACCESS

יוסם

dx.doi.org/10.17504/protocol s.io.14egn7znyv5d/v1

Protocol Citation: Alexander J Bradshaw 2023. Sigma GeneElute total RNA extraction from fungal tissue. **protocols.io**

https://dx.doi.org/10.17504/protocols.io.14egn7znyv5d/v1

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's working

Created: Jan 24, 2022

Last Modified: Mar 07, 2023

PROTOCOL integer ID:

57351

Tissue and workspace preparation

15m

1

ALL WORK MUST BE DONE IN THE STERILE HOOD THAT HAS BEEN CLEANED FOR RNA WORK



REGULARLY CHNAGE GLOVES AND WASH HANDS WITH RNASE TO AVOID DEGREDATION

MAKE SURE ALL PIPETORS, TIPS, AND ANY OTHER EQUIPMENT ARE IN THE HOOD AND CLEANED WITH RNASE

DO NOT MOVE ANYTHING IN OR OUT WITHOUT WASHING WITH RNASE

Reagents that need to be made:

Fresh, day of 70% etoh

- 2 Flash Freeze tissue in Liquid Nitrogen (LN2).
- Grind Fungal Tissue to a fine powder with a mortar and pestle with LN2, be careful to not allow the tissue to thaw during this Process.
- **3.1** At this point frozen ground tissue can be stored at -80C for later extraction.

RNA extraction

15m

- 4 add 600ul of buffer RL to a 1.7ml eppendorf tube.
- 5 Place **no more than 50mg** of ground tissue into the sample tube with buffer RL.
- 6 Incubate for 15-30 minutes at room temperature 8 Room temperature

15m

7 Centrifuge at maximum speed for 2 minutes

Equipment	
Centrifuge	NAME
Benchtop Centrifuge	TYPE
Eppendorf	BRAND
5405000441	SKU
https://online-shop.eppendorf.us/US-en/Centrifugation-44533/Centrifuges-44534/Centrifuge-5425-PF-243560.html	LINK
Any benchtop centrifuge will suffice	SPECIFICATIONS

- **8** Transfer the lysate to a new RNAse free 1.7ml tube.
- Add 1:1 volume (so 600ul) of **freshly** prepared 70% etoh
- 10 Vortex for 10 seconds, or until homogenous
- 11 Assemble a column with a waste tube from the GeneElute kit.
- 12 Add 600ul of lysate/etoh solution to the assembled column

13 Centrifuge at 6000G for 2 minuts 14 If lysate is not completely passes, spin at an additional 14,000G for 1 minute 15 Discard waste from waste tube, and repeat step 13 and 14 if more lysate/etoh exists. 16 Place column into a new waste collection tube 17 Add 400ul of wash solution A to column 18 Centrifuges at max speed for 1.5 minutes 19 discard waste from collection tube 20 Repeat steps 17-19 two more times (for a total of 3x wash steps) 21 Centrifuge Sample for a final 2 minute dry spin at max speed

- 22 Place column in a clean eppendorf tube provided in the GeneElute kit. 23 add 50ul of elution solution A 24 Centrifuge at 200G for 2 minutes 25 centrifuge at 14,000G for 1 minute 26 If the entire 50ul has not eluted, then spin for an additional minute at 14,000G 15m Quality control of RNA and storage
- 28 BLEACH GEL:
 100ml TAE
 400ul concentrated bleach
 1g agarose

 Make sure to add bleach before microwaving.

- 29 Load and run samples normally at 120V for ~20 minutes with a 100bp ladder.
- immediately store samples at -80C after loading gel.