

OCT 06, 2023

OPEN ACCESS



DOI:

dx.doi.org/10.17504/protocol s.io.kqdg3x8keg25/v1

Protocol Citation: Yun-Hee Youm, Yufeng Liu, Vishwa Deep Dixit, Rong Fan, Bo Tao 2023. Yale Murine TMC -Tissue Preparation Protocol . protocols.io https://dx.doi.org/10.17504/p

https://dx.doi.org/10.17504/protocols.io.kqdg3x8keg25/v1

License: This is an open access protocol distributed under the terms of the Creative Commons
Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's working

Created: Oct 06, 2023

Yale Murine TMC - Tissue Preparation Protocol

Yufeng Rong Yun-Hee Youm 1 , Liu 1 , Vishwa Deep Dixit 1 , Fan 2 , Bo Tao 2

¹Department of Pathology, Yale School of Medicine;

²Department of Biomedical Engineering, Yale School of Engineering and Applied Science



Hester Doyle

ABSTRACT

Protocol for embedding murine spleen, thymus and lymph node.

PROTOCOL integer ID:

88920

RNA Buffer (use before embedding tissue in OCT)

- 1 1x PBS-MC Recipe
 - All prepared in DNAse RNAase EDTA free deionized water
 - MgCl₂ (1 mM, add 1 ml of 1 M MgCl₂ stock solution into 1 L of 1x PBS)
 - CaCl₂ (0.1 mM, add 2 ml of 0.1 M of CaCl₂ stock soution into 1 L of 1x PBS)
 - 4% paraformaldehyde (PFA), optional
 - 1 X Protease inhibitors (Catalog # 04693132001, Roche-cOmplete, EDTA-free Protease Inhibitor Cocktail, Tablets provided in EASYpacks)
 - 1X Phosphatase inhibitor (Catalog # 4906837001; PHOSS-RO; Roche-PhosSTOP™; sufficient for 20-10 ml buffer preparations, suitable for tissue processing and immunoprecipitation)
 - RNAse inhibitors (Invitrogen SUPERase•In RNAse Inhibitor (20 U/µL; Catalog # AM2696)
- 2 Filter sterilize with 0.22 μm syringe filter. Store at 4°C before use. Use within 2 weeks.



3 Incubate tissue on ice in the buffer for 15 minutes or during the collection.

Tissue Preparation/Embedding

- 4 Collect tissue in PBS on ice, wash if necessary
- 5 Dehydration/Fixation
- 5.1 Incubate the tissue in 20% sucrose/PBS solution or 4% paraformaldehyde and allow it to sink

to the bottom of the vial at overnight at 4°C.

6 Embedding

- 6.1 Place the fresh tissue in the center of the mold (Tissue-Tek Cryomold #4566) filled with OCT (Tissue Plus OCT Compound, Fisher Scientific catalog # 23-730-571). Be careful to remove any air bubbles. Remove air bubbles in OCT bottle, then squeeze out.
- 6.2 Orient the OCT-embedded tissue into the desired position in the mold. Carefully squeeze out more OCT on top of the tissue, again avoiding bubbles. Squeeze enough OCT out until none of the tissue remains exposed.
- **6.3** Freeze the tissue block on dry ice (or in cryostat).
- 6.4 Wrap each block in aluminum foil or place into a small plastic bag. Store the tissue block at -80° C until ready for sectioning.