

Oct 05, 2021

Overlap & Gibson ligation

Shuning Guo¹

¹2021 iDEC NEFU_China



dx.doi.org/10.17504/protocols.io.byrspv6e

2021 iDEC NEFU_China

Shuning Guo

ABSTRACT

This protocol is used to lagate two pieces of DNA together without digesting the fragment with restriction endonucleases.

DOI

dx.doi.org/10.17504/protocols.io.byrspv6e

PROTOCOL CITATION

Shuning Guo 2021. Overlap & Gibson ligation. **protocols.io** https://dx.doi.org/10.17504/protocols.io.byrspv6e

KEYWORDS

Overlap, Gibson assembly

LICENSE

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

CREATED

Oct 04, 2021

LAST MODIFIED

Oct 05, 2021

PROTOCOL INTEGER ID

53778

MATERIALS TEXT

DNA fragments

Primers

ClonExpress II One Step Cloning Kit (Vazyme)

2×High Fidelity Master Mix (MCLAB)

Nanodrop

Thermocycler

Water bath

DdH20

SAFFTY WARNINGS

Please wear gloves for the experiment, don't try to touch the lid after PCR program initiation.

BEFORE STARTING

Frotocols.io

10/05/2021

Citation: Shuning Guo (10/05/2021). Overlap & Gibson ligation. https://dx.doi.org/10.17504/protocols.io.byrspv6e

Set up a small box with ice, put DNA and enzymes on it. Prepare the water bath to 37°C to have Gibson assembly.

Ligation of two DNA fragments by using cases below.
 Step 1 includes a Step case.

Overlap PCR
Gibson Assembly

Preparation of linearized vectors



Overlap PCR

- 2 Select an appropriate cloning site on the vector that will be linearized.
- 3 Vector linearization: the linearized vector can be obtained by digesting the circular vector with restriction enzymes or by reverse PCR.

PCR of the inserts DNA fragments

4 Amplify the insert DNA fragments with homologous sequences (for homologous recombination) of vector-upstream or -downstream by PCR using high fidelity DNA polymerase.

Calculate amount and ratio of linearized vectors and Inserts

- 5 Detect DNA concentration of linearized vectors and inserts by Nanodrop.
- 6 Calculation of the amount of vectors: Molar ratio of vector to insertion is 1:1

Recombination & PCR

7 Set up the following reaction on ice (50μl):

A	В
Forward Primer (10 μM)	1μΙ
Reverse Primer (10 μM)	1μΙ
Fragment1(vector)	X
Fragment2(insertion)	Υ
2×High Fidelity Master Mix (MCLAB)	25µl
ddH2O	Add to 50µl

The primer is used to amplify recombinant DNA fragment/circular DNA.

8 Program the thermocycler as follows:

Α	В
Temperature	Time
95/98°C	5 min
95/98°C	30 s
Tm-3~5°C	30 s
72°C	1kb/min
72°C	5~10 min
16°C	∞

Repeat 30 times in 3-5 steps

- $9 \qquad \text{Use the palm centrifuge to mix the solution in PCR tube.} \\$
- 10 Put the PCR tube into the thermocycler and Run the program.
- 11 Using agarose gel electrophoresis to confirm if correct construct was present.