

Jun 15, 2024

Recovery and preparation for transplantation of cryopreserved vmDA progenitors for transplantation.

DOI

dx.doi.org/10.17504/protocols.io.bp2l622d1gqe/v1

Tyra Fraser¹, Lachlan Thompson²

¹Florey Institute of Neuroscience and Mental Health;

²Florey Institute of Neuroscience and Mental Health, The University of Sydney

ASAP Collaborative Rese...

Team Kirik



courtney.wright Wright

University of Sydney

OPEN ACCESS



DOI: dx.doi.org/10.17504/protocols.io.bp2l622d1gqe/v1

Protocol Citation: Tyra Fraser, Lachlan Thompson 2024. Recovery and preparation for transplantation of cryopreserved vmDA progenitors for transplantation.. protocols.io https://dx.doi.org/10.17504/protocols.io.bp21622d1gqe/v1

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's working

Created: May 31, 2024

Last Modified: June 15, 2024 Protocol Integer ID: 100996

Keywords: Transplantation, Cryopreserved, iPSC, ventral midbrain, recovery., ASAPCRN



Funders Acknowledgement:

Michael J Fox Foundation

Grant ID: ASAP-000497

Abstract

This protocol outlines the recovery of cryopreserved vmDA progenitors. After recovery, this outlines the process to prepare these cells for xenotransplantation.

Guidelines

All work is to be conducted in well sterilised laminar flow hoods designated for human iPSC work where possible to minimise contamination.



Materials

General materials

- PBS -/-
- Accutase
- P10, 20, 200, 1000 plus tips
- 15ml falcon tubes
- 3 small Eppendorf tubes
- Trypan blue
- NBB27 + All
- Rock inhibitor (Ri)

A	В	
NBB27 Base media (For Terminal vmDA) 100ml	+ All (add as needed)	
DMEM/F12 47mL	BDNF (20ng/ml)	
NBM 47mL	GDNF (20ng/ml)	
B27 + VitA 2mL	TGFB3 (1ng/ml)	
N2 1mL	DAPT (10uM)	
ITS-A 1mL	AA (200uM)	
NEAA 1mL	dcAMP (0.25mM)	
GMAX 500uL		
Pen strep 500uL		

Required components for Base media NBB27



Safety warnings

• For hazard information and safety warnings, please refer to the SDS (Safety Data Sheet) for each of the raw materials used.



Recovery of cells

- 1 Prepare NBB27 base media according to the materials table.
- 2 1. Place 4 5 mL of NBB27 media + All + Ri 1:1000 in a 4 15 mL falcon tube.

3m

- 2. Warm cryopreserved cells in hand or in a water bath until a small chunk of ice is remains
- 3. Remove thawed portion into the tube containing the \perp 5 mL (prepared in as per Step 1)
- 4. Take Δ 500 µL of media and use it to thaw the remaining chunk of ice.
- 5. Remove all media from cryopreserved tube and place into the falcon tube with media.
- 6. Spin cells(300 x g, 4°C, 00:03:00).

3 1. Aspirate supernatant. Flick pellet twice.

3m

- 2. Resuspend in \perp 1 mL of NBB27 + All + Ri 1:1000.
- 3. Pipette \perp 10 μ L into a small Eppendorf tube for cell counting. Repeat for a second Eppendorf tube.
- 4. Take the 2 tubes and add \perp 10 μ L trypan blue to cells in each tube.
- 5. Place Δ 10 μ L of mixed cells in haemocytometer.
- 6. Count cells in each quadrant.
- 7. Calculate total number of cells. Repeat this for tube 2 to ensure an accurate cell count.

Total cells = Average count of quadrants x Dilution factor x Volume (ml) x 10^4

- 8. Calculate the total volume needed to resuspend cells to a final density (typically between 100-150K/µl.
- 9. Spin cells(300 x g, 4°C, 00:03:00)



4 1. Label small Eppendorf tube with specific details about the transplant.



- 2. Aspirate supernatant
- 3. Add half the required media on top of the cells gently (i.e. if you have 2 million cells total final volume is 🚨 20 µL to achieve 100 000 cells/uL, so add 🚨 10 µL of media (NBB27 + All + Ri 1:1000) to pellet.
- 4. Using a P20, gently disturb the pellet in a circular motion, taking care not to damage cells by hitting the edge of the tube with the pipette tip.
- 5. Once mixed, take up the suspension once or twice and transfer to a small Eppendorf tube.
- 6. Measure the volume of cell suspension.
- 7. Add the appropriate volume of NBB27 + All + Ri 1:1000 required to reach the final volume.
- 8. Place cells on ice ready for use