

JUN 07, 2023

# OPEN ACCESS

#### DOL

dx.doi.org/10.17504/protocol s.io.5jyl8jow9g2w/v1

**Protocol Citation:** Jie Hao Ou, Yin-Tse Huang 2023. Nanopore amplicon sequencing with DIY adapter. **protocols.io** 

https://dx.doi.org/10.17504/protocols.io.5jyl8jow9g2w/v1

License: This is an open access protocol distributed under the terms of the Creative Commons
Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

**Protocol status:** Working We use this protocol and it's working

Created: Mar 31, 2023

Last Modified: Jun 07, 2023

**PROTOCOL** integer ID:

79804

#### Workflow

#### Nanopore amplicon sequencing with DIY adapter

Jie Hao Yin-Tse Ou<sup>1</sup>, Huang<sup>2</sup>

<sup>1</sup>National Chung Hsing University, Taichung;

<sup>2</sup>Kaohsiung Medical University


Jho



**ABSTRACT** 

Nanopore amplicon sequencing with DIY adapter

1



#### **Preparation of amplicons**

- Use a primer with a HEAD to make amplicons, as in a regular procedure.
  Enzymes with or without proofreading can be used, and purification is not necessary.
- 3 Use a **barcoding index** for the second PCR.

Note:

- 1. non-proofreading enzyme (Taq) must be used to add a A tail to the PCR product.
- 4 Purify the PCR product and adjust the final concentration of the purified DNA to ~50 ng/ul.

## Pooling & 5' Phosphorylation

5

Mix the following materials in order: (10 samples as an example)

A	В
Sterile water	7 ul
10X T4 Polynucleotide Kinase Reaction Buffer (with 1 mM ATP)	2 ul
T4 Polynucleotide Kinase (10U/ul)	1 ul
PCR product (x10 samples)	1 ul x 10 samples = 10 ul

Note: Some manufacturers' buffers require additional ATP to be added to achieve a final reaction concentration of 0.1 mM.

6 Incubate at 37°C for 30 minutes.

30m

7 Heat inactivate by incubating at 65°C for 20 minutes

20m

8 Purify the DNA and adjust the final concentration to ~50 ng/ul.

### **Preparation of Adapter**

1h 4m

- **9** Order the following two primers:
  - Adapter\_top: TTTTTTTCCTGTACTTCGTTCAGTTACGTATTGCT

Adapter\_bottom: GCAATACGTAACTGAACGAAGTACAGG

Preferably, choose **OPC or a higher level** of purification method.

Dilute both primers to 100uM according to the manufacturer's instructions (TE buffer is recommended)

1m

11 Mix both primers together in equal volumes.

1m

12 Incubate the mixture in a dry bath at 95°C for 2 minutes.

Ideally, Adapter\_top and Adapter\_bottom would aneal to form a sticky end of double strand DNA

Allow the mixture to **slowly cool to room temperature** for one hour.

1h

**14** Make 1:10 dilution (5 uM)

Store the mixture at 4°C or in a freezer for long-term storage.

When necessary, divide the mixture into smaller portions to avoid repeated thawing.

### Attach adapter to PCR products.

1h

15 Mix the following materials in order:

A	В
5' Phosphorylated PCR product (50ng/ul)	10 ul
Sterile water	7 ul
10X T4 DNA Ligase Buffer (with 1 mM ATP)	2 ul
Adapter	0.1 ul

A	В
T4 ligase	1 ul (300U or 2.5U in Weiss Unit)

Note: Some manufacturers' buffers require additional ATP to be added to achieve a final reaction concentration of 0.1 mM.

16 Incubate at 16-20 °C for at least 5 01:00:00

1

17 Purify the DNA and adjust the final concentration to ~50 ng/ul.