

MAR 29, 2024

Openion of Gnotobiotic Stickleback Fish

Kat Milligan-McClellan¹

¹University of Connecticut

Dr. Napaaqtuk Lab

Tech. support email: kathryn.milligan-myhre@uconn.edu



Kat Milligan-McClellan University of Connecticut

OPEN ACCESS



DOI:

dx.doi.org/10.17504/protocols.io. n2bvjrd6plk5/v1

Protocol Citation: Kat Milligan-McClellan 2024. Derivation of Gnotobiotic Stickleback Fish. protocols.io

https://dx.doi.org/10.17504/protoc ols.io.n2bvjrd6plk5/v1

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's working

Created: Jan 09, 2019

ABSTRACT

This protocol is used to generate gnotobiotic stickleback fish. Based on the zebrafish protocols, this was optimized for stickleback. See the paper https://doi.org/10.1242/dmm.021881 for the first description of the use of this protocol. This was created by Kat Milligan-McClellan with extensive help from Erika Mittge at the University of Oregon.

GUIDELINES

Use a biosafety cabinet class II to ensure sterility of fish. If this protocol is performed without a biosafety cabinet, sterility drops considerably.

protocols.io

Last Modified: Mar 29, 2024

PROTOCOL integer ID: 19115

Keywords: stickleback, gnotobiotic, germ free, Gasterosteus aculeatus

MATERIALS

Tricaine methanesulfonate MS222 Sigma Aldrich

Petri dishes, untreated, 100mm, sterile

Petri dishes, untreated, 20mm or 60mm, sterile

Kim wipes or paper towels

Sharp pointed dissecting scissors similar to this

Fine point forceps similar to this

Razor

1L and 250ml 0.22µm vacuum filter systems, PES membrane

Two 50ml 0.22µm filters

Gloves

Sterile pediatric pipettes

50ml beakers covered with foil tops and autoclaved

Biosafety cabinet class II

Individually wrapped sterile 25ml and 2ml pipettes

Tissue culture flasks – 25cm², 75cm², 150cm² or 300cm² with 0.2 µm PTFE membranes on caps

Jars with paper towels inside and on the bottom of the jars (to prevent scissors and forceps from being damaged)

Incubator or temperature controlled room for raising fish

Media:

Use double distilled (ddH₂0) or higher purity water (reverse osmosis or ultrapure water AKA Milli-Q or NANA-pur), for all reagents except the 70% ethanol and 10% bleach. Use a minimum of distilled water for the 70% ethanol and 10% bleach.

70% ethanol

- 736ml of 95% ethanol
- Bring to 1L with dH₂O
- Store in air tight container

10% bleach

- 10ml bleach
- 90ml dH₂0

Stickleback medium

- 4g Instant Ocean (goes into solution best if add a little at a time while stirring)
- 1L ddH₂0
- 0.25g sodium bicarbonate

Can be stored at room temperature

10% PVP-I stock solution (Polyvinylpyrrolidone-iodine)

- 0.5g 0.01% free iodine, Western Chemical Inc)
- Bring to 50ml with ddH₂0
- store at room temperature in foil covered, tightly sealed container

0.4% Tricaine, AKA MS222

- 400mg Tricaine ** Tricaine must be pharmaceutical-grade.
- 97.9ml stickleback medium
- Adjust to pH 7.0 with sodium bicarbonate
- Filter sterilize with 0.22um vaccuum filter
 This can be made ahead of time and stored for weeks at -20°C or for up to 1 week at 4°C

Make these fresh every time:

Antibiotic stickleback medium, filter sterlized

- 250ul Ampicillin stock of 100mg/ml (100ug/ml final)
- 25ul Kanamycin stock of 50mg/ml (5ug/ml final)
- 7.8ul Amphotericin B stock of 8mg/ml (250ng/ml final)
- 250ml stickleback medium
- filter sterilize with 250ml 0.22um vacuum filter system, PES membrane

0.003% Bleach solution


- 125ul 6.0% bleach solution
- 250ml stickleback medium
- Filter sterilize with 250ml 0.22um vacuum filter system, PES membrane

0.2% PVP-I solution (Polyvinylpyrrolidone-iodine (0.01% free iodine, Western Chemical Inc)

- 5ml 10% PVP-I stock
- 245ml stickleback medium
- Filter sterilize with 250ml 0.22um vacuum filter system, PES membrane

BEFORE START INSTRUCTIONS

- Tools for dissections should be rinsed in 10% bleach and soaked in 70% ethanol prior to use
- Gloves should be worn throughout the protocol to prevent contamination from skin microbiome
- Any person handling fish should be trained on proper fish care BEFORE starting this
 protocol and should receive IACUC or other training (see ethics statement below)
- 25cm² flasks can hold about 10 eggs; 75cm² flasks can hold about 20 eggs and 50ml of water; 150cm² flasks can hold about 40 eggs and 100ml of water; 300cm² flasks can hold about 80 eggs and 200ml of water



protocols.io

- **6** Spray the outside of the euthanized male with 70% ethanol prior to dissection, and wipe body with Kimwipe or paper towel
- Dissect the testes out of the male fish by cutting from next to the anal vent to jaw, removing or pushing the intestine to the side, and using the sterile forceps to remove the testes. These are generally black but may be silver. Transfer the testes to the top of a sterile petri dish
- **8** When testes have been collected, use a clean, new razor to macerate the testes using lengthwise cuts and cross cuts
- Add 5-10 drops of filter-sterilized antibiotic stickleback medium to the macerated testes with a sterile transfer pipette. Pippette up and down to fully mix the testes. The solution should be cloudy. Transfer 3-5 drops of the testes to each clutch of stickleback eggs. 1 set of testes is typically enough to fertilize up to 3 clutches of eggs.
- 10 Incubate eggs with sperm for 15 minutes at room temperature.
- Add filter-sterilized antibiotic stickleback medium to the fertilized eggs to cover the eggs.

Prepare eggs for cleaning

- 12 Incubate fertilized eggs at 20-23°C until eggs reach 2-8 cell stage, ~2 hours post fertilization
- 13 Transfer fertilized eggs to sterile 100mm petri dishes and rinse in ~100ml sterile antibiotic stickleback medium

- Remove non-viable embryos from fertilized eggs, remove egg goo with a sterile transfer pipette, separate eggs gently with sterile tweezers or paint brushes, and rinse viable embryos with fresh antibiotic stickleback medium 2X
- About 6 hours post fertilization, transfer viable embryos into sterile autoclaved 50ml beakers with foil tops, about 100 eggs per beaker
- 16 add ~40ml filter sterilized stickleback medium to the eggs in the beaker

Prepare the hood

- 17 Clean the following with 70% ethanol and transfer the following items into the hood to minimize number of times entering and exiting the hood (per 100 embryos cleaned):
 - 3 sterile 50ml beakers with foil tops
 - Individually wrapped, sterile transfer pipettes or sterile, individually wrapped 2 ml pipettes
 - 1 L filter sterilized stickleback medium
 - 0.003% bleach
 - 0.2-0.4% PVP-I (some flasks may be contaminated with 0.2% PVP-I, but more fish are likely to die in the 0.4% PVP-I)
 - Large beaker for collecting liquid waste
- 18 Sterilize the items above by exposing them to UV light for a minimum of 10 minutes.
- Turn UV light off, then bring in embryos. Spray outside of beaker with 70% EtOH prior to bringing embryos into the hood. MAKE SURE NO ETHANOL GETS INTO THE BEAKER WITH THE EGGS

Clean surface of chorions 20 Transfer embryos to clean autoclaved, foil covered beaker 21 Pour off all but ~10ml stickleback medium carefully into waste container 22 Transfer remaining 10ml stickleback medium with eggs into clean 50 ml beaker 23 Add ~20ml sterile stickleback medium to old beaker to get remaining eggs 24 Transfer remaining eggs to beaker 25 Bring volume in new beaker up to 50ml with sterile stickleback medium 26 Rinse embryos 3X with 50ml filter sterilized stickleback medium

Mar 29 2024

27

Immerse embryos in ~50ml 0.2-0.4% PVP-I solution for 10 minutes

28	Rinse embryos with sterile stickleback medium 1X
29	Transfer embryos to fresh beaker as in step 21-25
30	Rinse embryos in sterile stickleback medium additional 2X
31	Immerse embryos in 50ml 0.003% bleach for 10 minutes.
32	Rinse embryos in sterile stickleback medium 1X
33	Transfer embryos to fresh beaker as in steps 21-25.
34	Rinse embryos additional 2X in sterile stickleback medium
35	Add sterile stickleback medium to tissue culture flasks.

mprotocols.io

- 25cm² flasks add 19ml of stickleback medium (assumes about 1ml of medium will be used to transfer eggs)
- 75cm² flasks add 48ml of stickleback medium (assumes 2ml of medium in transfer)
- 150cm² flasks add 96ml of water (assumes about 4ml of medium in transfer)
- 300cm² flasks add 194ml of water (assumes about 6ml of medium in transfer)
- Transfer embryos to flasks containing sterile stickleback medium using sterile, individually wrapped pipettes. Tightly close flasks after transfer
 - For 25cm² flasks add up to 10 eggs
 - 75cm² flasks add up to 20 eggs
 - 150cm² flasks add up to 40 eggs
 - 300cm² flasks add up to 80 eggs

Post-cleaning fish husbandry

- Move flasks to incubator in upright position to ensure eggs do not get stuck in the neck of the flask in the transfer
- Incubate embryos in light-controlled 18-20°C in incubator, laying flasks flat. Make sure eggs do not go into the neck of the flask.
- Check for contamination of water by microscopy throughout the experiment. Using an inverted light microscope, examine the inside of the bottom of the flask for cocci, rods, or filamentous microbes, which may be moving or stationary. Presence of microbes indicates contamination
- Daily, record the number of fish dead or not moving in response to external stimuli. Always transfer flasks in upright position and ensure no eggs are in the neck of the flask.
- Fish can remain in germ free flasks until 14 days post fertilization without food. At that point they will require food.

protocols.io

- To determine contamination of water by culture, plate 50ul to 100ul of water on TSA plates and incubate at 20°C. Presence of microbes indicates contamination.
- To determine contamination of flask by microscopy, visualize bottom of flask using inverted light microscopy under a minimum of 40X magnification. Presence of microbes on inside of bottom of flask indicates contamination.
- To determine contamination of flask by 16S PCR, collect water on 0.22um filter, extract DNA from filter, and perform PCR of 16S ribosomal RNA gene using standard 27F and 1492R primers. Presence of a band of about 1400 bp from the PCR product on gel electrophoresis indicates contamination.