



Oct 11, 2022

Manual Tissue Dissociation for Multiome Analysis

Stephen Fisher¹, Marielena Grijalva¹, Rong Guo¹, sarahjoh¹, Hieu Nguyen¹, John Renz², Jean G Rosario¹, Steven Rudich², Brian Gregory¹, Junhyong Kim¹, Kate O'Neill¹ ¹University of Pennsylvania; ²Gift of Life Donor Program

Works for me Share

dx.doi.org/10.17504/protocols.io.8epv59y34g1b/v1

Stephen Fisher University of Pennsylvania

ABSTRACT

This protocol describes dissociation of snap-frozen ovarian tissue in order to isolate nuclei that can be used for downstream analysis. This protocol can also be used on fresh tissue; freezing tissues leads to a slight decrease in viability after tissue thawing and dissociation. We used this protocol on both ovarian and Fallopian tube snap-frozen tissues. This protocol does not aim to isolate intact ovarian follicles and does not attempt to grossly separate ovarian cortex and medulla. Although this protocol details manual tissue dissociation, we have performed automated tissue dissociation using the S2 Singulator with similar results, for both ovarian and Fallopian tube tissue.

dx.doi.org/10.17504/protocols.io.8epv59y34g1b/v1

PROTOCOL CITATION

Stephen Fisher, Marielena Grijalva, Rong Guo, sarahjoh, Hieu Nguyen, John Renz, Jean G Rosario, Steven Rudich, Brian Gregory, Junhyong Kim, Kate O'Neill 2022. Manual Tissue Dissociation for Multiome Analysis. protocols.io

https://dx.doi.org/10.17504/protocols.io.8epv59y34g1b/v1

FUNDERS ACKNOWLEDGEMENT

NIH

Grant ID: U54HD104392

LICENSE

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

CREATED

Aug 05, 2022

LAST MODIFIED

Oct 11, 2022

PROTOCOL INTEGER ID

68253

MATERIALS TEXT

Wash Buffer: 4mL

• 1% UltraPure BSA, 50 mg/mL (Thermo Fisher Scientific; AM2616)



Citation: Stephen Fisher, Marielena Grijalva, Rong Guo, sarahjoh, Hieu Nguyen, John Renz, Jean G Rosario, Steven Rudich, Brian Gregory, Junhyong Kim, Kate O'Neill Manual Tissue Dissociation for Multiome Analysis https://dx.doi.org/10.17504/protocols.io.8epv59y34g1b/v1

- Protector RNase Inhibitor, 0.6U/μL (Millipore-Sigma; 3335399001)
- 1X PBS (Gibco; 14200-075)
- Store at 4°C and keep on ice during use
- The buffer will last for up to 5 days, however the RNase Inhibitor should be added the day of use

Aldrich Catalog #03335399001

⊠UltraPure™ BSA (50 mg/mL) **Thermo Fisher**

Scientific Catalog # AM2616

Scientific Catalog #14200075

NP40 Lysis Buffer: 3mL

- 0.1% Nonidet P40 Substitute (Millipore-Sigma; 74385)
- 10mM Trizma Hydrochloride Solution, pH 7.4 (Millipore-Sigma; T2194)
- 10mM Sodium Chloride Solution, 5M (Millipore-Sigma; 59222C)
- 3mM Magnesium Chloride Solution, 1M (Millipore-Sigma; M1028)
- Nuclease-free water
- Store at 4°C and keep on ice during use
- The buffer will last for up to 5 days
- ⋈ Nuclease-free Water Contributed by users
- Nonidet P40 Substitute Sigma

Aldrich Catalog # 74385

Trizma Hydrochloride Solution pH 7.4 Sigma

Aldrich Catalog #T2194

Sodium chloride Sigma

Aldrich Catalog #59222C-1000ML

Aldrich Catalog #M1028

Protocol:

- Snap-frozen tissue block
- NP40 lysis buffer (see above)
- Ice
- Wash buffer (see above)
- Ice bucket

⊠1.5 mL LoBind tubes

■ Eppendorf Catalog #022431021

.

 \(\omega) \) Trypan Blue Stain (0.4%) for use with the Countess™ Automated Cell Counter **Thermo**

Fisher Catalog #T10282

■ ⊠ Dry Ice Contributed by users

Strainer Corning Catalog #352340



Hemacytometers with Cover Glass Marienfeld EF16034F

Pellet Pestle

Kimble Kontes K749520-1590

1.5 mL Polypropylene w/o Microtubes RNAse DNase free

VWR® Pour-Boat Weighing Dishes flat-bottomed dish

VWR International 10803-166

BEFORE STARTING

Prepare the Wash Buffer and NP40 Lysis Buffer no more than 5 days in advance.

Methods 22m

- 1 Keep snap-frozen tissue specimen on dry ice, after removing from freezer and until ready to begin.
- 2 Using a disposable weigh boat, quickly weigh the tissue specimen while still frozen.
- 3 Mince tissue with a fresh scalpel until tissue is the size of dry rice grains (or smaller) and transfer to a 1.5mL Eppendorf tube.
- 4 Add 300µL NP40 lysis buffer. Homogenize with pellet pestle 15X.

protocols.io

3

Citation: Stephen Fisher, Marielena Grijalva, Rong Guo, sarahjoh, Hieu Nguyen, John Renz, Jean G Rosario, Steven Rudich, Brian Gregory, Junhyong Kim, Kate O'Neill Manual Tissue Dissociation for Multiome Analysis https://dx.doi.org/10.17504/protocols.io.8epv59y34g1b/v1

7m Add 1mL NP40 lysis buffer and incubate on ice. The incubation time is tissue dependent. a. Ovarian tissue: **© 00:04:00** b. Fallopian tube tissue: © 00:03:00 Strain through a 40µm filter. 5m 7 Centrifuge at 500g, & 4 °C for © 00:05:00. Remove supernatant without disturbing the pellet. Add 1mL wash buffer slowly, without mixing. 5m 10 Incubate on ice for **© 00:05:00**. Slowly pipet to resuspend the pellet. 11 5m Centrifuge at 500g, & 4 °C for © 00:05:00. Remove supernatant without disturbing the pellet. 13 Add 500µL-1mL wash buffer and pipet to resuspend. 14 Tip: Additional washes may be necessary based on the quality control checks in step 15 (do not exceed 4 washes).

other debris.

m protocols.io

15

4

Quality Control: Check under microscope for debris. There are specific acceptable levels of blebbing that we are looking for, specifically levels as represented in images A and B from Panel A in the <u>10X Genomics document</u> <u>CG000375</u>. We're looking for <5% live cells (ideally no cells), minimal to no clumping, no large debris, minimal to no

Citation: Stephen Fisher, Marielena Grijalva, Rong Guo, sarahjoh, Hieu Nguyen, John Renz, Jean G Rosario, Steven Rudich, Brian Gregory, Junhyong Kim, Kate O'Neill Manual Tissue Dissociation for Multiome Analysis https://dx.doi.org/10.17504/protocols.io.8epv59y34g1b/v1

Using Trypan blue, load nuclei onto a hemocytometer and count.

Tip: Step 14 can be repeated 3 more times if a large amount of debris is still present (do not exceed 4 total washes).

- Process the isolated nuclei with the 10X Genomics permeabilization protocol described in section 1.2 Nuclei Permeabilization of "Nuclei Isolation from Complex Tissues for Single Cell Multiome ATAC + Gene Expression Sequencing demonstration protocol."
- 17 Process the permeabilized nuclei with the 10X Genomics Multiomic ATACseq and RNAseq protocols described in "Chromium Next GEM Single Cell Multiome ATAC + Gene Expression Reagent Kits User Guide."

Step-specific processing notes are included below.

- 17.1 **Step 3.1**: During dynabeads cleanup, aspirate the entire supernatant including the white debris at the bottom.
- 17.2 **Steps 5.1 and 6.1**: When computing the number of PCR cycles, we round up, when within about 100 nuclei/cells of the threshold for the number of PCR cycles.
- 17.3 **Step 7.5**: When computing the number of PCR cycles, we do not round up when near the threshold for the number of PCR cycles.
- 17.4 Quality control of ATAC library: While we require the Agilent Bioanalyzer trace at step 5.3 to contain the five expected peaks (0-nucleosome, 1-nucleosome, 2-nucleosomes, 3-nucleosomes, and multiple-nucleosomes), we are somewhat lenient in the expectation that the 1-nucleosome peak will be higher than the other peaks. If peaks are missing, we don't proceed with the sample. If the peaks are visible but the material concentration is low, we recommend rebuilding the library from the cDNA step 4.3.
- 17.5 **Quality control of cDNA library**: The peak of the Agilent Bioanalyzer trace at step 6.3 should roughly be gaussian centered around 480. If the peak is to narrow or asymmetric, then size selection was not performed correctly and we recommend rebuilding the library from the cDNA step 4.3.
- 17.6 **Quality control of GEX libraries**: The peak of the Agilent Bioanalyzer trace at step 7.7 should roughly be gaussian centered around 480. If the peak is to narrow or asymmetric, then size selection was not performed correctly and we recommend rebuilding the library from the cDNA step 4.3.
- 17.7 **Tip**: An Illumina MiSeq run can prove helpful to rebalance the libraries, if needed, and confirm the libraries are properly binding to the flow cell. MiSeq results do not have sufficient sequencing depth for downstream 10X protocol analyses.