

Version 11 ▼

May 04, 2020

# In vitro transcription of guide RNAs and 5'-triphosphate removal V.11

Mark Dewitt<sup>1</sup>, Julia Wong<sup>1</sup>, Beeke Wienert<sup>1</sup>

<sup>1</sup>UC BERKELEY-IGI

1 Works for me

dx.doi.org/10.17504/protocols.io.bfxfjpjn

### CornLab



#### **ABSTRACT**

sgRNA template assembly, in vitro T7 transcription, and sgRNA column cleanup to remove 5'-triphosphate groups

**EXTERNAL LINK** 

https://doi.org/10.1371/journal.pbio.2005840

THIS PROTOCOL ACCOMPANIES THE FOLLOWING PUBLICATION

Wienert B, Shin J, Zelin E, Pestal K, Corn JE (2018) In vitro–transcribed guide RNAs trigger an innate immune response via the RIG-I pathway. PLoS Biol 16(7): e2005840. doi: 10.1371/journal.pbio.2005840

### **GUIDELINES**

The primers used are: one long, variable oligo that carries the T7 promoter and desired guide sequence; an 82-nt constant oligo that carries the 3' end of the sgRNA; two short external primers for amplification.

# **Assembly Oligos:**

T7FwdVar:


GGATCCTAATACGACTCACTATAG---guide-sequence---GTTTTAGAGCTAGAA

T7RevLong:

AAAAAAGCACCGACTCGGTGCCACTTTTTCAAGTTGATAACGGACTAGCCTTATTTTAACTTGCTATTTCTAGCTCTAA

## **Amplification Primers:**

T7FwdAmp: GGATCCTAATACGACTCACTATAG T7RevAmp: AAAAAAGCACCGACTCGG



Odd numbers: just PCR product Even numbers: with T7E1 treatment

Here's a gel that shows some good guides and some that didn't work examples of more promising looking guides would be #'s 20, 22, 26, and 28.

**Designing the guide sequence:** The T7 transcript starts with the G before the dashes in the Fwd assembly oligo. If your target calls for a G at the 5' end of the guide, use the one already included in T7FwdVar design. If your target calls for a different base at the 5' end, put the whole guide sequence in T7FwdVar; there will be an extra G on the end that should have minimal effect, unless your guide is quite short.

**Making the template:** we have used the Phusion-HF DNA polymerase. Although the amplification primers have quite different Tm's, they work together fine.

mprotocols.io

05/04/2020

**Citation:** Mark Dewitt, Julia Wong, Beeke Wienert (05/04/2020). In vitro transcription of guide RNAs and 5'-triphosphate removal. <a href="https://dx.doi.org/10.17504/protocols.io.bfxfipjn">https://dx.doi.org/10.17504/protocols.io.bfxfipjn</a>

#### STEPS MATERIALS

NAME	CATALOG #	VENDOR
DNase I (RNase-free) - 1,000 units	M0303S	New England Biolabs
Alkaline Phosphatase, Calf Intest (CIP) - 1,000 units	M0290S	New England Biolabs
HiScribe T7 High Yield RNA Synthesis Kit - 50 rxns	E2040S	New England Biolabs

# Design sgRNA and order PCR oligos.

Add the desired protospacer sequence to the T7FwdVar oligo and order the oligo from your favorite oligonucleotide supplier. There are many programs available for protospacer design that attempt to optimize on- and/or off-target activity. Which program is most useful depends upon many factors including type of editing, organism being edited, etc. Choice of protospacer design program is beyond the scope of this protocol.

The transcript will start with the bolded G just 5' of the dashes in the T7FwdVar oligo. T7 RNA polymerase requires a 5' G for proper transcript initiation. If your protospacer has a G at the 5' end, you can omit it from the T7FwdVar design to avoid duplication of the G. If your protospacer has a C, T, or A at the 5' end, add the whole protospacer sequence to T7FwdVar. In this case, there will be an extra G added to the 5' end of the protospacer, but literature indicates this will have minimal effect unless your guide is very short.

#### Primers:

 $\label{thm:control} T7FwdVar\ oligo\ (5'-GGATCCTAATACGACTCACTATA{\textbf{G}}--protospacer\ sequence--GTTTTAGAGCTAGAA-3')\ T7RevLong\ oligo\ (5'-$ 

AAAAAAGCACCGACTCGGTGCCACTTTTTCAAGTTGATAACGGACTAGCCTTATTTTAACTTGCTATTTCTAGCTCTAAAAC-3')

T7FwdAmp primer (5'-GGATCCTAATACGACTCACTATAG-3')

T7RevAmp primer (5'-AAAAAAGCACCGACTCGG-3')

### Generate in vitro transcription DNA template

2 For each T7FwdVar oligo you designed, set up the following PCR (total volume should be 20.0 μL). Make sure everything is RNase free and filter tips are used. Furthermore, wipe down everything (in every step of protocol) with RNase Away to ensure no contamination with RNAse.

13.4 µl DEPC-treated H<sub>2</sub>O

4.0 uL 5x Phusion HF Buffer

 $0.8 \mu l 10 \, mM \, dNTPs$ 

 $0.4\,\mu l\, T7 Fwd Var\, (1\,\mu M)$ 

0.4 μl T7RevLong (1 μM)

0.4 μl T7FwdAmp (100 μM)

 $0.4 \,\mu l \, T7 Rev Amp \, (100 \,\mu M)$ 

0.2 μl Phusion HF DNA polymerase (2u/μl)

If making multiple sgRNA templates, prepare a master mix with all components except T7FwdVar. Include a no template control (omit T7FwdVar).

# Primers:

T7FwdVar oligo (5'-GGATCCTAATACGACTCACTATA**G**--protospacer sequence—GTTTTAGAGCTAGAA-3') T7RevLong oligo (5'-

AAAAAAGCACCGACTCGGTGCCACTTTTTCAAGTTGATAACGGACTAGCCTTATTTTAACTTGCTATTTCTAGCTCTAAAAC-3')

T7FwdAmp primer (5'-GGATCCTAATACGACTCACTATAG-3')

T7RevAmp primer (5'-AAAAAAGCACCGACTCGG-3')

### In vitro transcription DNA template PCR

3 Run PCR: 95° 30 sec

Citation: Mark Dewitt, Julia Wong, Beeke Wienert (05/04/2020). In vitro transcription of guide RNAs and 5'-triphosphate removal. <a href="https://dx.doi.org/10.17504/protocols.io.bfxfipin">https://dx.doi.org/10.17504/protocols.io.bfxfipin</a>

95° 10 sec 57° 10 sec 72° 10 sec 15x steps 2-4 72° 2 min 4° hold

No PCR cleanup necessary at this point

# In vitro T7 transcription

4 We like to use HiScribe T7 High Yield RNA Synthesis Kit but any T7 RNA synthesis kit should be fine.

Mix the following to make 20 µl total T7 transcription mix

volume	reagent
2 µl	10x Buffer 1x
2 µl	ATP (100 mM), 10 mM
2 µl	GTP (100 mM), 10 mM
2 µl	CTP (100 mM), 10 mM
2 µl	UTP (100 mM), 10 mM
8 µl	DNA template from Step 3
2 µl	T7 RNA polymerase mix

HiScribe T7 High Yield RNA Synthesis
Kit - 50 rxns
by New England Biolabs
Catalog #: E2040S

5 Incubate transcription mix for ~18 hours (over night) at 37° in a thermocycler

**③18:00:00** 

**8 37 °C** 

# DNA template removal

6 Remove DNA template by adding 1 μl of RNase-free DNase; incubate 15 min at 37C in thermocycler © 00:15:00 37C incubation



& 37 °C

# Removal of 5'-triphosphate groups

7 T7 in vitro transcription results in RNA carrying a 5'-triphosphate group. This triggers a RIG-I-mediated innate immnue response in mammalian cells and can cause cell death, particularly in primary cells. We highly recommend treating your IVT sgRNA with Alkaline Calf Intestinal Phosphatase (CIP) before proceeding to the purification step. We found that CIP treatment must be rigorous to completely remove all 5-PPP groups from your RNA. However, CIP binds tightly to RNA and NEB recommends to only use the minimal amount needed.

**⋈** protocols.io 3 05/04/2020

Citation: Mark Dewitt, Julia Wong, Beeke Wienert (05/04/2020). In vitro transcription of guide RNAs and 5'-triphosphate removal. <a href="https://dx.doi.org/10.17504/protocols.io.bfxfipin">https://dx.doi.org/10.17504/protocols.io.bfxfipin</a>

Bring your IVT mix to a total volume of 88 ul with RNAse-free water

8 Add 10ul of NEB buffer 2.1 (comes with the CIP enzyme) Add 2ul (20 units) of CIP



Alkaline Phosphatase, Calf Intest (CIP)

-1,000 units

by New England Biolabs

Catalog #: M0290S

9 Mix well and incubate at 37C for 3h

**© 03:00:00** 

& 37 °C

### sgRNA purification

sgRNAs need to be purfied before transfection. There are different methods one could purify their sgRNAs. We found that while SPRI bead clean-up of RNAs is quick and gives reliable yields (see older versions of protocol), SPRI bead purified sgRNAs still cause an elevated immune response even after CIP treatment. We therefore tested different column purification kits and found that column purification of sgRNAs completely eliminates the immune response after CIP treatment.

We use the Qiagen RNeasy Mini Prep Kit and follow the manufacturer's instructions with the following modifications:



Yields of from column purification can be low as the sgRNAs are small and most kits are designed to bind longer RNAs. We found the Qiagen RNeasy kit works ok, but others recommend the miRNeasy kit from Qiagen. It might be worth trying a few different kits to optimize your yield.

- 11 Add 350  $\mu$ l RLT Buffer to the sample
- 12 Add 550 μl 100% ethanol
- 13 Tranfer ~500 µl to an RNeasy mini spin column; spin for 15 sec
  Then transferr the remainder onto the same column; spin for 15 sec
- 14 Add 500 µl RPE Buffer; spin 15 sec Repeated this wash step
- 15 Moved spin column to a new collection tube and spin for 1 min to dry the membrane completely

- 16 Move spin column to an RNAse-free 1.5 ml microfuge tube Add 20-30 µl DEPC-treated H2O; spin 1 min Optional: Repeat the elution to collect any remaining RNA
- 17 Measure your RNA concentration by Nanodrop or Qubit. Store sgRNAs at -80C