

FEB 28, 2024

OPEN ACCESS



DOI:

dx.doi.org/10.17504/protocols.io. 14egn35mpl5d/v1

Protocol Citation: Roshni Jaffery, Ningbo Zheng, Jiakai Hou, Ashley Guerrero, Si Chen, Chunyu Xu, Nicholas A. Egan, Ritu Bohat, Weiyi Peng 2024. Cytotoxicity Assay Protocol. protocols.io

https://dx.doi.org/10.17504/protocols.io.14egn35mpl5d/v1

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's working

Cytotoxicity Assay Protocol

Roshni Jaffery^{1,2}, Ningbo Zheng^{1,2}, Jiakai Hou^{1,2}, Ashley Guerrero^{1,2}, Si Chen^{1,2}, Chunyu Xu^{1,2}, Nicholas A. Egan^{1,2}, Ritu Bohat^{1,2}, Weiyi Peng^{1,2}

¹Department of Biology and Biochemistry, University of Houston, Houston, TX, USA;

ASAP Collaborative Research Network

LRRK2



sarfraz.ahmed

ABSTRACT

This is the protocol for cytotoxicity assay in cancer cell lines using flow cytometry.

MATERIALS

- 1. Tumor cell line
- 2. Tumor-reactive T cells
- 3. Tumor cell medium: RPMI 1640 (Gibco 11875) + 10% Fetal Bovine Serum (FBS) complete mixture

1000X beta-mercaptoethanol (55mM)

- 5. 1X Phosphate-buffered saline (PBS)
- 6. FACS Buffer: 2% FBS in PBS
- 7. APC-conjugated rabbit anti-active caspase 3 Ab
- 8. BD Cytofix/CytopermTM Fixation/Permeabilization Kit
- 9. Fixation/permeabilization solution
- 10.BD Perm/WashTM Buffer

²Aligning Science Across Parkinson's Collaborative Research Network

motocols.io

Created: Feb 28, 2024 Last Modified: Feb 28, 2024 PROTOCOL integer ID: 95903 **Keywords:** cytotoxicity assay, cancer cell lines, flow cytometry **Funders Acknowledgement:** Aligning Science Across Parkinson's (ASAP) Grant ID: ASAP-000312 1 Begin T cell culturing a week prior. Grow and culture tumor cell lines. Ensure the cells are not over-confluent. 2 Split the tumor cells the day before the assay. Perform the cytotoxic assay as described in next steps. 3 Count tumor cells. Collect 3-5M cells for each cell line. 4 Centrifuge the cells and wash the pellet once with PBS. Ensure that all media is washed off as this can inhibit the staining. 5 Aspirate the supernatant and leave as little PBS as possible

protocols.io

- Re-suspend cells in culture medium at the appropriate ratio for the experiment (1X10⁶ / ml for 50,000 cells/50ul/well or about ~80% confluent) using 96 well round well plate with 50,000 cell tumor and in triplication.
- Add 50 ul of T cell suspension diluted to achieve the desired E:T ratio. Below is an example of how to set up E:T ratios:

A	В	С
ET Ratio(s)	T cells/50ul /well	Tumor cells/50ul/well
0:1	0 (only with T cell medium)	5 x104 cells
1:1	5 x104 cells	5 x104 cells
3:1	1.5x105 cells	5 x104 cells

- 8 Centrifuge the mixed cells in the tubes at 300 rpm for 5 minutes to gently pellet the cells. Incubate for 3 hours at 37⁰C.
- Add 150ul PBS into the plate and then centrifuge at 2000rpm for 5min.
- Remove the supernatant and add then 100ul/well Trypsin. The plate is incubated at 37C incubator for 3-5mins.
- 11 Add 100ul FACS buffer to stop the trypsinization and centrifuge at 2000rpm for 5 min.
- 12 Remove the supernatant carefully.

Oct 28 2024

Oct 28 2024