



## Nov 05, 2020

# © Isolation of Stromal Vascular Fraction (SVF) from mouse brown adipose tissue (BAT) for single cell RNA-seq

## Farnaz Shamsi<sup>1</sup>

<sup>1</sup>Section on Integrative Physiology and Metabolism, Joslin Diabetes Center, Harvard Medical School, Boston, MA, USA



### **ABSTRACT**

This protocol outlines the procedure for the isolation of the Stromal Vascular Fraction (SVF) from mouse brown adipose tissue (BAT) for single cell RNA-seq. This protocol uses a combination of Collagenase I and Dispase II to digest freshly isolated BAT. Compared to using Collagenase I alone, this combination results in a more efficient dissociation of the adipose vasculature.

#### **ATTACHMENTS**

Isolation\_of\_Stromal\_Vasc ular\_Fraction\_(SVF)\_from\_ mouse\_brown\_adipose\_tis sue\_(BAT)\_for\_single\_cell\_ RNA-seq.pdf

DOI

dx.doi.org/10.17504/protocols.io.bj64krgw

#### PROTOCOL CITATION

 $\label{eq:sample_scale} Farnaz\,Shamsi\,2020.\,Isolation\,of\,Stromal\,Vascular\,Fraction\,(SVF)\,from\,mouse\,brown\,adipose\,tissue\,(BAT)\,for\,single\,cell\,RNA-seq.\,\textbf{protocols.io}$ 

https://dx.doi.org/10.17504/protocols.io.bj64krgw

## **KEYWORDS**

stromal vascular fraction, mouse brown adipose tissue, brown adipose tissue, single cell RNA-seq, RNA-seq

## LICENSE

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

CREATED

Aug 22, 2020

LAST MODIFIED

Nov 05, 2020

## OWNERSHIP HISTORY

Aug 22, 2020 Emily Hasser University of Washington

Nov 05, 2020 Farnaz Shamsi

PROTOCOL INTEGER ID

40892

ATTACHMENTS

```
Isolation_of_Stromal_Vasc
 ular Fraction (SVF) from
 mouse_brown_adipose_tis
 sue_(BAT)_for_single_cell_
      RNA-seq.pdf
MATERIALS TEXT
```

**MATERIALS** 

**⊠** Dead Cell Removal Kit **Miltenyi** 

Biotec Catalog #130-090-101

Corning® 40µm Cell

Strainer Corning Catalog #431750

**MS** Columns **Miltenyi** 

Biotec Catalog #130-042-201

**X** ACK Lysing Buffer

(1X) Lonza Catalog #10-548E

X RNaseZap™ RNase Decontamination Solution Thermo Fisher

Scientific Catalog #AM9780

Strainer Corning Catalog #352360

MACS Separator Miltenyi Biotec

**Digestion Media:** 

Corporation Catalog #LS004196

⊠ Dispase (5 U/mL) Stemcell

Technologies Catalog # 07913

⊠ Bovine Serum Albumin (BSA): Gemini Bio Products BSA V FATTY ACID FREE 100G Fisher

Scientific Catalog #50-753-3073

₩ HBSS: Corning® Hanks Balanced Salt Solution 1X with calcium and magnesium

Corning Catalog #21-020-CM

**Growth Media:** 

Fisher Catalog #11965118

SAFETY WARNINGS

For hazard information and safety warnings, please refer to the SDS (Safety Data Sheet).

ABSTRACT

This protocol outlines the procedure for the isolation of the Stromal Vascular Fraction (SVF) from mouse brown adipose tissue (BAT) for single cell RNA-seq. This protocol uses a combination of Collagenase I and Dispase II to digest freshly isolated BAT. Compared to using Collagenase I alone, this combination results in a more efficient

mprotocols.io 11/05/2020

Citation: Farnaz Shamsi (11/05/2020). Isolation of Stromal Vascular Fraction (SVF) from mouse brown adipose tissue (BAT) for single cell RNA-seq. https://dx.doi.org/10.17504/protocols.io.bj64krgw

dissociation of the adipose vasculature.

BEFORE STARTING

Prepare the digestion media containing 1.5 mg/ml Collagenase I, 2.5 U/ml Dispase, and %2 BSA in HBSS buffer.

Warm to § 37 °C.

Prepare growth media by adding FBS (%10) to DMEM. Warm to § 37 °C.

- 1 Sacrifice the mouse.
- 2 Spray the animal extensively with 70 % EtOH and RNaseZap™.
- 3 Dissect interscapular brown adipose tissue (BAT). If tissues from multiple animals are being dissected, store them in HBSS until all of them are dissected.
- 4 C

Mince the tissue to very fine pieces in a 50 ml Falcon tube. Add 110 mL digestion media for each BAT.

5

Place the tubes in a water bath or incubator with a shaker/rotator at § 37 °C for © 00:45:00 .

- 6 Remove the tissue from the incubator and vortex for © 00:00:10.
- 7

Centrifuge at 300 x g, 4°C, 00:10:00 in a swinging bucket centrifuge.

- 8 Aspirate the supernatant carefully not to disturb the pellet of SVF cells.
- 9 Resuspend the pellets in **10 mL growth media**.
- 10

Filter through a 100 μm cell strainer into a fresh 50 ml tube. Wash the tube with an additional **10 mL** and filter

through the cell strainer.



Centrifuge at **300 x g, 00:07:00**.

- 12 Completely remove supernatant and re-suspend the pellet in **□2 mL sterile ACK lysis buffer**; place **§ On ice** for **⋄00:05:00**.
- 13

Filter through a 40  $\mu$ m cell strainer into a fresh 50 ml tube. Wash the tube with  $\Box$ 20 mL growth media and filter through the cell strainer.

14

Centrifuge at **300 x g, 00:07:00**.

- 15 Resuspend the pellet in  $\square$ 1 mL %1.5 BSA in PBS .
- 16 Use  $\blacksquare 10 \ \mu I$  of the cell suspension for cell counting and viability assessment.
- 17

Centrifuge the cell suspension 300 x g, 00:05:00.

18

Resuspend the cells in  $\[ \Box 100 \ \mu I$  dead cell removal bead solution . Incubate the samples for  $\[ \odot 00:15:00 \]$  at  $\[ \& Room \ temperature \]$ .

- 19 Prepare the binding solution by diluting the 20X solution in sterile ddH20.
- Place the MS columns on the MACS separator. Prepare each column by rinsing it with **0.5 mL 1X binding solution**. Let the solution pass through the column.

- 21 Add **3900 μl 1X binding solution** to each sample and apply cell suspension onto the column.
- 22 Collect effluent in a 2 ml low bind tube as live cell fraction.
- 23

Rinse the column with an additional  $\square 1$  mL 1X binding solution.

- 24 Use **10 μl sample** for cell counting and viability assessment.
- 25

Centrifuge the cell suspension  $300 \times g$ , 00:05:00.

- 26 Resuspend the cells in  $\Box$ 50  $\mu$ l  $\Box$ 100  $\mu$ l %1.5 BSA in PBS .
- 27 Keep the cell suspension & On ice and proceed to 10x Genomics Single Cell Protocol. Minimize the time between cell preparation and chip loading.