



Sep 19, 2020

© Bulk EV staining with CFDA-SE (with NAP-5 purification)

Aizea Morales Kastresana¹, Bryce Killingsworth¹, Jennifer Jones¹

¹Translational Nanobiology Section, Laboratory of Pathology, Center for Cancer Research, National Cancer Institute, National Insti

1 Works for me dx.doi.org/10.17504/protocols.io.ber9jd96

Translational Nanobiology Section



ABSTRACT

A protocol for bulk CFSE staining of EVs.

EXTERNAL LINK

https://www.nature.com/articles/s41598-017-01731-2

THIS PROTOCOL ACCOMPANIES THE FOLLOWING PUBLICATION

Morales-Kastresana, A., Telford, B., Musich, T.A. et al. Labeling Extracellular Vesicles for Nanoscale Flow Cytometry. Sci Rep 7, 1878 (2017). https://doi.org/10.1038/s41598-017-01731-2

dx.doi.org/10.17504/protocols.io.ber9jd96

PROTOCOL CITATION

Aizea Morales Kastresana, Bryce Killingsworth, Jennifer Jones 2020. Bulk EV staining with CFDA-SE (with NAP-5 purification). protocols.io

https://dx.doi.org/10.17504/protocols.io.ber9jd96

MANUSCRIPT CITATION please remember to cite the following publication along with this protocol

Morales-Kastresana, A., Telford, B., Musich, T.A. et al. Labeling Extracellular Vesicles for Nanoscale Flow Cytometry. Sci Rep 7, 1878 (2017). https://doi.org/10.1038/s41598-017-01731-2

EXTERNAL LINK

https://www.nature.com/articles/s41598-017-01731-2

KEYWORDS

flow cytometry, EVs, CFSE, bulk staining

This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

CREATED

Apr 07, 2020

LAST MODIFIED

Sep 19, 2020

OWNERSHIP HISTORY

Apr 07, 2020 Bryce Killingsworth

Aug 22, 2020



Translataional Nanobiology Section, Laboratory of Pathology, Center for Cancer Research, National Cancer Institute, National Institutes of Health

6

PROTOCOL INTEGER ID

35361

GUIDELINES

- When possible CFDA-SE dye and CFSE-stained EVs should be protected from significant light exposure
- Fresh aliquots of CFDA-SE should be prepared from solid CFDA-SE dye every few months to avoid using dye with diminished dying ability due to hydrolysis (however in our lab older aliquots of dye have been used without reduced staining capacity)
- See this link for useful information about handling CFSE and using it for labeling cells for flow cytometry:

mprotocols.io

09/19/2020

Citation: Aizea Morales Kastresana, Bryce Killingsworth, Jennifer Jones (09/19/2020). Bulk EV staining with CFDA-SE (with NAP-5 purification). https://dx.doi.org/10.17504/protocols.io.ber9jd96

 $\underline{https://med.virginia.edu/flow-cytometry-facility/wp-content/uploads/sites/170/2015/10/Protocol-for-CFSE-Labeling.pdf}$

MATERIALS

NAME	CATALOG #	VENDOR
DPBS	14190	Invitrogen - Thermo Fisher
DMSO, Anhydrous	D12345	Thermo Fisher
Vybrant™ CFDA SE Cell Tracer Kit	V12883	Thermo Fisher
illustra NAP-5 Columns	17085301	Ge Life Sciences

MATERIALS TEXT

For preparing CFDA-SE aliquots:

- 1 vial of solid dye from Vybrant CFDA-SE Cell Tracer Kit
- Anhydrous DMS0
- Small volume tubes for aliquoting CFDA-SE (0.5 mL or PCR tubes)
- Large volume tube (5 mL snap tube or 15 mL conical) for diluting CFDA-SE

For staining EVs with CFDA-SE:

- 1 aliquot of CFDA-SE
- 1 Nap-5 column
- 1 500 mL bottle of DPBS
- 1 ring stand to hold Nap-5 column
- Eppendorf 0.5 mL and 1.5 mL LoBind tubes
- Preparation of EVs to stain
- Foil or other cover to protect stained EVs from light
- 37 °C water bath or heat block

DISCLAIMER:

This protocol summarizes key steps for a specific type of method, which is one of a collection of methods and assays used for EV analysis in the NCI Translational Nanobiology Section at the time of submission of this protocol. Appropriate use of this protocol requires careful, cohesive integration with other methods for EV production, isolation, and characterization.

Preparing CFDA-SE dye aliquots

- 1 Determine whether or not you need to prepare new aliquots of CFDA-SE dye.
- 2 Let a new vial of solid CFSE-DA dye warm to RT (should take less than 10 minutes.)
- 3 Per the Vybrant™ CFDA SE Cell Tracer Kit instructions, sissolve the solids in the vial in □90 μl anhydrous DMSO (based on the quantity of dye in each vial this creates a [M]10 Milimolar (mM) solution.)
- 4 Dilute the solution to □4500 μI total volume with the same anhyrous DMSO, creating a ™200 Micromolar (μM) solution.
- 5 Aliquot volumes of choice into tubes and freeze at & -20 °C, under desiccating conditions to prevent dye hydrolysis during storage.

Dying EVs with CFDA-SE

- 6 Warm one [κ]200 Micromolar (μΜ) aliquot of CFDA-SE in your hand, or in a § 37 °C water bath until just thawed.
- Dilute the CFDA-SE with DPBS to a concentration of [M]40 Micromolar (μM), pipetting then vortexing to ensure the DMSO in the aliquot fully mixes with the DPBS.
- Prepare a mixture of EVs in DPBS, diluting the mixture to $\Box 50 \ \mu I$ in a 0.5 mL low protein binding tube.

9	Pipette □50 μl	of [M]40 Micromolar (μM)	CFDA-SE into the tube with the EV mixture and vortex to mix
---	-----------------------	--------------------------	---

10	Cover with foil and float onto a	${\mathfrak z}$ 37 ${}^{\circ}{\mathbf C}$ water bath for 2 hours, inverting and flicking the tube halfway through the
	incubation	

Removing free dye with Nap-5 size exclusion column

- 11 Remove top and bottom caps from column and equilibrate with ~ **10 mL** of DPBS. Ensure that the column is flushed continuously and does not dry
- 12 Mark 2 Eppendorf LoBind 1.5 mL tubes at the 0.5 mL line on the side of the tube with a pen
- 13 Vortex and quickly spin down stained EV mixture
- 14 The moment after the last drop of buffer elutes from the Nap-5 column, load the entire **100 μl** volume of EVs on top of the gel bed of the column and immediatly begin collecting eluate in the first marked 1.5 mL tube.
- 15 The moment after the loaded EV mixture has been absorbed into the Nap-5 gel, gently fill the buffer reservoir at the top of the column to the top, using ~ 3 mL of DPBS
- $16 \quad \text{After } \ \textbf{_0.5 mL} \ \text{ of eluate has filled the first } 1.5 \, \text{mL tube, start collecting eluate in the second } 1.5 \, \text{mL tube}$
- 17 Upon elution of **Q0.5 mL** into the second 1.5 mL tube, the Nap-5 column can be filled with DPBS and flushed
- 18 The first 1.5 mL tube is considered Fractions 1 and 2 and should consist of void DPBS and the second 1.5 mL tube is considered Fraction 3 and 4 and sholud consist of eluted EVs
- 19 The column should be flushed with ~ 🖫 10 mL of DPBS then loaded with 🖫 3 mL of filtered 20% Ethanol for storage