

JAN 25, 2024

OPEN ACCESS



DOI:

dx.doi.org/10.17504/protocols.io. bp2l6xwmklqe/v1

Protocol Citation: Michael X. Henderon, Lindsay Meyerdirk 2024. α-Synuclein Protein Preparation (Large scale). protocols.io

https://dx.doi.org/10.17504/protoc ols.io.bp2l6xwmklqe/v1

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

Protocol status: Working We use this protocol and it's working

Created: Dec 21, 2023

③ α-Synuclein Protein Preparation (Large scale)



In 1 collection

Michael X. Henderon¹, Lindsay Meyerdirk¹

¹Van Andel Institute



michael.henderson

ABSTRACT

This protocol details α -synuclein protein preparation in a large scale.

ATTACHMENTS

932-2406.docx

GUIDELINES

Adapted from: Xiao Tu, Kelvin Luk, Jonathan Branch, Patrick O'Brien, Dustin Covell, Katelyn Becker, Volpicelli-Daley, Laura A et al. "Addition of exogenous α-synuclein preformed fibrils to primary neuronal cultures to seed recruitment of endogenous α -synuclein to Lewy body and Lewy neurite-like aggregates." Nature protocols vol. 9,9 (2014): 2135-46. doi:10.1038/nprot.2014.143

Last Modified: Jan 25, 2024

MATERIALS

PROTOCOL integer ID: 93624

Funders Acknowledgement: Aligning Science Across

Parkinson's

Grant ID: ASAP-020616

Materials

- LB + 100 mg/L ampicillin (LB/Amp) plates
- Competent BL21(DE3) RIL cells (Stratagene- A) (20 µL aliquots)
- α-synuclein gene of interest cloned into pRK172 Ndel-HindIII site
- 100mg/mL Ampicillin stock
- 40 mL Dounce homogenizer and pestle A
- Dialysis tubing (Spectrum Labs, Membrane tubing 12-14 kD)
- Fisher Scientific Sonic Dismembrator Model 500 (Sonicator)
- FPLC
- Collection tubes
- Superdex 200 Column
- 1000 mL 0.22 μm filter unit
- 15% SDS—PAGE gels
- Amicon Ultra Centrifugal Filter devices (Amicon Ultra 15 10K MWCO)
- MonoQ column (GE Health, HiTrap Q HP 645932)

Note

For truncated synucleins, another column may be necessary.

Media and solutions

Lysogeny Broth (LB)

A	В	С
Ingredient	Amount	Final Conc.
Bacto-tryptone	10g	
Yeast Extract	5g	
NaCl	10g	
MilliQ H2O	To 1 L	

Autoclave and cool before use.

Terrific Broth (TB)

А		В	С
In	gredient	Amount	Final Conc.
Ва	acto-tryptone	48 g	
Ye	east extract	96 g	
GI	lycerol	16 mL	
М	illiQ H2O	To 4 L	
10	Ox Phosphate Buffer	Add 50 mL to 450 mL TB	

Autoclave and cool before use.

10x Phosphate Buffer (PB, 1L)

A	1	В	С
Ir	ngredient	Amount	Final Conc.
K	KH2P04	23.2 g	
K	(2HP04	125.4 g	
N	MilliQ H2O	To 1 L	

0.5 M IPTG

A	В	С
Ingredient	Amount	Final Conc.
IPTG	120 mg	0.5 M
MilliQ H2O	1 mL	

High Salt Buffer (50 mL/L culture)

A	В	С
Ingredient	Amount	Final Conc.
5 M NaCl	150 mL	750 mM
0.5 M Tris, pH 7.6	20 mL	10 mM
0.5 M EDTA	2 mL	1 mM
0.5 M PMSF	2 mL	1 mM
MilliQ H20	To 1 L	

Add protease inhibitors 1:1000 and PMSF immediately prior to use.

5 M NaCl (1 L)

A	В	С
Ingredient	Amount	Final Conc.
Sodium Chloride pH to 7.4	292.2 g	5 M
MilliQ H2O	To 1 L	

0.5 M Tris, pH 7.6 (1 L)

A	В	С
Ingredient	Amount	Final Conc.
Tris-base	60.57 g	0.5 M
HCl, pH to 7.6	~30 mL	
MilliQ H2O	To 1 L	

0.5 M EDTA, pH 8.0 (500 mL)

A	В	С
Ingredient	Amount	Final Conc.
Sodium hydroxide pellets	10 g	0.5 M
MilliQ H2O	400 mL	
EDTA pH to 8.0	96.05 g	
MilliQ H20	To 500 mL	

Gel Filtration Dialysis Buffer (1.25 L/L culture)

A	В	С
Ingredient	Amount	Final Conc.
5 M NaCl	50 mL	50 mM
0.5 M Tris, pH 7.6	100 mL	10 mM
0.5 M EDTA	10 mL	1 mM
0.5 M PMSF	10 mL	1 mM

A	В	С
MilliQ H2O	To 5 L	

Add PMSF immediately prior to use.

Gel Filtration Buffer (1 L)

A	В	С
Ingredient	Amount	Final Conc.
5 M NaCl	10 mL	50 mM
0.5 M Tris, pH 7.6	20 mL	10 mM
0.5 M EDTA	2 mL	1 mM
MilliQ H2O	To 1 L	

Buffer A (1L/L culture)


A	В	С
Ingredient	Amount	Final Conc.
5 M NaCl	20 mL	25 mM
0.5 M Tris, pH 7.6	80 mL	10 mM
0.5 M EDTA	8 mL	1 mM
0.5 M PMSF	8 mL	1 mM
MilliQ H2O	To 4 L	

Add PMSF and filter with 0.2 μm filter (for column) immediately prior to use.

Buffer B (400 mL/L culture)

A	B	C
Ingredient	Amount	Final Conc.
5 M NaCl	200 mL	1 M
0.5 M Tris, pH 7.6	20 mL	10 mM
0.5 M EDTA	2 mL	1 mM
0.5 M PMSF	2 mL	1 mM
MilliQ H20	To 1 L	

Add PMSF and filter with 0.2 µm filter (for column) immediately prior to use.



protocols.io 6 1h Incubate the plate inverted at 37 °C (*) Overnight **Day 1: Transformation- Buffer Preparation** Make 🗸 4 L of TB and 🗸 400 mL of 10x phosphate buffer. △ 450 mL of TB + △ 50 mL 10x phosphate buffer into 8x 2 L flasks. Add △ 200 mL to a 1L flask. Cover the tops with foil, and autoclave on the liquid setting. Make sure to let flasks cool for at least 01:00:00 after they have been autoclaved, or if you're in a 1h 30m 9 cool in the cold room for at least (5) 00:30:00 **Day 2: Making Starter Culture** 10 Add \bot 5 µL of \bot 100 mg/mL Ampicillin to \bot 5 mL SOC/TB/LB in a round bottom tube. 11 Pick a colony with a Δ 20 μL pipet tip and drop the tip into the starter culture. Swirl around to ensure the colony detaches from the pipet tip.

12

(*) Overnight

30m

Shake at 😯 200 rpm at 🐉 37 °C





Add 4 0.5 mL of the starter culture to each500 mL flask of TB/phosphate buffer and allow to shake in incubator @ 30m for 00:30:00 without antibiotic.



After © 00:30:00, add 🗓 0.5 mL ampicillin (🖺 100 mg/mL) and grow © Overnight at 37°C. 2d 1h

Expression will occur without induction © Overnight. With such a small starter culture, the goal is for at

Day 3: Protein Isolation

least (24:00:00 growth.

Transfer bacteria cultures to large centrifuge bottles (provided by glassware), make sure the bottles are balanced and centrifuge for 00:20:00 at 5000 x g and 4 °C (rotor F10S).



15

Pour out the supernatant after each spin and keep adding more of the culture to the bottles (balanced) until all culture is centrifuged.



16



Note

THIS IS THE POINT TO FREEZE THE PELLETS IF YOU ARE NOT PROCEEDING WITH THE PREP.

If so, scrape out the pellets and transfer to a labeled _____ 50 mL conical and store at _____ -20 °C . Otherwise:

- 17
- Break down pellets in beaker with manual agitation. Pour roughly 40 mL at a time into a 40 mL dounce homogenizer.
- Homogenize with pestle A (>15 times), making sure that you have broken up all clumps. Repeat with remaining bacteria until all is homogenized and poured into a small plastic beaker.
 - Rinse the homogenizer with the high salt buffer 2-3 times to get the remaining clumps and cell lysate out of the homogenizer
- Heat electric deep fryer on high heat until water is rapidly boiling, being sure to fill the pot up so that a tube rack can be submerged.
- Sonicate On ice (in a plastic or metal beaker) at 35% for 00:01:20 total ON time (5 sec ON, 2 1m 20s OFF, 8 min total time).
 - 21.1 You will have to attach the tip to the sonicator, make sure the tip is 1-2cm from the bottom of the cup taking care not to hit/break the tip.
- Transfer the homogenate to 50 mL conical tubes (~3/4 full).

Oct 25 2024



Note

MAKE SURE ALL TUBES ARE BALANCED AT THIS TIME.

22.1 Boil the homogenate for 00:20:00

20m

- Make 4 5 L gel filtration dialysis buffer and put in the cold room.
- After boiling, bury homogenate tubes in ice and place them in the cold room for at least 00:30:00 or until they feel cold.
- Centrifuge cold lysate for 00:20:00 at 11800 x g and 4 °C (rotor F21).



OPTIONAL: Take an aliquot of the supernatant. Add 5X sample buffer and run on a 15% gel.





27 Cut dialysis tubing (12-14 kD tubing) and wash in the dialysis buffer to soften the tubing.



protocols.io

28

Pipet supernatant into the tubing, close with clamps (**leave an air bubble to promote floatation of the tubing), put the tubing in dialysis buffer and leave in cold room (5) Overnight on the stirrer (stir slowly!).



- 29 If you are doing gel filtration tomorrow, prep the ÄKTA (S.1), and start the program for the gel filtration column for loading tomorrow. (S.2) Lines should be set up as:
 - A1-Size Exclusion Buffer
 - A2-Sterile Distilled Water
 - B1-20% Ethanol
 - B2-20% Ethanol

30 Clean-up: wash all beakers and tubes with bleach and water. Wash dounce homogenizer with DI water and methanol.



Day 5: Gel filtration

31



Note

Concentration and gel filtration steps can be done on separate days if the concentration takes too long. Gel filtration is done with 1-2 runs/L of cell culture and up to A 3 mL of sample/run. Make sure the fraction collector has 24/run 15 mL tubes and is centered correctly. After column prep, the fraction tube should be transferred to the fraction collector arm.

Filter the protein through a \rightarrow 6.22 µm filter (\bot 1000 mL filter unit due to large surface area).

32

Concentrate down to 2-4 mL/L of cell culture in Amicon Ultra Centrifugal Filter devices at 4000 x g



15m



👏 00:15:00 /cycle or Sartorius Vivaspin 15R at 😝 5000 x g

Note

This step may take you all day if you prepare a large scale of synuclein.



34 Load the protein sample onto the column using the A1 inlet, MAX of A 13 mL




34.1 When the sample is getting close to the bottom of the red stopper, pause the ÄKTA and add 1-2mL of Gel Filtration Buffer into the 50mL conical so you can pull up more protein, continue the program and stop it when it is close to the bottom again.

Note

MAKE SURE YOU PULL UP NO AIR.

- 35 Once the sample is all loaded, continue to the "next breakpoint" to start the elution
 - **Manual->Execute Manual Instructions**
 - i. Other-> Next Breakpoint->Insert->Execute
 - Select continue
 - The program should start up again
- 36 Make 4 L of Buffer A, and place in the cold room.
- 37 Take \perp 10 µL of the even fractions, mix with \perp 2.5 µL 5x sample buffer run on 15% acrylamide gels (will need 2 to see all the fractions of interest).

Oct 25 2024





Pipette the fractions into the tubing and dialyze the fractions against Buffer A Overnight.

15m



41 After the elution, the program will continue automatically to wash the column, and store it in 20% Ethanol.



Day 6: MonoQ Column (1)

42

Note

MonoQ Column separates by ion affinity and may need to be calibrated based on overall charge, and the ramp may need to be determined empirically. 25%B has worked for tagged proteins before, α -synuclein elute at a higher %B than tagged α -synuclein. 1-2 runs/L of cell culture and up to 20 mL of sample/run. Make sure the fraction collector has 33/run 15 mL tubes and is centered correctly. After column prep, the fraction tube should be transferred to the fraction collector arm.

Connect the MonoQ column between ports 2A (top) and 2B (bottom) (S.1)

- Switch inputs A1, A2 and B1 and start the MonoQ program **(S.3).** Lines should be set up as:
 - A1-Buffer A


- A2-Sterile Distilled Water
- B1-Buffer B
- B2-20% Ethanol

44

Load the sample using A1. While the sample is loading collect the flow through to test so you know you are not losing protein that is not sticking to the column.



44.1



Note

MAKE SURE YOU PULL UP NO AIR


45 Once the sample is loaded, continue to the "next breakpoint" to start the wash and anion exchange.



46



Take \square 10 µL of the even fractions as they come off, mix with \square 2.5 µL 5x sample buffer run on two 15% acrylamide gels. If you will run a second day of MonoQ, you can pick the fractions to keep based on the UV trace alone.



Dialyze the fractions against Buffer A (or DPBS if this is pure enough) Overnight

15m



Note

To increase purity >90% a second day of MonoQ is recommended. Dialyze the selected fractions back into buffer A 🕥 Overnight

Day 6: MonoQ Column (2)

49 Repeat steps 44-48 above, and keep fractions based on coomassie and UV trace and dialyze into DPBS, 20m



(*) Overnight <u>С</u>н 7.0

50 The primary goal is to get rid of truncated α-synuclein. This shows up as a hump on the later end of the asynuclein peak and can be visualized as truncated forms on the Coomassie-stained gel (E.3).

Day 7: Concentrate and Aliquot

Concentrate down to approximately 2 mL of α-synuclein or molar equivalent in Amicon Ultra

10m



51

Centrifugal Filter devices at 4000 x g , ₿ 4°C (C) 00:10:00 /cycle.

Note

The concentration needs to be over the \triangle 5 mg/mL or \triangle 15 mg/mL concentration at which the protein will be aggregated.

- 51.1 Measure the protein concentration by a BCA assay with sample dilutions of 1:10, 1:20, 1:40, 1:60, 1:80, 1:160, 1:320, 1:640.
- 51.2 Load only \triangle 10 μ L of each sample into the BSA assay.





51.3 Take the average of the concentration estimations for which values are in the linear range of the BSA curve.

Note

You can expect 10-50 mg protein/L culture, depending on the construct.

- Filter the protein through a + 0.22 μm filter. Since this is a small volume, the small blue syringe filters are ideal to minimize sample loss.
- Aliquot the protein into tubes with the protein type, concentration, date and initials.
- Freeze at -80 °C (monomer) or proceed with aggregation (fibrils).
- For aggregation, aliquot the protein out into low binding tubes.



Note

You want at least \square 750 μ L per tube, \square 1 mL is ideal.


Place tubes in a heated shaker at 1000 rpm at 137 °C for 168:00:00





- After 7 days, aliquot the fibrils into small aliquots to avoid freeze thaw cycles, and store in the mid/back of the -80 °C freezer.
- For quality control the sedimentation assay and thioflavin T assay should be done after they fibrillization (see additional protocols).

Examples of Mouse Alpha Synuclein Prep done on 12.2020

59







Supplemental Information: S.1 Preparing the AKTA Chromatography Syste...

Oct 25 2024

60 Place all the lines in their corresponding bottles.

- Using the 25 mL Syringe pull 20 mL through the lines at the correct pump location, do this slowly, if you go too quick you can introduce air into the system die to back pressure. To do this:
 - 61.1 Go to Manual->Execute Manual Instructions->Flow path
 - a. Then you can choose Inlet A or Inlet B
 - i. Then choose your flow path (A1 or A2 for A, B1 or B2 for B)
 - a. Select Insert
 - ii. Hit the **Execute** button
 - You can now pull the liquid out of the corresponding pumps you just turned on. Do this by:
 - Turning the knob on the outside of the pump and inserting the syringe tip into the opening and slowly pulling back
 - Make sure to tighten the pump knobs once you have finished pulling the lines

Note

Repeat this procedure until you have pulled out 20 mL from each line.

Supplemental Information: S.1 Preparing the AKTA Chromatography Syste..

62

Note

ALWAYS DETACH BOTTOM TO TOP, AND ATTACH TOP TO BOTTOM!

Manual->Execute Manual Instructions-Insert the following instructions

- 62.1 i. Pumps
 - 1. System Flow: 2 ml/min
 - 2. Pressure control: **System Pressure**
 - a. INSERT
- 62.2 ii. Flow Path

- 1. Inlet B-> B2-> INSERT
- 2. Column Position-> select 1-> INSERT

62.3 iii. Alarms

- 1. Alarm system pressure-> Enabled
- 2. High alarm = 0.5 mPA
 - a. INSERT
- 63 Confirm on the screen that the B2 path is highlighted and flowing over the column to waste at 2 mL/min or slower.
- 64 Unscrew the bottom connector from the Q column (20% Ethanol should be dripping out) and cap the bottom.

Note

The pressure alarm is going to go off, this is normal.

- Loosen the connector at the top of the column, and hit continue on the program.
- 66 Fill the top of the Q column with 20% Ethanol and screw the top cap on.

Note

If connecting the Superdex 200 immediately, you can let the Ethanol drip for a minute while you change them. Otherwise, hit pause.

Supplemental Information: S.1 Preparing the AKTA Chromatography Syste...

67	If you just detached the Q column you can continue on, if the system was off perform the steps above (1.i->1.iii), their should be 20% Ethanol dripping from the top connecting line.
68	Insert the column into the holders on the ÄKTA carefully (bottom should be in line with the bottom of the pumps).
69	Remove the cap from the top of the column, 20% Ethanol should start dripping out of the tubing from the column. Remove the tubing from 1A location on the ÄKTA (this is the location the 20% Ethanol should be dripping from), connect the column to the port on the machine in a drip to drip fashion.
	Note
	IF YOU SEE ANY AIR BUBBLES DETACH IMMEDIATELY and let the solution flow back out of the tubing.
70	Detach the buffer reservoir from the bottom of the superdex column, you should see It dripping out now.
71	Attach the tubing to the line coming from the 1B position on the ÄKTA.
72	Buffer should be flowing and the column should be ready to go.
	Supplemental Information: S.1 Preparing the AKTA Chromatography Syste
73	Manual-> Execute Manual Instructions-Insert the following instructions

- 73.1 i. **Pumps**
 - 1. System Flow: 2 ml/min
 - 2. Pressure control: System Pressure
 - a. INSERT
- 73.2 ii. Flow Path
 - 1. Inlet B-> B2-> INSERT
 - 2. Column Position->select 1 -> INSERT
- 73.3 iii. Alarms
 - 1. Alarm system pressure-> Enabled
 - 2. High alarm = **0.5 mPA**
 - a. INSERT
- When you see 20% Ethanol dripping from system, you can detach the bottom connector and attach the buffer reservoir, allow the ÄKTA to flow over the column until the reservoir is filled so that the stopper is pass the line.
- Detach the top of the column, 20% Ethanol should be dripping out, quickly cap the top of the tubing off.
- 76 Carefully remove the column and store it in the bottom of the fridge.

Supplemental Information: S.1 Preparing the AKTA Chromatography Syste..

If you just detached the Superdex column you can continue on, if the system was off perform the steps above (1.i->1.iii), there should be 20% Ethanol dripping from the top connecting line.

👸 protocols.io

, proto	
78	Attach the tubing to the port 1A on the machine, when 20% Ethanol starts dripping from the tubing, remove the cap from the Q trap.
79	Fill the top of the Qtrap with Ethanol so that it is bubbled up at the top and attach the connector to the column.
	Note
	The alarm will go off, that is normal.
80	Remove the cap from the bottom of the column and continue to run the program on the computer.
81	Connect the line from port 1B to the column.
82	The column should now have the 20% Ethanol running over it.
	S.2 Size Exclusion Chromatography Program- No Wash Size Exclusion As
83	Method settings: column selected (HiLoad 26/600 Superdex 200pg) pressure limit should be 0.5 MPa, column volume (CV): 318.557ml column position: 1 flow rate 2.6 ml/min control the flow to avoid overpressure should be selected.

84

System prep:

protocols.io

- A2 is selected
- Injection valve with capillary loop is selected to be washed
- Fraction collector is selected to be washed

85 Column Wash:



- 2.6 ml/min (select use the same flow rate as in methods setting)
- A2 is shown 0% B1
- Wash is 1 CV sent to waste (~ 🔼 320 mL)

86 Equilibration:

- 2.6 ml/min (select use the same flow rate as in methods setting)
- A1 is shown, 0% B
- Equilibrate until 2 CV (~ 【 640 mL)

87 Miscellaneous

87.1 Message is selected "load sample".

87.2 Pause after message is selected.

88 Load sample

88.1 Select "reset UV monitor".

Oct 25 2024

	88.2	Select "use the same flow rate as in method setting".
	88.3	A1 should be shown with 0% B.
	88.4	Equilibrate until "the total volume is 0.2 CV" is selected.
89	Elution	
	89.1	Select "use the same flow rate as in method settings".
	89.2	A1 should be shown.
	89.3	Isocratic elution should be selected Volume: 1.5 CV 0% B.
	89.4	Fractionate: select using fraction collector 1. Fraction type: Peak Fractionation 2. Peak Frac settings: 50.00 mAu for both start and end level 3. Peak fractionation volume



89.5 Select start fractionation after 0.2 CV.

90

Water wash



90.1 Select use the same flow rate as in method settings.

90.2 A2 should be shown as the inlet A.

90.3 Wash until: select "the total volume is 2 CV.

90.4 Fractionate: select "in waste".

91 Ethanol equilibration B2.

S.3 Henderson Lab MonoQ Qtrap HP Protocol

92 This method will include the following steps





System prep

■ Wash the system with ∠ 20 mL volume per position at ∠ 10 mL per min from inlet A1. Make sure the column position "by-pass" is selected.

93 Equilibration



5 ml/min wash of column with A1 inlet for 5CV

94 Miscellaneous

pauses the system with the message "load sample"

95 Load sample

2 ml/min through A1 for 20 CV

96 Column wash



2 ml/min wash of column with A1 inlet for 5 CV

97 Elution-15%

- 2 ml/min linear gradient elution from 100% A1 inlet to 15% B1 inlet over 10 CV.
- Collecting
 ☐ 2 mL fractions after UV goes to 25.00mAu

98 Elution-30%

- 2 ml/min linear gradient elution from 15% B1 to 30% B1 over 10 CV.
- Collecting fixed ∠ 2 mL fractions starting at 15%

99 Elution-100%

- 2 ml/min linear gradient from 30% B1 to 100% B1 over 5 CV.

Oct 25 2024



Column wash



■ 5 ml/min 100% B1 inlet over 5 CV

101

Equilibration of Column

• 5 ml/min A1 inlet for 5 CV

102

Ethanol wash



• 5 ml/min 100% B2 inlet line for 5CV

Oct 25 2024