

#### **VERSION 2**

JUL 11, 2023



#### DOI:

dx.doi.org/10.17504/protocol s.io.8epv51me6l1b/v2

**Protocol Citation:** Philippa R Kennedy 2023. Degranulation and cytokine production (functional assay). **protocols.io** 

https://dx.doi.org/10.17504/p rotocols.io.8epv51me6l1b/v2 Version created by Philippa R Kennedy

License: This is an open access protocol distributed under the terms of the Creative Commons
Attribution License, which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

**Protocol status:** Working We use this protocol and it's working

Created: Dec 15, 2022

Last Modified: Jul 11, 2023

**PROTOCOL** integer ID:

74080

# Degranulation and cytokine production (functional assay) V.2

### Philippa R Kennedy<sup>1</sup>

<sup>1</sup>University of Minnesota



Philippa R Kennedy University of Minnesota

#### **ABSTRACT**

Two primary functions of NK cells - their cytotoxcity and ability to produce cytokines, are measured in a flow-based assay that assesses these responses at the single cell level when NK cells are challenged with tumor cells. Cytotoxicity is not directly measured, instead it is inferred from cytotoxic granlue release. For this reason, this assay should be accompanied by a direct measure of cytotoxicity, such as a *Time - lapse killing assay*. Cytotoxic granlue release is measured by the accumulation of the cytotoxic granule membrane protein, CD107a (LAMP1), at the surface of the NK cell, when fusion of recycling endosomes with the lysosome is blocked by monensin. Cytokines accumulate in NK cells when Golgi transport is blocked by brefeldin A. At the end of an effector:target co-culture, these proteins and other lineage surface markers are detected by flow cytometry.

This version takes less time than the previous protocol without affecting the quality of the result.

**Keywords:** natural killer cell, NK cell, CD107a, flow cytometry, cytokine, functional

#### **GUIDELINES**

The day of the assay (after effectors are plated) is long because of the 5 h incubation. Be sure to start early in the day.

During the setup of the assay, to avoid shocking the cells, pre-warm media and pipette gently, up until the staining steps. After the 5 h incubation, the aim is to stop all reactions, so pre-cool centrifuges and staining buffers to 4°C. Once cells are fixed, this cooling is no longer necessary.

The manufacturer recommend live/dead staining in PBS, but a side-by-side comparison of staining in PBS or flow buffer revealed no difference in performance of the NIR dye in our hands.

The manufacturer recommends washing in perm buffer after staining, but a side-byside comparison of washing in perm buffer or flow buffer revealed no difference in performance of the staining in our hands.

When working with tissue samples, blocking prior to staining is required; filtering through a  $70\mu m$  filter prior to running through a flow cytometer is required; and counting beads can be beneficial for accurate assessment of cell number.

#### **MATERIALS**

#### R10 media recipe:

- RPMI cat. 2240-089, Gibco
- 10% heat inactivated fetal calf serum cat. 26140079, Gibco
- 100 U/ml Penicillin & 100 μg/ml Streptomycin cat. 15140122, Gibco

#### B0 media recipe:

- 60% DMEM cat. 10-017-CV Corning
- 30% Hams F12 cat. 10-080-CV Corning
- 10% heat inactivated AB serum cat. HP1022 Valley Biomedical Inc
- 100 U/ml Penicillin & 100 μg/ml Streptomycin cat. 15140122, Gibco
- 20 μM β-mercaptoethanol cat. M7522, Sigma Aldrich
- 50 μM Ethanolamine cat. E0135, Sigma Aldrich
- 20 μg/ml Ascorbic Acid cat. A4544, Sigma Aldrich
- 5 ng/ml Sodium Selenite (Na<sub>2</sub>SeO<sub>3</sub>) cat. S5261, Sigma Aldrich

#### Flow buffer:

- 1% heat inactivated AB serum, cat. HP1022 Valley Biomedical Inc
- 0.5mM EDTA
- PBS cat. 21-040-CV, Corning

#### **Inhibitors**

- GolgiStop Cat. No. 554724, BD Biosciences
- GolgiPlug Cat. No. 555029, BD Biosciences

#### Stains:

- anti-CD107a, clone H4A3, cat. 328606, BioLegend, RRID:AB\_1186036
- anti-CD56-PE-Cy7, clone HCD56 cat. 318318, Biolegend, RRID:AB\_604107
- anti-CD3-PECF594, clone UCHT1, cat. 562280, BD Horizon, RRID:AB\_11153674
- anti-IFNy-Bv650, clone 4S.B3, cat. 502538, BioLegend, RRID:AB\_2563608
- anti-TNFa-Bv421, clone Mab11, cat. 502932, Biolegend, RRID:AB\_10960738
- Live/Dead Fixable Near-IR Staining Kit, cat. L-34976, Thermo Fisher

#### **Fixation:**

2% Paraformaldehyde/PBS

#### Permeabilization:

Permeabilization Buffer(10x), cat. 00-8333-56 eBioscience

#### For tissue samples:

- Human TruStain FcX™ Fc Receptor Blocking Solution (cat. 422302, BioLegend)
- CountBright<sup>™</sup> Absolute Counting Beads, for flow cytometry (cat. C36950, ThermoFisher Scientific)
- EZflow cell strainer 70μm, (cat. 1170C02, Thomas Scientific)

#### **BEFORE START INSTRUCTIONS**

If working with frozen cells, these must be thawed and prepared the day before the assay. Book flow cytometers in advance to avoid delays in acquiring the data. Ideally, samples should be run the day after the assay was performed, but can be stored up to three days e.g. if assay was performed on a Friday.

## Preparing effector and target cells

1 Effector cells (PBMCs or enriched NK cells) are resuspended in R10.
Induced pluripotent stem cell (iPSC)-derived NK cells should be resuspended in B0.

#### 1.1 R10 media recipe:

- RPMI cat. 2240-089, Gibco
- 10% heat inactivated fetal calf serum cat. 26140079, Gibco
- 100 U/ml Penicillin & 100 μg/ml Streptomycin cat. 15140122, Gibco

#### B0 media recipe:

- 60% DMEM cat. 10-017-CV Corning
- 30% Hams F12 cat. 10-080-CV Corning
- 10% heat inactivated AB serum cat. HP1022 Valley Biomedical Inc
- 100 U/ml Penicillin & 100 μg/ml Streptomycin cat. 15140122, Gibco
- 20 μM β-mercaptoethanol cat. M7522, Sigma Aldrich
- 50 μM Ethanolamine cat. E0135, Sigma Aldrich
- 20 μg/ml Ascorbic Acid cat. A4544, Sigma Aldrich
- 5 ng/ml Sodium Selenite (Na2SeO3) cat. S5261, Sigma Aldrich
- Target cells are added to each well at an effector:target ratio of 2:1. At the same time, FITC conjugated anti-CD107a (clone H4A3, BioLegend; batch specific, but normally 3 μL/well) is added to each well. The cells are then incubated at 37°C 5% CO<sub>2</sub>. Ο 01:00:00

1h

 $5 \times 10^5$  cells/well are added to a U-bottomed 96 well plate.

1d

These numbers can be decreased to  $1 \times 10^5$  effector cells/well if the number of effector cells is limited, so long as target numbers are decreased accordingly.

If thawing effector cells, these should be plated one day in advance in 200  $\mu$ L **R10** (PBMC) or 200  $\mu$ L **B0 with 50 U/mL IL-2** (iPSC-NK cells) and cultured at 37°C 5% CO<sub>2</sub> overnight

Overnight. This allows recovery of surface proteins and functionality. In this case, plates are spun at 300g for 5 min the following day in order to remove excess media.

## **Adding inhibitors**

One hour after the addition of anti-CD107a, cells are given monensin (GolgiStop Cat. No. 554724, BD Biosciences) and brefeldin A (GolgiPlug Cat. No. 555029, BD Biosciences). GolgiStop (1/150) and GolgiPlug (1/100) are diluted in R10 and 20 μL is added to each well. Cells are incubated for a further 4 h at 37°C 5% CO<sub>2</sub>. 04:00:00

4h

## Live/dead and surface staining of cells

30m

- Cells are washed twice, as defined below, in flow buffer (1% AB serum, 0.5mM EDTA in PBS).
  This definition also applies to subsequent washes.
- 5.1 The plate is spun in a centrifuge at 300 g for 5 min (this is approximately 1200 rpm in a large

5m

benchtop centrifuge). The supernatant is removed and replaced with 200 µL flow buffer/well (first wash).

5.2 The plate is spun again in the centrifuge at 300g for 5 min. The supernatant is removed and replaced with 200  $\mu$ L flow buffer/well (second wash).

5m

5.3 The plate is spun for a final time at 300g for 5 min and the supernatant is removed.

5m

Optional: If working with processed tissues, prepare 5μL Fc Receptor Blocking Solution (cat. 422302, BioLegend) in 100μL flow buffer. Resuspend each well in 20μL of this blocking solution and incubate for 5 min 00:05:00 at room temperature to block non-specific staining.

Proceed to surface staining without washing.

5m

7 Cells are resuspended in 50 μL flow buffer containing:

25m

- 1. anti-CD56-PE-Cy7 (clone HCD56, Biolegend; batch specific, but normally 5 μL/test)
- 2. anti-CD3-PECF594 (clone UCHT1, BD Horizon, batch specific, but normally 1 μL/test)
- 3. Live/Dead Fixable Near-IR Staining Kit, cat. L-34976, Thermo Fisher (1/1000 dilution) Incubate for 15 min at 4 °C  $\odot$  00:15:00 . After the incubation, wells are topped up to 200  $\mu$ L with flow buffer and washed once with flow buffer.  $\odot$  00:10:00

8 • Cells are resuspended in 100 μL 2% paraformaldehyde/PBS and incubated at room temperature in the dark for 10 min to fix them 00:10:00 . Afterwards, wells are topped up to 200 μL with flow buffer and washed once with flow buffer. 00:10:00

20m

#### Note

The assay can be paused here overnight. If doing so, wash once more in flow buffer, topping up to 100  $\mu$ L/well, then store at 4 °C. Seal the edge of the plate with parafilm to avoid evaporation.

## Intracellular staining of cells

- Cells are washed in 150 μL perm buffer (10% Permeabilization Buffer, cat. 00-8333-56 eBioscience/distilled H<sub>2</sub>0).
- 10 Permeabilized cells are resuspended in 50 μL perm buffer containing:

30m

- 1. BV650 conjugated IFNγ (4S.B3, BioLegend; batch specific, but normally **3 μL/test**)
- 2. BV421 conjugated TNFa (Mab11, Biolegend; batch specific, but normally **5 μL/test**).

They are incubated for 30 min at 4 °C in the dark. (5) 00:30:00

After staining, wells are topped up to 200 μL with flow buffer and washed once with flow buffer. Cells are resuspended in 200 μL of flow buffer and transferred to bullet tubes. (5) 00:10:00

10m

- The tubes are covered and stored in the dark at 4 °C until they are ready to be run on a flow cytometer (LSR II, BD Biosciences).
  - To be able to compare NK cell numbers or tumor cell numbers between samples, run the flow cytometer at a consistent speed (e.g. high) and acquire data for a set time (e.g. 60s)
- Data is analyzed using FlowJo software (Tree Star Inc., RRID:SCR\_008520)
  - Degranulation (CD107a+) and cytokine production (IFN $\gamma$ + or TNF $\alpha$ +) are assessed for the live (dead cell marker-) NK cell (CD56+ CD3-) population.