

JUL 21, 2023

# OPEN ACCESS

dx.doi.org/10.17504/protocol s.io.261ge3mxol47/v1

**Protocol Citation:** Sneha Shrestha, Christopher LeBoa 2023. River water laboratory processing Protocol.

#### protocols.io

https://dx.doi.org/10.17504/p rotocols.io.261ge3mxol47/v1

License: This is an open access protocol distributed under the terms of the Creative Commons Attribution License. which permits unrestricted use, distribution, and reproduction in any medium, provided the original author and source are credited

**Protocol status:** Working We use this protocol and it's working

Created: Apr 21, 2023

Last Modified: Jul 21, 2023

**PROTOCOL** integer ID: 80906

## River water laboratory processing Protocol

Sneha Shrestha<sup>1</sup>, Christopher LeBoa<sup>2</sup>

<sup>1</sup>Dhulikhel Hospital; <sup>2</sup>UC Berkeley



Christopher LeBoa

DISCLAIMER

DISCLAIMER - FOR INFORMATIONAL PURPOSES ONLY; USE AT YOUR OWN **RISK** 

The protocol content here is for informational purposes only and does not constitute legal, medical, clinical, or safety advice, or otherwise; content added to protocols.io is not peer reviewed and may not have undergone a formal approval of any kind. Information presented in this protocol should not substitute for independent professional judgment, advice, diagnosis, or treatment. Any action you take or refrain from taking using or relying upon the information presented here is strictly at your own risk. You agree that neither the Company nor any of the authors, contributors, administrators, or anyone else associated with protocols.io, can be held responsible for your use of the information contained in or linked to this protocol or any of our Sites/Apps and Services.

#### **ABSTRACT**

These are the qPCR conditions used for the S. Typhi and Paratyphi qPCR used for environmental surveillance by our lab team

#### **MATERIALS**

#### Microbiology Laboratory:

(Amount of materials required for a month of sampling)

- 1. 0.5% sodium hypochlorite
- 2. 70% ethanol
- 3. Sterile D/W
- 4. 15ml Falcon tubes (48 tubes)
- 5. 50ml Falcon tubes (24 tubes)
- 6. Sterile, clear glass tubes
- 7. 1ml sterile tips (2 boxes) and pipette
- 8. 200µl sterile tips (2 boxes) and pipette
- 9. Selenite F broth (10ml in each tube, 29 tubes)

- 10. Sterile 1.5ml eppendorf tubes (116 eppendorfs)
- a. DNA Zap solution A and B
- 11. DNA extraction kit (DNEasy Blood and Tissue Kit Cat# 69504)

#### **Molecular Laboratory**:

- 1. 0.5% sodium hypochlorite
- 2.70% ethanol
- 3. Master mix (TaqMan Environmental Mastermix)
- 4. Primer F (ST/SPTA)
- 5. Primer R (ST/SPTA)
- 6. Probe (ST/SPTA)
- 7. dH20
- 8. Template DNA
- 9. Sterile eppendorf
- 10. PCR strips
- 11. 10µl tips (3 boxes) and pipette
- 12. 20µl sterile tips (1 box) and pipette
- 13. 200µl sterile tips (1 box) and pipette
- 14. 1ml sterile tips (1 box) and pipette

#### **qPCR Conditions**

### List of primer and probes used:

#### Salmonella Typhi:

Salmonella Typhi Forward Primer-5' CGCGAAGTCAGAGTCGACATAG 3'
Salmonella Typhi Reverse Primer -5' AAGACCTCAACGCCGATCAC 3'
Salmonella Typhi Probe-5' FAM-CATTTGTTCTGGAGCAGGCTGACGG-BHQ1a-Q3'

#### Salmonella Paratyphi-A:

Salmonella Paratyphi-A Forward Primer - 5'ACGATGATGACTGATTTATCGAAC 3' Salmonella Paratyphi-A Reverse Primer - 5' TGAAAAGATATCTCTCAGAGCTGG 3' Salmonella Paratyphi-A Probe-5' FAM-

CCCATACAATTTCATTCTTATTGAGAATGCGC-BHQ1a-Q 3'

#### Master mix setup

Salmonella Typhi/Paratyphi-A qPCR:

A	В
Master mix (TaqMan Environmental Mastermix) (2x)	10 μΙ
Primer F (10µM)	0.80 µl (400nM)
Primer R(10µM)	0.80 µl (400nM)
Probe (10μM)	0.4 μl (200nM)

A	В
Nuclease Free Water	4 μl (DNase/RNase- Free)
Template	
Total	20 ul

### **Cycling parameters:**

Encode these temperatures onto qPCR machine 15 min at 95°C (Holding stage) 30 secs at 95°C (Cycling Stage) 30 secs at 60°C (Cycling Stage)

Initial Denaturation	15 min at 95C	
Dentaturation	30 secs at 95C	45 cycles
Annealing and Extension (Fluorescence Capture Step)	30 sec at 60C	

### **PCR Result:**

- 1. Export Ct value results from qPCR machine
- 2. Upload results into excel file.
- 3. Upload the file to the RedCap app.

# **Turbidity Testing**

- 1 2ml of sample (from 5ml separated for Phage Screening) is taken in a sterile glass tube
- 2 Turbidity is measured by densitometry.

# **Differential Centrifugation**

- 3 Spin down 45ml of collected water sample at 2000rpm for 1 min to separate out larger debris.
- 4 Transfer the supernatant to a new sterile 50ml tube.
- **5** Centrifuge at 4000rpm for 25mins.
- **6** Discard the supernatant and resuspend the pellet in 0.5ml of sterile D/w.

## **Enrichment and DNA extraction**

7 Transfer 0.5ml of resuspended pellet into 10ml of Selenite F broth.

ð	Transfer Titll of this suspension to a sterile 1.5th tube for DNA extraction for 10.
9	Incubate the inoculated Selenite F broth overnight (16hrs) at 37°C.
10	At the end of incubation, transfer 1ml of the o/n growth to 1.5ml tube for DNA extraction at T16.
	DNA extraction (DNEasy Blood and Tissue Kit Cat# 69504)
11	Transfer 1ml of bacterial suspension in SF broth to 1.5ml tube.
12	Centrifuge at 2000rpm for 2mins.
13	Discard the Supernatant.
1.4	Decreased well-strice 2000 to DDC
14	Resuspend pellet in 200 μl PBS.
15	Add 20 μl proteinase K.

16 Add 200 µl buffer AL. Mix thoroughly by vortexing. 17 Incubate for 10mins at 55°C. 18 Add 200 µl ethanol (96-100%) and mix thoroughly by vortexing. 19 Transfer the mixture into a DNeasy Mini spin column placed in a 2ml collection tube. Centrifuge at 8000rpm for 1min. Discard the flow-through and replace a new collection tube. 20 Add 500 µl Buffer AW1 to the column and centrifuge at 8000rpm for 1 min. Discard flow-through and replace a new collection tube. 21 Add 500 µl Buffer AW2 to the column and centrifuge at 14000 rpm for 3 mins. Discard flowthrough. 22 Transfer the collection tube to a new 1.5ml microcentrifuge tube. 23 Elute the DNA by adding 60 µl Buffer AE to the center of the spin column membrane. Incubate for 1 min at room temperature. Centrifuge at 8000 rpm for 1 min.

# Real time PCR (Adapted from Tran Vu Thieu Nga)

#### 24 Primer preparation

Primers/probes are shipped in lyophilized form and need to be constituted with TE buffer or nuclease

free dH20. Make the primary primer/probe stock solution of 100  $\mu$ M.

Amount of nuclease free dH20= 10 µl × X ng

Here, X is the amount of primer/probe provided by the manufacturer.

Generally, use the following formula to find unknown volume or concentration.

C1\*V1 = C2\*V2

Where,

C1 = Initial concentration.

V1 = Initial volume.

C2 = Final concentration.

V2 = Final volume.

Here, for this protocol, we used a portion of the 100  $\mu$ M primers/probes to make 10  $\mu$ M/ $\mu$ l solutions

to use as working solutions. Aliquot the working solution into 5 separate tubes and store at -20  $^{\circ}\text{C}$  to

avoid contamination and multiple freeze-thawing cycles.

#### 25 Master mix setup

Master mix hi/Paratyphi-A qPCR:

26