

### Overview


Principal Component Analysis (PCA)

Probabilistic PCA

Independent component analysis (ICA)

## Latent variables

- Sometimes data depends on the variables we can not measure (hard to measure)
  - Answers on the test depend on Intelligence
  - Brain activity in the brain is measured by sensors
  - Stock prices depend on market confidence






Source: Leadliaison.com

## Latent variables

 Latent factor discovered → data storage may decrease a lot



- Center
- Scaling
- Original vs compressed
  - 100x100x5=50000
  - 100x100+2\*5+2\*5=10020



#### **Principal Component Analysis (PCA)**


- PCA is a technique for reducing the complexity of high dimensional data
- It can be used to approximate high dimensional data with a few dimensions (latent features) -> much less data to store
- New variables might have a special interpretation

#### **Applications**

- Image recognition
- Information compression
- Subspace clustering
- ...


### Principal Component Analysis (PCA)

- Example 1: Hadwritten digits
  - Can we get a more compact summary?



#### Absorbance records for ten samples of chopped meat

#### Parallel coordinate plot for "FAT"




1 target (fat)

100 features (absorbance at 100 wavelengths or channels)

The features are strongly correlated to each other

# 3-D plots of absorbance records for samples of meat - channels 1, 50 and 100

#### **Scatterplot for three components**




# Principal components analysis

Idea: Introduce a new coordinate system (PC1, PC2, ...) where


- The first principal component (PC1) is the direction that maximizes the variance of the projected data
- The second principal component (PC2) is the direction that maximizes the variance of the projected data after the variation along PC1 has been removed
- The third principal component (PC3) is the direction that maximizes the variance of the projected data after the variation along PC1 and PC2 has been removed
- ....

In the new coordinate system, coordinates corresponding to the last principal components are very small  $\rightarrow$  can take away these columns

# Principal Component Analysis - two inputs



# PCA- after reducing dimensionality




- Data became approximate (but less data to store)
- $PC_1$ , ...  $PC_M$  are actually eigenvections of **sample covariance** (first largest eigenvalue,...,Mth largest egenvalue)

# PCA: another view

 Aim: minimize the distance between the original and projected data

$$\min_{V} \sum_{i=1}^{N} ||x_n - \tilde{x}_n||^2$$



# **PCA:** computations

Data 
$$D = \|\mathbf{x}_1 \ \mathbf{x}_2 \ ... \ \mathbf{x}_p\|, \quad \mathbf{x}_i = (x_{i1}, ..., x_{in})$$


1. Centred data

$$X = \left\| \mathbf{x}_1 - \overline{\mathbf{x}}_1 \ \mathbf{x}_2 - \overline{\mathbf{x}}_2 \dots \mathbf{x}_p - \overline{\mathbf{x}}_p \right\|,$$

2. Covariance matrix

$$S = \frac{1}{N} X^T X$$

3. Search for eigenvectors and eigenvalues of **S** 





	Column 1	Column 2
Column 1	0.951	0.905
Column 2	0.905	1.883


# PCA: computations

4. Coordinates of any data point  $x=(x_1...x_p)$  in the new coordinate system:

$$z = (z_1, \dots z_n), z_i = x^T u_i$$







Matrix form: Z = X U


- 5. Discard principle components after some *M*
- 6. New data will have dimensions N x M instead of N x p

Getting approximate original data:

$$X' = ZU_M^T$$

Store: N x M+ p x M instead N x p

## Principal Component Analysis



Eigenanalysis of the Covariance Matrix

Eigenvalue 2.8162 0.3835

Proportion 0.880 0.120

Cumulative 0.880 1.000


#### Loadings (U)

# Principal Component Analysis

Digits: two eigenvectors extracted

$$x = 3 + z1 \cdot 3 + z2 \cdot 3$$


Interptretation of eigenvectiors



### PCA in R

Prcomp(), biplot(), screeplot()

```
mydata=read.csv2("tecator.csv")
data1=mydata
data1$Fat=c()
res=prcomp(data1)
lambda=res$sdev^2
#eigenvalues
lambda
#proportion of variation
sprintf("%2.3f",lambda/sum(lambda)*100)
screeplot(res)
```



```
> lambda
```

```
[1] 2.612713e+01 2.385369e-01 7.844883e-02 3.018501e-07 2.052212e-04 1.084213e-04 2.077326e-05 1.150359e-09 2.077326e-05 1.150359e-09 2.077326e-05 1.150359e-09 2.077326e-09 2.077826e-09 2.077826e-09 2.077826e-09 2.077826e-09 2.077826e-09 2.077826e-09 2
```

```
> sprintf("%2.3f",lambda/sum(lambda)*100)
[1] "98.679" "0.901" "0.296" "0.114" "0.006
[9] "0.000" "0.000" "0.000" "0.000" "0.000
```

Only 1 component captures the 99% of variation!

### PCA in R

Principal component loadings (U)


U=res\$rotation
head(U)

#### > head(U)

```
PC1 PC2 PC3
Channell 0.07938192 0.1156228 0.08073156 -0.0927
Channell 0.07987445 0.1170972 0.07887873 -0.0981
Channell 0.08036498 0.1185571 0.07702127 -0.1031
Channell 0.08085611 0.1200006 0.07515015 -0.1077
Channell 0.08184806 0.1227401 0.07125048 0.1156
```

Data in (PC1, PC2) – scores (Z)

plot(res\$x[,1], res\$x[,2], ylim=c(-5,15))




Do we need second dimension?


## PCA in R

#### Trace plots

```
U=loadings(res)
plot(U[,1], main="Traceplot, PC1")
plot(U[,2],main="Traceplot, PC2")
```

#### 






Which components contribute to PC1-2?

#### Absorbance records for ten samples of chopped meat

#### PCA2 captures the most of remaining variation



# PCA for high-dimensional data

- Standard PCA for p>>N
  - At most N eigenvalues are nonzero
  - Running time is  $O(p^3)$

- High-dimensional PCA
  - 1. Use  $S' = \frac{1}{N}XX^T$  (instead of  $S = \frac{1}{N}X^TX$ )
  - 2. Eigenvalues do not change
  - 3. Eigenvectors of S are  $X^T v_i$


•  $z_i$ -latent variables,  $x_i$ - observed variables

$$z \sim N(0, I)$$
  
  $x|z \sim N(x|Wz + \mu, \sigma^2 I)$ 

Alternatively

$$z \sim N(0, I), x = \mu + Wz + \epsilon, \epsilon \sim N(0, \sigma^2 I)$$

• Interpretation: Observed data (X) is obtained by rotation, scaling and translation of standard normal distribution (Z) and adding some noise.



- Aim: extract Z from X
- Distribution of *x*:

$$x \sim N(\mu, C)$$

$$C = WW^T + \sigma^2 I$$

- Rotation invariance
  - Assume that x was generated from z' = Rz,  $RR^T = I$ , p(x) does not change!

$$x|z' \sim N(x|Wz' + \mu, \sigma^2 I)$$

- Model will not be able find latent factors uniquely! ⊗
  - It does not distinguish z from z'

Estimation of parameters: ML

Theorem. ML estimates are given by

$$\mu_{ML} = \bar{x}$$

$$W_{ML} = U_M (L_M - \sigma_{ML}^2 I)^{\frac{1}{2}} R$$

$$\sigma_{ML}^2 = \frac{1}{p-M} \sum_{i=M+1}^p \lambda_i$$

- $U_M$  matrix of M eigenvectors
- $L_M$  diagonal matrix of M eigenvalues
- R any orthogonal matrix

- Estimation of Z
  - Use mean of posterior

$$\hat{z} = (W_{ML}^T W_{ML} + \sigma_{ML}^2 I)^{-1} W_{ML}^T (x - \mu)$$

- Connection to standard PCA
  - Assume R = I,  $\sigma^2 = 0$  get standard PCA components scaled by inverse root of eigenvalues

$$Z = XUL^{-\frac{1}{2}}$$

# Advantages of probabilistic PCA

- More settings to specify → more flexible
- Can be faster when M<<p</li>
- Missing values can be handled
- M can be derived if a Bayesian version is used
- Probabilistic PCA can be applied to classification problems directly
- Probabilistic PCA can generate new data

## Probabilistic PCA in R

- Use pcaMethods from Bioconductor
- Install
  - source("https://bioconductor.org/biocLite.R")
  - biocLite("pcaMethods")


Ppca(data, nPcs,...)

**Results**: scores, loadings...

# Independent component analysis (ICA)

- Probabilistic PCA does not capture latent factors
  - Rotation invariance
- Let's choose distribution which is not rotation invariant > will get unique latent factors
- Choose non-Gaussian  $p_i(z) = p(z)$
- Assuming latent features are independent

$$p(z) = \prod_{i=1}^{M} p_i(z_i)$$



Model

$$x = \mu + Wz + \epsilon, \quad \epsilon \sim N(0, \Sigma)$$

- Estimation A: Maximum likelihood ( $V = W^{-1}$ )
  - Assuming noise-free x

$$\max_{V} \sum_{i=1}^{n} \sum_{j=1}^{p} \log \left( p_{j}(v_{j}^{T} x_{i}) \right)$$
Subject to  $||v_{i}|| = 1$ 

• Setting  $G_j(z) = -\log\left(p_j(z)\right)$ ,  $z_j = v_i^T x$  and assuming large sample

$$\min_{V} \sum_{j=1}^{p} E(G_j(z_j))$$

Subject to 
$$||v_i|| = 1$$


#### Prewhitening

- Use PCA: X' = XU
- Computing  $z_i$ s for given V: Z = X'V

- **Estimation B**: maximize negentropy
  - ICA looks for model which is as much non-Gaussian as possible
- Entropy  $H(z) = -\int p(z) \log p(z) dz = E(-\log p(z))$
- Negentropy  $J(z_i) = H(z'_i) H(z_i)$ 
  - $z_i' \sim N(Ez_i, var(z_i))$
- Negentropy maximization

$$\max_{V} \sum_{j=1}^{p} J(z_{j}) = \min_{V} \sum_{j=1}^{p} H(z_{j}) = \min_{V} \sum_{j=1}^{p} E\left(-\log p\left(z_{j}\right)\right)$$

### • Example



Source: Elem of stat learn by Hastie

# Independent component analysis: R

```
S \leftarrow cbind(sin((1:1000)/20), rep((((1:200)-100)/100), 5)) #Generate data
A <- matrix(c(0.291, 0.6557, -0.5439, 0.5572), 2, 2)
X <- S %*% A
a <- fastICA(X, 2, alg.typ = "parallel", fun = "logcosh", alpha = 1,
     method = "R", row.norm = FALSE, maxit = 200, tol = 0.0001, verbose = TRUE) #ICA
                       Original Signals
                                                          Mixed Signals
                                                                                             ICA source estimates
                200
                     400
                         600
                              800
                                                   200
                                                        400
                                                            600
                                                                 800
                                                                      1000
                                                                                      200
                                                                                           400
                                                                                                600
                                                                                                     800
                                                                                                         1000
       0.0
                                           0.0
       -0.5
```

732A99/TDDE01