Kinematics: Local Linear Flows

24th Sept, 2018

Overview

A given fluid motion can be understood by looking at a local picture or at the global picture. The local picture refers to an analysis of the fluid motion at length scales much smaller than the macroscopic length scale. Looking at small length scales allows us to linearize the flow field and construct a locally linear description of the flow. The overall global flow might well be non-linear. The global flow is understood via means of streamlines, streaklines and pathlines. These two means of looking at a fluid flow will be explored in the following lectures. This lecture will focus on the local linear flows.

1 Linearity and its consequences

A local description of fluid flows requires us to operate at length scales much smaller than the macroscopic length scale. The macroscopic length scale is, roughly speaking, the length over which the fluid velocity varies substantially. Since we will be concerned with much smaller lengths than this, we can linearize the variation in velocity about any point \underline{X}_0 and consider only the linear variation of velocity with \underline{r} i.e. $\underline{u} \propto \underline{r}$. Taylor expanding about a point \underline{X}_0 gives:

$$\underline{u}(\underline{X}_0 + \underline{r}) = \underline{u}(\underline{X}_0) + \frac{\partial \underline{u}}{\partial \underline{r}} \Big|_{X_0} \cdot \underline{r} + O(r^2)$$
 (1)

$$\Rightarrow \delta \underline{u} = \frac{\partial \underline{u}}{\partial \underline{r}} \Big|_{\underline{X}_0} \underline{r} \tag{2}$$

Therefore, velocity at any point $\underline{X}_1 = \underline{X}_0 + \underline{r}$, is a linear function of the position. A transformation between position vector and the velocity vector must be carried out via a second order tensor which is the velocity gradient tensor in this case.

Note that, since velocity is a linear function of position, therefore, the velocity gradient tensor must be a constant independent of \underline{r} and hence independent of \underline{X}_1 . Therefore, the velocity gradient tensor is the same at

all points in the flow. If the velocity gradient is the same at all the points, it implies that the variation in velocity as seen from any point is the same as seen from any other point. Therefore, in a linear flow, the flow pattern remains identical at all points and there is no intrinsic length scale to the flow.

The fact that there is no length scale to the flow can also be seen from the dimensions of the velocity gradient $[M^0L^0T^{-1}]$. There is no length scale, but only a time scale which denotes the strength of the linear flow - how efficiently the flow stretches or deforms a fluid element.

2 The velocity gradient tensor

The velocity gradient tensor can be better analyzed if we seperate out its symmetric and antisymmetric parts and then from the symmetric part, seperate out the trace and a traceless part. This gives us:

$$\begin{split} \frac{\partial u_i}{\partial x_j} &= \underbrace{\frac{1}{2}} (\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i}) + \underbrace{\frac{1}{2}} (\frac{\partial u_i}{\partial x_j} - \frac{\partial u_j}{\partial x_i}) \\ \Rightarrow \frac{\partial u_i}{\partial x_j} &= \underbrace{\frac{e_{kk}}{3}} \delta_{ij} + \underbrace{\frac{1}{2}} (\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} - \frac{e_{kk}}{3} \delta_{ij}) + \underbrace{\frac{1}{2}} (\frac{\partial u_i}{\partial x_j} - \frac{\partial u_j}{\partial x_i}) \\ \Rightarrow \delta u_i &= \underbrace{\frac{\partial u_i}{\partial x_j}} r_j = \delta u_i^1 + \delta u_i^2 + \delta u_i^3 \end{split}$$

Therefore we have split our linear flow into three seperate velocity fields given by:

$$\delta u_i^1 = \frac{e_{kk}}{3} \delta_{ij} r_j$$

$$\delta u_i^2 = \frac{1}{2} \left(\frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} - \frac{e_{kk}}{3} \delta_{ij} \right) r_j$$

$$\delta u_i^3 = \frac{1}{2} \left(\frac{\partial u_i}{\partial x_j} - \frac{\partial u_j}{\partial x_i} \right) r_j$$

Based on the velocity gradient tensor associated with each of the three fields, we can conclude the following:

• δu_i^1

The velocity gradient has only diagonal terms which describe the normal strains on a fluid element. Normal forces cause expansion or contraction of a fluid element without causing shape distortion. Also, we see that $\delta u_i^1 = \frac{e_{kk}}{3} \delta_{ij} r_j = \frac{e_{kk}}{3} r_i$ - the flow is purely radial and causes volumetric changes without shape distortions.

The constant potential surfaces for this case are spheres and hence the streamlines (being perpendicular to constant potential surfaces are radial.

• δu_i^2

Since the trace of the velocity gradient is zero, there is no expansion or contraction of fluid elements under this velocity field. However, the non-zero off-diagonal elements indicate shear forces which lead to shape distortions without change in volume of the fluid element. Since the velocity gradient tensor for this case is symmetric, we can diagonalize it. Since it is also traceless, a general velocity gradient tensor for this type of flow will have the form:

$$\frac{\partial u_i^2}{\partial x_j} = \begin{pmatrix} a & 0 & 0\\ 0 & b & 0\\ 0 & 0 & -(a+b) \end{pmatrix}$$

Then the corresponding velocity becomes:

$$u_i^2 = \begin{pmatrix} a & 0 & 0 \\ 0 & b & 0 \\ 0 & 0 & -(a+b) \end{pmatrix} r_i$$

which indicates that flow goes out in directions 1 and 2 and comes in from direction 3 such that the total volume remains conserved. This is biaxial extensional flow. The streamlines can be easily visualized in 2D where velocity gradient becomes

$$u_i^2 = \begin{pmatrix} a & 0 \\ 0 & -a \end{pmatrix} r_i$$

$$\Rightarrow \begin{pmatrix} u_x \\ u_y \end{pmatrix} = \begin{pmatrix} a & 0 \\ 0 & -a \end{pmatrix} \begin{pmatrix} x \\ y \end{pmatrix}$$

$$\Rightarrow u_x = \frac{dx}{dt} = ax$$

$$u_y = \frac{dy}{dt} = -ay$$

$$\Rightarrow \frac{dy}{dx} = \frac{-y}{x}$$

$$\Rightarrow xy = C$$

and hence the streamlines for planar extensional flow are rectangular hyperbolae. Such flows have excellent stretching abilities.

The extension of a fluid element with time can be analyzed as follows:

$$\Rightarrow \frac{dr_1}{dt} = ar_1$$
$$\frac{dr_2}{dt} = -ar_2$$
$$\Rightarrow r_1 = r_{1_0}e^{at}$$
$$r_2 = r_{2_0}e^{-at}$$

which tells us that, in a hyperbolic linear flow, fluid elements get stretched exponentially with time. Along the stretching direction, the farther an element goes, the faster it gets stretched.

• δu_i^3

The velocity gradient here is antisymmetric. This means that the diagonal elements are zero and hence there are no volumetric changes. The velocity field can be obtained as follows:

$$\begin{split} \delta u_i^3 &= \omega_{ji} r_j \\ &= \frac{1}{2} (\frac{\partial u_i}{\partial x_j} - \frac{\partial u_j}{\partial x_i}) r_j \\ &= \frac{1}{2} (\delta_{il} \delta_{jm} - \delta_{im} \delta_{jl}) \frac{\partial u_l}{\partial x_m} r_j \\ &= \frac{1}{2} \epsilon_{ijk} \epsilon_{klm} \frac{\partial u_l}{\partial x_m} r_j \\ &= \frac{1}{2} \underline{\omega} \wedge \underline{r} \end{split}$$

This velocity field corresponds to solid body rotation. The angular velocity (Ω) gives the vorticity (ω) of the flow $(\omega = \Omega/2)$. The previous two velocity fields were irrotational and therefore, we can define a scalar potential corresponding to them.

It should be noted that if a line element is kept in a linear flow, then it tends to align with the stretching direction (in extensional flow), rotate (in rigidly rotating flow) or translate (in a radial flow). But, in a linear flow, a line element doesn't bend because bending occurs when there is a non-linear variation of velocity along the line. For a linear flow, the velocity variation between any two points is obviously linear.

3 A general classification of linear flows

Any general linear flow can be constructed using a linear combination of planar extensional flow and solid body rotation. In principle, one can write

$$\nabla \underline{u} = \lambda \begin{pmatrix} 1 & 0 \\ 0 & -1 \end{pmatrix} + (1 - \lambda) \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix}$$

But the resulting matrix can be simplified slightly if we rotate the coordinate axes for the extensional flow by $\pi/4$ and consider the velocity gradient

$$\nabla \underline{u} = \begin{pmatrix} 0 & a \\ a & 0 \end{pmatrix}$$

$$\Rightarrow \begin{pmatrix} u_x \\ u_y \end{pmatrix} = \begin{pmatrix} 0 & a \\ a & 0 \end{pmatrix} \begin{pmatrix} x \\ y \end{pmatrix}$$

$$\Rightarrow u_x = \frac{dx}{dt} = ay$$

$$u_y = \frac{dy}{dt} = ax$$

$$\Rightarrow \frac{dy}{dx} = \frac{x}{y}$$

$$\Rightarrow x^2 - y^2 = C$$

which gives rectangular hyperbolae with asymptotes at $\theta = \pm \pi/4$. Now to this planar extension we can add solid body rotation as follows:

$$\nabla \underline{u} = \frac{1+\alpha}{2} \underbrace{\begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix}}_{\text{irrotational extension}} + \frac{1-\alpha}{2} \underbrace{\begin{pmatrix} 0 & -1 \\ 1 & 0 \end{pmatrix}}_{\text{pure rotation}}$$

$$\Rightarrow \nabla \underline{u} = \begin{pmatrix} 0 & \alpha \\ 1 & 0 \end{pmatrix}$$

This one-parameter matrix provides us with a family of all possible planar linear flows. This can be seen as follows

$$\nabla \underline{u} = \begin{pmatrix} 0 & \alpha \\ 1 & 0 \end{pmatrix}$$

$$\Rightarrow \begin{pmatrix} u_x \\ u_y \end{pmatrix} = \begin{pmatrix} 0 & \alpha \\ 1 & 0 \end{pmatrix} \begin{pmatrix} x \\ y \end{pmatrix}$$

$$\Rightarrow u_x = \frac{dx}{dt} = \alpha y$$

$$u_y = \frac{dy}{dt} = x$$

$$\Rightarrow \frac{dy}{dx} = \frac{x}{\alpha y}$$

$$\Rightarrow x^2 - \alpha y^2 = C$$

As α is varied from -1 to 1, the streamlines changes from ellipses to hyperbolae. A visualization of the changing streamline pattern is given here. Varying α gives us

• $\alpha = -1$: circles - solid body rotation

- $-1 < \alpha < 0$: ellipses elliptic linear flow
- $\alpha = 0$: straight lines simple shear flow
- $0 < \alpha < 1$: hyperbolae hyperbolic linear flow
- $\alpha = 1$: rectangular hyperbolae planar extensional flow

4 Linear flow and Kolmogorov scale in Turbulence

A turbulent flow consists of a broad range of length and time scales. The length scale of the smallest eddy in the flow is known as the Kolmogorov length scale (l_k). At lengths scales smaller than l_k , we again observe linear flow. Obviously, the flow no longer has a length scale but only a time scale given by the velocity gradient tensor, given by the following relation

$$\underline{u} = (\nabla \underline{u})\underline{r}$$

The velocity gradient, being that for a linear flow, doesn't vary spatially. But owing to the unsteadiness in the flow it can vary with time. Hence the linear flow at any point keeps changing randomly with time.

A charaterstic of turbulent flow is that energy is supplied to the flow at large length scales, but it is dissipated at the smallest scales - the Kolmogorov scale, where viscosity finally becomes important. Viscosity smoothens out sharp gradients quickly and hence if $|\nabla \underline{u}|$ is large, the dissipation is also large. Let energy be supplied at a rate given by ϵ . The dissipated energy per unit mass can be written as $\sim u^2/t$ (kinetic energy dissipated per unit time). Since at l_k , all supplied energy must be dissipated, we have:

$$\frac{u_k^2}{t} = \frac{u_k^3}{l_k} = \epsilon$$

The ratio of energy supplied to energy dissipated is in fact the Reynolds number which will certainly be O(1) at Kolmogorov length scale. Therefore:

$$Re_k = \frac{l_k u_k}{\nu} \sim 1$$
$$\Rightarrow u_k \sim \frac{\nu}{l_k}$$

Now we can use this expression for velocity in the energy balance to write

$$\frac{u_k^3}{l_k} \sim \frac{\nu^3}{l_k^4} \sim \epsilon$$

$$\Rightarrow l_k \sim \left(\frac{\nu^3}{\epsilon}\right)^{1/4}$$

which is the Kolmogorov scale, quite easily obtained from just an energy balance. The expression tells us that high viscosity causes a large l_k . But more importantly, it tells us that as we supply more and mroe energy to the system, it modifies so that smaller and smaller flow scales appear so that eventually viscosity starts to dominates. We can get an idea as to how small l_k is compared to some geometric scale L.

$$\frac{L}{l_k} \sim \frac{L}{(\nu^3/\epsilon)^{1/4}}$$

In order to obtain the Reynolds number, we need macroscopic quantities (and not Kolmogorov scale quantities) in the above expression. So we substitute ϵ in terms of macroscopic velocity scale U and length L. As before $\epsilon \sim U^3/L$ and hence:

$$\frac{L}{l_k} \sim \frac{L}{(\nu^3/\epsilon)^{1/4}} \sim \frac{LU^{3/4}}{\nu^{3/4}L^{1/4}} \sim Re^{3/4}$$

$$\Rightarrow l_k \sim LRe^{-3/4}$$

Therefore, if a numerical simulation intends to resolve all length scales in a turbulent flow simulation, then this expression tells us how the grid resolution must scale with Re. If $Re \sim 10000$ then we have that $l_k \sim L/1000$, or we need 1000 points in each direction. In three dimensions then, this penalty will scale as $\sim Re^{-9/4}$.

This is how the smallest eddy size varies with space. If we want to capture all time scales in the flow, then we must determine the smallest time scale in the flow (t_k) in terms of some macroscopic time scale.

$$t_k^{-1} = \frac{u_k}{l_k} = \frac{\nu}{l_k^2} = \frac{\nu}{L^2 Re^{-6/4}}$$

If the macroscopic time is T ($\sim L/U$), then we have:

$$\frac{T}{t_k} = \frac{L\nu}{UL^2Re^{-6/4}} = Re^{1/2}$$

$$\Rightarrow t_k = T(Re^{-1/2})$$

This is how the time stepping for a turbulent simulation must scale with Re. Therefore, the total penalty for a turbulent simulation with Re becomes $\sim Re^{1/2}Re^{9/4} = Re^{11/4}$, which nearly Re^3 . As Reynolds number doubles, the number of nodes nearly go up by an order of magnitude.

5 Appendix

- 5.1 Proof that $\nabla \cdot u$ equals fractional rate of change of volume
- 5.2 Some applications of linear flows
- 5.2.1 Simple-shear flow
- 5.2.2 Local picture of a Point-Vortex
- 5.2.3 Flow between two cylinders

Let there be two concentric cylinders of radius R_1 and R_2 rotating with angular velocities Ω_1 and Ω_2 . The flow profile between these cylinders is given by

$$u_{\theta} = \frac{A}{r} + Br$$

We will briefly examine the local flow for two cases. Note that, if fluid sweeps past a rigid boundary with 'no-slip' condition at the wall, then the local flow very close to the wall will always be simple-shear flow. Velocity will be zero at the surface and will increase linearly away from the wall.

When the inner cylinder is rotating and outer cylinder is at rest ($\Omega_2 = 0$), we will have simple-shear flow at the outer cylinder. But close to the inner cylinder, r is small and hence $u_{\theta} = A/r + Br \sim A/r$. This is the flow due to a point vortex with the local flow picture given by the planar extension flow. Hence, close to the inner cylinder, one has planar extensional flow. As one moves away from the inner cylinder, the term Br starts to become dominant. This term is responsible for the solid body rotation type flow which contains vorticity. Addition of vorticity causes the transition from planar extension flow $(r \to R_1)$ to simple shear flow $(r \to R_2)$ via hyperbolic extensional flows $(R_1 \ll r \ll R_2)$.

When the outer cylinder is rotating and the inner cylinder is at rest $(\Omega_1 = 0)$, we have simple shear flow at the inner wall. Again as we move outwards towards increasing r, vorticity in the flow increases and leads to the more vortical elliptic linear flows. Right at the outer wall we reach solid body rotation which is a purely vortical flow.

5.3 2D Taylor-Green Vortex

$$u_1 = A\cos(x_1)\sin(x_2)$$

$$u_2 = -A\sin(x_1)\cos(x_2)$$