Thrashing and Storage Devices

ECE 469, March 26

Aravind Machiry



RECAP: Page Replacement Algorithms

- Optimal
- FIFO
- Random
- Approximate LRU (NRU)
- FIFO with 2nd chance
- Clock: a simple FIFO with 2nd chance
- Enhanced FIFO with 2nd chance

Whose pages should be replaced?



- Global replacement:
 - All pages from all processes are lumped into a single replacement pool
 - Most flexibility, least (performance) isolation
- Local replacement
 - Per-process replacement:
 - Each process has a separate pool of pages
 - Per-user replacement:
 - Lump all processes for a given user into a single pool
- In local replacement, must have a mechanism for (slowly) changing the allocations to each pool

Why we need paging? Handling low memory



Suppose you have 8GB of main memory

- Can you run a program that its program size is 16GB?
 - Yes, you can load them part by part
 - This is because we do not use all of data at the same time
- Can your OS do this execution seamlessly to your application?


Why we need paging? Efficient use of memory!



- Process exhibit locality not all pages of a process need to be in memory!
- Bringing in only required pages allows us to execute multiple processes seamlessly:
 - Increases CPU utilization

Increasing multiprogramming increases CPU utilization!!?





What happens when there is not enough physical memory?




- Suppose many processes are making frequent references to 50 pages, memory has 49
- Assuming LRU
 - Each time one page is brought in, another page, whose content will soon be referenced, is thrown out
- What is the average memory access time?
- The system is spending most of its time paging!
- The progress of programs makes it look like "memory access is as slow as disk", rather than "disk being as fast as memory"

Thrashing!!




• Thrashing ≡ a process is busy swapping pages in and out


Thrashing can lead to vicious cycle




- If a process does not have "enough" pages, the page-fault rate is very high. This leads to:
 - low CPU utilization
 - OS thinks that it needs to increase the degree of multiprogramming (actual behavior of early paging systems)
 - another process added to the system
 - page fault rate goes even higher

Thrashing!!





What causes Thrashing!?



- The system does not know it has taken more work than it can handle
- Virtual memory bites back!

- Mitigating Thrashing:
 - Run fewer programs.
 - Dropping or degrading a course if taking too many than you can handle

Demand Paging and Thrashing!?

- Why does demand paging work?
 - Data reference exhibits locality

- Why does thrashing occur?
 - \bullet Size of locality > total memory size

Intuitively, what to do about thrashing?




- If a single process's locality too large for memory, what can OS do?
 - e.g., pin most data (hotter data) in memory, sacrifice the rest
- If the problem arises from the sum of several processes?
 - Figure out how much memory each process needs "locality"
 - What can we do?
 - Can limit effects of thrashing using local replacement
 - Or, bring a process' working set before running it
 - Or, wait till there is enough memory for a process's need

Key Observation

- Locality in memory references
 - Spatial and temporal
- Want to keep a set of pages in memory that would avoid a lot of page faults
 - "Hot" pages






Working Set Model – by Peter Denning (Purdue CS head, 79-83)



- An informal definition:
 - Working set: The collection of pages that a process is working within a time interval, and which must thus be resident if the process is to avoid thrashing

- But how to turn the concept/theory into practical solutions?
 - Capture the working set
 - Influence the scheduler or replacement algorithm



Working Sets




```
page reference table  ... 2615777751623412344434344413234443444...   \Delta \qquad \qquad \Delta \qquad \qquad
```

- The working set size is num of pages in the working set
 - the number of pages touched in the interval [t- Δ +1..t].
- The working set size changes with program locality.
 - during periods of poor locality, you reference more pages.
 - Within that period of time, you will have a larger working set size.
- Goal: keep WS for each process in memory.

Working Set Model

- Usage idea: use recent needs of a process to predict its future needs
 - Choose Δ, the WS parameter
 - At any given time, all pages referenced by a process in its last Δ seconds comprise its working set
 - Don't execute a process unless there is enough memory to fit its working set
- Needs a companion replacement algorithm






Working Set Replacement Algorithm



- Main idea
 - Take advantage of reference bits
 - Variation of FIFO with 2nd chance
- An algorithm (assume reference bit)
 - On a page fault, scan through all pages of the process
 - If the reference bit is 1, clear the bit, record the current time for the page
 - If the reference bit is 0, check the "last use time"
 - If the page has not been used within Δ , replace the page
 - Otherwise, go to the next page


Working Set Clock Algorithm (assume reference bit + modified bit)



- Upon page fault, follow the clock hand
- If the reference bit is 1, set reference bit to 0, set the current time for the page and go to the next
- If the reference bit is 0, check "last use time"
 - If page used within Δ , go to the next
 - If page not used within Δ and modify bit is 1
 - Schedule the page for page out (then reset modify bit) and go to the next
 - If page not used within Δ and modified bit is 0
 - Replace this page

Challenges with WS algorithm implementation


- What should ∆ be?
 - What if it is too large?
 - What if it is too small?



- How many jobs need to be scheduled in order to keep CPU busy?
 - Too few □ cannot keep CPU busy if all doing I/O
 - Too many □ their WS may exceed memory

Working Sets in Real World





More Challenges with WS algorithm implementation

- Working set isn't static
- There often isn't a single "working set"
 - e.g., Multiple plateaus in previous curve (L1 \$, L2 \$, etc)
 - Program coding style affects working set
 - e.g., matrix multiply
- Working set is often hard to measure
 - What's the working set of an interactive program?
 - How to calculate WS if pages are shared?

Storage Devices

Devices used to store data



Storage Technologies

- Tapes
- Magnetic Disks
- Flash Memory



Tapes

- Low-cost, highly-reliable storage.
- Slow access: ~30MB Per Second.




Magnetic Disks


- (Used to be) De Facto standard for storage.
- Medium access: ~150MB Per Second.
- Relatively high failure rate (vs Tape).


Magnetic Disk






Disk Components






Surface Organized into Tracks





Tracks Broken into Sectors







- Disk accesses in the granularity of a sector (usually 512KB)
- This I/O interface is called block I/O interface


Disk Head Position






Rotation is Counterclockwise






About to Read Blue Sector





After Reading Blue Sector






After **BLUE** read


Red Request Scheduled Next






After **BLUE** read


Seek to Red's Track






Seek to Red Sector to Reach Head





Read Red Sector





Real numbers for Modern Disks



- # of platters: 1-8
- 2-16 surfaces for data
- # of tracks per surface: 10s of 1000s
- same thing as # of cylinders
- # sectors per track: 200-1000
- so, 100-500KB
- # of bytes per sector: usually 512
- can be chosen by OS for some disks

Response Time for Disks

- Access time: (service time for a disk access)
 - Once command is received, how long it takes to get the data to OS.
 - Seek + Rotation + Transfer

- Response time:
 - Commands may be queued!
 - Queue time + Access time

Seek Time



- Time required to move head over desired track
 - Physically moving the head, not electronic => slow!
- A seek has up to four components
 - accelerate
 - coast at max velocity
 - decelerate
 - settle onto correct track
- Seek time depends on workload
 - For random workloads, longer seek time

Rotational Latency



- Time required for the first desired sector to reach head
- Depends on rotation speed
 - measured in Rotations Per Minute (RPMs)
- Computing average rotational latency
 - for almost all workloads, we can safely assume that there is an equal likelihood of landing on any sector of the track
 - this gives equal probability of each rotational latency
 - from 0 sectors to N-1 sectors
 - thus, average rotational latency is time for 1/2 revolution
 - e.g., for 7200 RPM
 - one rotation = 60s / 7200 = 8.33 ms
 - average rotational latency = 4.16 ms

Modern Disk Performance Characteristics



- Seek times: 0.5-15ms, depending on distance
 - average 5-6ms
 - improving at 7-10% per year

- Rotation speeds: 5600-15000 RPMs
 - improving at 7-10% per year


Disk failures

- Disks fail more often....
 - When continuously powered-on
 - With heavy workloads
 - Under high temperatures



How disks fail?

- How do disks fail?
 - Whole disk can stop working (e.g., motor dies, firmware errors)
 - Transient problem (cable disconnected, firmware errors)
 - Individual sectors can fail (e.g., head crash or scratch)
 - Data can be corrupted or block not readable/writable




Fixing disk errors

- Disks can internally fix some sector problems
 - ECC (error correction code): Detect/correct bit flips
 - Retry sector reads and writes: Try 20-30 different offset and timing combinations for heads
 - Remap sectors: Do not use bad sectors in future
 - How does this impact performance contract??



Flash Memory: NAND Cell







Flash Memory: NAND Cell



Reading



0




1


Flash Memory: NAND Cell



Writing



0



1

Flash Memory




NAND Flash Die Layout Die Plane Block Page

Flash Memory

- Page Size: 512 4K bytes.
- Write needs complete erasure:
 - Erase before write.
 - Cannot go cell-wise from 0 -> 1
 - Any cells that have been set to 0 (written to) by programming can only be reset to 1 by erasing the entire block.
- Writes >> Reads

Flash Memory: SSD







SSD: Flash Translation Layer

- Maps logical blocks to real blocks.
- Hides erase before write.
- Maintains free blocks.

