

方档: <https://docs.docker.com/engine/install/centos/>

1, Uninstall old versions

```
1 sudo yum remove docker \  
2     docker-client \  
3     docker-client-latest \  
4     docker-common \  
5     docker-latest \  
6     docker-latest-logrotate \  
7     docker-logrotate \  
8     docker-engine
```

2, Set up the repository

```
1 sudo yum install -y yum-utils  
2  
3 sudo yum-config-manager \  
4     --add-repo \  
5     https://download.docker.com/linux/centos/docker-ce.repo  
6  
7 sudo yum -y update
```

3, Install Docker Engine

```
1 sudo yum install docker-ce docker-ce-cli containerd.io
```

4, 然后就是服务的启停了

```
1 // 起
2 systemctl start docker
3 // 停
4 system stop docker
5 // 查看状态
6 systemctl status docker
7 // 开机自己启动
8 systemctl enable docker
9 // 重新启动
10 sudo systemctl restart docker
11
12 # 如果启动失败，可能需要执行以下命令
13 sudo systemctl daemon-reload
```

当然，还有一些其他配置，可以参考文档<https://docs.docker.com/engine/install/centos/>

安装docker-compose

安装docker-compose之前得先安装docker

```
1 sudo curl -L "https://github.com/docker/compose/releases/download/2.20.0/docker-
  compose-$(uname -s)-$(uname -m)" -o /usr/local/bin/docker-compose
2
3 sudo chmod +x /usr/local/bin/docker-compose
```

Note: If the command docker-compose fails after installation, check your path. You can also create a symbolic link to /usr/bin or any other directory in your path.

For example:

```
1 sudo ln -s /usr/local/bin/docker-compose /usr/bin/docker-compose
```

docker-registry的安装

我的目的地是搭建一个只用用户名和密码登录的本地开发环境，和docker官网上的安装方法有差别，记录如下

<https://docs.docker.com/registry/deploying/>

第一步，进入安装目录

```
1 cd /root/app/docker-registry
```

第二步,生成认证文件（testuser是用户名，testpassword是密码，可以自己指定）

```
1 mkdir auth
2 docker run \
3   --entrypoint htpasswd \
4   httpd:2 -Bbn testuser testpassword > auth/htpasswd
```

第三步，安装

```
1 docker run -d \
2   -p 5000:5000 \
3   --restart=always \
4   --name registry \
5   -v "$(pwd)/auth:/auth \
6   -e "REGISTRY_AUTH=htpasswd" \
7   -e "REGISTRY_AUTH_HTPASSWD_REALM=Registry Realm" \
8   -e REGISTRY_AUTH_HTPASSWD_PATH=/auth/htpasswd \
9   registry:2
```

docker官网上的安装

```
1 docker run -d \  
2   -p 5000:5000 \  
3   --restart=always \  
4   --name registry \  
5   -v "$(pwd)"/auth:/auth \  
6   -e "REGISTRY_AUTH=htpasswd" \  
7   -e "REGISTRY_AUTH_HTPASSWD_REALM=Registry Realm" \  
8   -e REGISTRY_AUTH_HTPASSWD_PATH=/auth/htpasswd \  
9   -v "$(pwd)"/certs:/certs \  
10  -e REGISTRY_HTTP_TLS_CERTIFICATE=/certs/domain.crt \  
11  -e REGISTRY_HTTP_TLS_KEY=/certs/domain.key \  
12  registry:2
```

因为我们不需要https认证，所以去除几行。

然后就可以登录了

```
1 docker login 192.168.199.104:5000  
2 docker login -u testuser -p testpassword 192.168.199.104:5000
```

查看docker-rejestr的镜像占用存储大小

```
1 du -sch /val/lib/rejestr
```

docker image时去除none

```
1 docker images --filter "dangling=false"
```

在安装K8s时docker 默认不能以root用户运行，执行以下命令让其他用户可以执行docker

```
1 sudo usermod -aG docker $USER && newgrp docker
```