



Utility scale dynamic circuits

Mirko Amico
Technical Lead – Quantum Algorithm Engineering
IBM Quantum




What is dynamic circuit?

Unitary quantum circuit





Dynamic quantum circuit




What is dynamic circuit?

Unitary quantum circuit




Dynamic quantum circuit




Dynamic circuits → can implement *any* allowed quantum process, not just unitary evolution.

What is dynamic circuit?

Unitary quantum circuit



Dynamic quantum circuit




Dynamic circuits → can implement *any* allowed quantum process, not just unitary evolution.

Measurements and feedforward → new quantum algorithms?


What makes dynamic circuits powerful?

A spacetime view:




What makes dynamic circuits powerful?

1. The ability to **reset & reuse** qubits can reduce **spatial** overhead




What makes dynamic circuits powerful?

1. The ability to **reset & reuse** qubits can reduce **spatial** overhead




Example: staircase circuit




What makes dynamic circuits powerful?

1. The ability to **reset & reuse** qubits can reduce **spatial** overhead




Example: staircase circuit




What makes dynamic circuits powerful?

2. Measurements and feedforward can reduce temporal overhead



What makes dynamic circuits powerful?

2. Measurements and feedforward can reduce temporal overhead




Example: GHZ state preparation


$$|\Psi\rangle = \frac{1}{\sqrt{2}}(|000\dots 0\rangle + |111\dots 1\rangle)$$

What makes dynamic circuits powerful?

2. Measurements and feedforward can reduce temporal overhead



Unitary: $O(N)$ depth




Example: GHZ state preparation


$$|\Psi\rangle = \frac{1}{\sqrt{2}}(|000\dots 0\rangle + |111\dots 1\rangle)$$

What makes dynamic circuits powerful?

2. Measurements and feedforward can reduce temporal overhead



Unitary: $O(N)$ depth



Example: GHZ state preparation


$$|\Psi\rangle = \frac{1}{\sqrt{2}}(|000\dots 0\rangle + |111\dots 1\rangle)$$

There is a speed-limit for unitarily spreading correlations


Bravyi et al., PRL (2006)

What makes dynamic circuits powerful?

2. Measurements and feedforward can reduce temporal overhead



Unitary: $O(N)$ depth




Example: GHZ state preparation

$$|\Psi\rangle = \frac{1}{\sqrt{2}}(|000\dots 0\rangle + |111\dots 1\rangle)$$

There is a speed-limit for unitarily spreading correlations


Bravyi et al., PRL (2006)

Dynamic: $O(1)$ depth




What makes dynamic circuits powerful?

2. Measurements and feedforward can reduce temporal overhead



Unitary: $O(N)$ depth




Example: GHZ state preparation

$$|\Psi\rangle = \frac{1}{\sqrt{2}}(|000\dots 0\rangle + |111\dots 1\rangle)$$

There is a speed-limit for unitarily spreading correlations




Bravyi et al., PRL (2006)

Dynamic: $O(1)$ depth



Applications of dynamic circuits

(beyond error correction)



State preparation

- Long-range entangled states [1]
- Matrix product states [2]
- Topologically ordered states [3]
- Gibbs states [4]

Non-unitary processes

- Driven-dissipative dynamic
- Measurement-induced phase transitions [5]
- Nonlinear transformations [6]




Unitary compilation

- Long-range entangling gates [1]
- Many-qubit gates (e.g. fanout) [7]
- Distributed quantum computing

[1] Bäumer et al., PRX Quantum (2024); [2] Smith et al., PRX Quantum (2024); [3] Tanitasadakarn et al., PRX Quantum (2023);
[4] Lin et al., arXiv: 2505.21308 (2025); [5] Skinner et al., PRX (2019); [6] Holmes et al., PRResearch (2023); [7] Bäumer et al., PRResearch (2024)

Applications of dynamic circuits

(beyond error correction)



State preparation

- Long-range entangled states [1]
- Matrix product states [2]
- Topologically ordered states [3]
- Gibbs states [4]

Non-unitary processes

- Driven-dissipative dynamics
- Measurement-induced phase transitions [5]
- Nonlinear transformations [6]


Unitary compilation

- Long-range entangling gates [1]
- Many-qubit gates (e.g. fanout) [7]
- Distributed quantum computing

[1] Bäumer et al., PRX Quantum (2024); [2] Smith et al., PRX Quantum (2024); [3] Tanitasadakarn et al., PRX Quantum (2023);
[4] Lin et al., arXiv: 2505.21308 (2025); [5] Skinner et al., PRX (2019); [6] Holmes et al., PRResearch (2023); [7] Bäumer et al., PRResearch (2024)


Affleck-Kennedy-Lieb-Tasaki (AKLT) state

Spin-1 chain: encode each spin-1 site with a pair of qubits



Affleck-Kennedy-Lieb-Tasaki (AKLT) state


Spin-1 chain: encode each spin-1 site with a pair of qubits



- A prototypical example of a matrix product state (MPS)

Affleck-Kennedy-Lieb-Tasaki (AKLT) state


Spin-1 chain: encode each spin-1 site with a pair of qubits



- A prototypical example of a matrix product state (MPS)
- An example of symmetry-protected topological (SPT) order [1]

Affleck-Kennedy-Lieb-Tasaki (AKLT) state


Spin-1 chain: encode each spin-1 site with a pair of qubits



- A prototypical example of a matrix product state (MPS)
- An example of symmetry-protected topological (SPT) order [1]
- A resource for measurement-based quantum computation [2-3]

Affleck-Kennedy-Lieb-Tasaki (AKLT) state

Spin-1 chain: encode each spin-1 site with a pair of qubits




- A prototypical example of a matrix product state (MPS)
- An example of symmetry-protected topological (SPT) order [1]
- A resource for measurement-based quantum computation [2-3]
- Preparation: $O(N)$ depth unitary circuit $\rightarrow O(1)$ depth dynamic circuit [4, 5]

Dynamic circuits (initial release)

SMITH, CRANE, WIEBE, and GIRVIN

PRX QUANTUM **4**, 020315 (2023)




Presented at IBM Quantum Summit (2022)

- Up to $N_{\text{sites}} = 6$ AKLT state preparation
 - 14 qubits (unitary)
 - 18 qubits (measurement based)
 - 4 used as fusion qubits
- Post-process only (no ffwd)

Dynamic circuits (initial release)

SMITH, CRANE, WIEBE, and GIRVIN

PRX QUANTUM 4, 020315 (2023)



Presented at IBM Quantum Summit (2022)

- Up to $N_{\text{sites}} = 6$ AKLT state preparation
 - 14 qubits (unitary)
 - 18 qubits (measurement based)
 - 4 used as fusion qubits
- Post-process only (no ffwd)

Dynamic circuits capability introduced at the summit in 2022 enabled this experiment to run with **real time feed-forward!**

But with some challenges and limitations...

Re-introduction of Dynamic Circuits

Previous version

- Parallel feed forward operations limited to 10 bit input using Switch
 - Up to 12 site AKLT state

Re-introduction of Dynamic Circuits

Previous version

- Parallel feed forward operations limited to 10 bit input using Switch
 - Up to 12 site AKLT state
- Measurement used mid-circuit and terminal were all the same

Re-introduction of Dynamic Circuits

Previous version

- Parallel feed forward operations limited to 10 bit input using Switch
 - Up to 12 site AKLT state
- Measurement used mid-circuit and terminal were all the same
- Non-deterministic timing
 - Dynamical decoupling limited to static part of the circuit

Re-introduction of Dynamic Circuits


Previous version

- Parallel feed forward operations limited to 10 bit input using Switch
 - Up to 12 site AKLT state
- Measurement used mid-circuit and terminal were all the same
- Non-deterministic timing
 - Dynamical decoupling limited to static part of the circuit
- No visualization of scheduled circuit made it challenging

Re-introduction of Dynamic Circuits

Previous version

- Parallel feed forward operations limited to 10 bit input using Switch
 - Up to 12 site AKLT state
- Measurement used mid-circuit and terminal were all the same
- Non-deterministic timing
 - Dynamical decoupling limited to static part of the circuit
- No visualization of scheduled circuit made it challenging



New dynamic circuits features

- Parallel ifs / feed forward operations
 - Demonstrate up to 30 site AKLT state using 90 qubits

Re-introduction of Dynamic Circuits

Previous version

- Parallel feed forward operations limited to 10 bit input using Switch
 - Up to 12 site AKLT state
- Measurement used mid-circuit and terminal were all the same
- Non-deterministic timing
 - Dynamical decoupling limited to static part of the circuit
- No visualization of scheduled circuit made it challenging



New dynamic circuits features

- Parallel ifs / feed forward operations
 - Demonstrate up to 30 site AKLT state using 90 qubits
- Faster, independently calibrated MidCircuitMeasure enabled

Re-introduction of Dynamic Circuits

Previous version

- Parallel feed forward operations limited to 10 bit input using Switch
 - Up to 12 site AKLT state
- Measurement used mid-circuit and terminal were all the same
- Non-deterministic timing
 - Dynamical decoupling limited to static part of the circuit
- No visualization of scheduled circuit made it challenging




New dynamic circuits features

- Parallel ifs / feed forward operations
 - Demonstrate up to 30 site AKLT state using 90 qubits
- Faster, independently calibrated MidCircuitMeasure enabled
- Stretch enables better implementation of dynamical decoupling during feed-forward time

Re-introduction of Dynamic Circuits

Previous version

- Parallel feed forward operations limited to 10 bit input using Switch
 - Up to 12 site AKLT state
- Measurement used mid-circuit and terminal were all the same
- Non-deterministic timing
 - Dynamical decoupling limited to static part of the circuit
- No visualization of scheduled circuit made it challenging



New dynamic circuits features

- Parallel ifs / feed forward operations
 - Demonstrate up to 30 site AKLT state using 90 qubits
- Faster, independently calibrated MidCircuitMeasure enabled
- Stretch enables better implementation of dynamical decoupling during feed-forward time
- Scheduled circuits are returned (beta) to help with debugging and optimization

AKLT state preparation with utility scale dynamic circuits

- Different methods to prepare the AKLT states:
 1. Unitary
 2. Measurement based without dynamic circuits (post-process)
 3. Measurement based with dynamic circuits (real-time feed-forward)
 4. Hybrid (combine unitary and dynamic)

AKLT state preparation with utility scale dynamic circuits

- Different methods to prepare the AKLT states:
 1. Unitary
 2. Measurement based without dynamic circuits (post-process)
 3. Measurement based with dynamic circuits (real-time feed-forward)
 4. Hybrid (combine unitary and dynamic)
- What changes in the circuit:
 1. Extra ancilla qubits needed
 2. Depths of the circuit: 2Q gate and measurement layers


AKLT state preparation with utility scale dynamic circuits

- Different methods to prepare the AKLT states:
 1. Unitary
 2. Measurement based without dynamic circuits (post-process)
 3. Measurement based with dynamic circuits (real-time feed-forward)
 4. Hybrid (combine unitary and dynamic)
- What changes in the circuit:
 1. Extra ancilla qubits needed
 2. Depths of the circuit: 2Q gate and measurement layers
- What features could be used to improve:
 1. Parallel ifs for larger state preparation
 2. Different measurement types
 3. Stretch DD
 4. Visualization (beta) for optimization and debugging

Validation of AKLT state preparation

String order

$$\langle O_{\text{str}}^z \rangle_{\ell,i} = \langle S_i^z \prod_{k=1}^{\ell-2} e^{i\pi S_{i+k}^z} S_{i+\ell-1}^z \rangle$$




Non-zero value: fingerprint of symmetry-protected topological (SPT) order

Validation of AKLT state preparation


String order

$$\langle O_{\text{str}}^z \rangle_{\ell,i} = \langle S_i^z \prod_{k=1}^{\ell-2} e^{i\pi S_{i+k}^z} S_{i+\ell-1}^z \rangle$$



Non-zero value: fingerprint of symmetry-protected topological (SPT) order


$N_{\text{sites}} = 30$ on Heron processor



Validation of AKLT state preparation

String order


$$\langle O_{\text{str}}^z \rangle_{\ell,i} = \langle S_i^z \prod_{k=1}^{\ell-2} e^{i\pi S_{i+k}^z} S_{i+\ell-1}^z \rangle$$



Non-zero value: fingerprint of symmetry-protected topological (SPT) order

Ex) $\ell = 10$


$N_{\text{sites}} = 30$ on Heron processor



21 total *length 10* chains

AKLT state preparation with utility scale dynamic circuits

- Different methods to prepare the AKLT states:
 1. Unitary
 2. Measurement based without dynamic circuits (post-process)
 3. Measurement based with dynamic circuits (real-time feed-forward)
 4. Hybrid (combine unitary and dynamic)
- What changes in the circuit:
 1. Extra ancilla qubits needed
 2. Depths of the circuit: 2Q gate and measurement layers
- What features could be used to improve:
 1. Parallel ifs for larger state preparation
 2. Different measurement types
 3. Stretch DD
 4. Visualization (beta) for optimization and debugging




Unitary AKLT state preparation ($N_{\text{sites}} = 6$)

Total number of qubits needed

$$= N_{\text{sites}} \times 2 + \text{ancillas}$$

$$= N_{\text{sites}} \times 2 + 2 = 14$$




On IBM Herons, transpiles to
 $Rz(\theta)$'s plus:

$$7CZ + 10Sx$$

per 2 N_{sites}


Unitary AKLT state preparation ($N_{\text{sites}} = 6$)

Total number of qubits needed
= $N_{\text{sites}} \times 2 + \text{ancillas}$
= $N_{\text{sites}} \times 2 + 2 = 14$





AKLT state preparation with utility scale dynamic circuits

- Different methods to prepare the AKLT states:
 1. Unitary
 2. Measurement based without dynamic circuits (post-process)
 3. Measurement based with dynamic circuits (real-time feed-forward)
 4. Hybrid (combine unitary and dynamic)
- What changes in the circuit:
 1. Extra ancilla qubits needed
 2. Depths of the circuit: 2Q gate and measurement layers
- What features could be used to improve:
 1. Parallel ifs for larger state preparation
 2. Different measurement types
 3. Stretch DD
 4. **Visualization (beta)** for optimization and debugging




Unitary scheduled circuit ($N_{\text{sites}} = 6$)



```
job.result().metadata["compilation"]["scheduler_timing"]["timing"]
```

Validation of AKLT state preparation ($N_{\text{sites}} = 30$)


Unitary (62 qubits)




Circuit duration: $\sim 16.3 \mu s$

Validation of AKLT state preparation ($N_{\text{sites}} = 30$)

Unitary (62 qubits)




Circuit duration: $\sim 16.3 \mu\text{s}$




21 x length-10 chains

AKLT state preparation with utility scale dynamic circuits

- Different methods to prepare the AKLT states:
 1. Unitary ($\sim 16.3\mu s$)
 2. **Measurement based without dynamic circuits (post-process)**
 3. Measurement based with dynamic circuits (real-time feed-forward)
 4. Hybrid (combine unitary and dynamic)
- What changes in the circuit:
 1. Extra ancilla qubits needed
 2. Depths of the circuit: 2Q gate and measurement layers
- What features could be used to improve:
 1. Parallel ifs for larger state preparation
 2. Different measurement types
 3. Stretch DD
 4. Visualization (beta) for optimization and debugging




Measurement based AKLT state preparation ($N_{\text{sites}} = 6$)



$Z(\theta)$'s plus: $7 \times CZ + 10 \times Sx$


$$\begin{aligned} \text{Total number of qubits needed} \\ &= N_{\text{sites}} \times 2 + \text{ancillas} \\ &= N_{\text{sites}} \times 3 = 18 \end{aligned}$$




On IBM Herons, transpiles to $Rz(\theta)$'s plus:

$7CZ + 10Sx$
for any N_{sites}

Measurement based scheduled circuit ($N_{\text{sites}} = 6$)




$Z(\theta)$'s plus: $7CZ + 10Sx$




Validation of AKLT state preparation ($N_{\text{sites}} = 30$)

Measurement based (90 qubits)




Circuit duration: $\sim 3.8 \mu\text{s}$




21 x length-10 chains

Validation of AKLT state preparation ($N_{\text{sites}} = 30$)


Measurement based (90 qubits) $l = 10$



Circuit duration: $\sim 3.8 \mu\text{s}$



(90 qubits)




(62 qubits)

21 x length-10 chains


AKLT state preparation with utility scale dynamic circuits

- Different methods to prepare the AKLT states:
 1. Unitary ($\sim 16.3\mu s$)
 2. Measurement based without dynamic circuits (post-process) ($\sim 3.8\mu s$)
 - 3. Measurement based with dynamic circuits (real-time feed-forward)**
 4. Hybrid (combine unitary and dynamic)
- What changes in the circuit:
 1. Extra ancilla qubits needed
 2. Depths of the circuit: 2Q gate and measurement layers
- What features could be used to improve:
 - 1. Parallel ifs for larger state preparation**
 2. Different measurement types
 3. Stretch DD
 4. Visualization (beta) for optimization and debugging




Dynamic AKLT state preparation ($N_{\text{sites}} = 6$)


Total number of qubits needed
 $= N_{\text{sites}} \times 2 + \text{ancillas}$
 $= N_{\text{sites}} \times 3 = 18$




Dynamic scheduled circuit ($N_{\text{sites}} = 6$)




Dynamic scheduled circuit ($N_{\text{sites}} = 6$)





Dynamic scheduled circuit ($N_{\text{sites}} = 6$)



Dynamic scheduled circuit ($N_{\text{sites}} = 6$)




Dynamic scheduled circuit ($N_{\text{sites}} = 6$)




AKLT state preparation with utility scale dynamic circuits



- Different methods to prepare the AKLT states:
 1. Unitary ($\sim 16.3\mu s$)
 2. Measurement based without dynamic circuits (post-process) ($\sim 3.8\mu s$)
 - 3. Measurement based with dynamic circuits (real-time feed-forward)**
 4. Hybrid (combine unitary and dynamic)
- What changes in the circuit:
 1. Extra ancilla qubits needed
 2. Depths of the circuit: 2Q gate and measurement layers
- What features could be used to improve:
 - 1. Parallel ifs for larger state preparation**
 2. Different measurement types
 - 3. Stretch DD**
 4. Visualization (beta) for optimization and debugging



Dynamic with stretch scheduled circuit ($N_{\text{sites}} = 6$)




Dynamic with stretch scheduled circuit ($N_{\text{sites}} = 6$)




AKLT state preparation with utility scale dynamic circuits

- Different methods to prepare the AKLT states:
 1. Unitary ($\sim 16.3\mu s$)
 2. Measurement based without dynamic circuits (post-process) ($\sim 3.8\mu s$)
 - 3. Measurement based with dynamic circuits (real-time feed-forward)**
 4. Hybrid (combine unitary and dynamic)
- What changes in the circuit:
 1. Extra ancilla qubits needed
 2. Depths of the circuit: 2Q gate and measurement layers
- What features could be used to improve:
 - 1. Parallel ifs for larger state preparation**
 2. Different measurement types
 - 3. Stretch DD**
 4. Visualization (beta) for optimization and debugging






Validation of AKLT state preparation ($N_{\text{sites}} = 30$)

Dynamic (90 qubits)




Circuit duration: $\sim 8\mu\text{s}$






21 x length-10 chains

Validation of AKLT state preparation ($N_{\text{sites}} = 30$)

Dynamic (90 qubits)




Circuit duration: $\sim 8\mu\text{s}$



21 x length-10 chains


AKLT state preparation with utility scale dynamic circuits

- Different methods to prepare the AKLT states:
 1. Unitary ($\sim 16.3\mu s$)
 2. Measurement based without dynamic circuits (post-process) ($\sim 3.8\mu s / \sim 6.4\mu s$)
 - 3. Measurement based with dynamic circuits (real-time feed-forward)** ($\sim 8\mu s$)
 4. Hybrid (combine unitary and dynamic)
- What changes in the circuit:
 1. Extra ancilla qubits needed
 2. Depths of the circuit: 2Q gate and measurement layers
- What features could be used to improve:
 1. Parallel ifs for larger state preparation
 2. Different measurement types
 3. Stretch DD
 4. Visualization (beta) for optimization and debugging




AKLT state preparation with utility scale dynamic circuits

- Different methods to prepare the AKLT states:
 1. Unitary ($\sim 16.3\mu s$)
 2. Measurement based without dynamic circuits (post-process) ($\sim 3.8\mu s / \sim 6.4\mu s$)
 - 3. Measurement based with dynamic circuits (real-time feed-forward)** ($\sim 8\mu s$)
 4. Hybrid (combine unitary and dynamic)
- What changes in the circuit:
 1. Extra ancilla qubits needed
 2. Depths of the circuit: 2Q gate and measurement layers
- What features could be used to improve:
 1. Parallel ifs for larger state preparation
 - 2. Different measurement types**
 3. Stretch DD
 4. Visualization (beta) for optimization and debugging



Dynamic AKLT state preparation ($N_{\text{sites}} = 6$)




MidCircuitMeasure instruction


Dynamic with original measure scheduled circuit

measure

Capture length: 1440ns




Dynamic with *measure_2* scheduled circuit



● measure

Capture length: 1440ns

Readout error




● measure_2




Capture length: 500ns

Validation of AKLT state preparation ($N_{\text{sites}} = 30$)

Dynamic (90 qubits)




Circuit duration: $\sim 7.1 \mu\text{s}$



21 x length-10 chains


AKLT state preparation with utility scale dynamic circuits

- Different methods to prepare the AKLT states:
 1. Unitary ($\sim 16.3\mu s$)
 2. Measurement based without dynamic circuits (post-process) ($\sim 3.8\mu s/\sim 6.4\mu s$)
 3. Measurement based with dynamic circuits (real-time feed-forward) ($\sim 8\mu s/7.1\mu s$)
 4. **Hybrid (combine unitary and dynamic)**
- What changes in the circuit:
 1. Extra ancilla qubits needed
 2. Depths of the circuit: 2Q gate and measurement layers
- What features could be used to improve:
 1. Parallel ifs for larger state preparation
 2. Different measurement types
 3. Stretch DD
 4. Visualization (beta) for optimization and debugging




Dynamic ($N_{\text{sites}} = 4$) plus unitary ($N_{\text{sites}} = 2$) extension

Total number of qubits needed
 $= N_{\text{sites}} \times 2 + \text{ancillas}$
 $= N_{\text{sites}} \times 2 + (N_{\text{sites}} - 2)$
 $= 16$






Validation of AKLT state preparation ($N_{\text{sites}} = 30$)

Dynamic + (L2+R2) unitary extension (86 qubits)




Circuit duration: $\sim 6.9 \mu\text{s}$







21 x length-10 chains

Validation of AKLT state preparation ($N_{\text{sites}} = 30$)

Dynamic + (L2+R2) unitary extension (86 qubits)




Circuit duration: $\sim 6.9 \mu\text{s}$



21 x length-10 chains

DD or no DD???



AKLT state preparation ($N_{\text{sites}} = 30$)

- Different methods to prepare the AKLT states:
 1. Unitary ($\sim 16.3\mu\text{s}$)
 2. Measurement based without dynamic circuits (post-process) ($\sim 3.8\mu\text{s}$ / $\sim 6.4\mu\text{s}$)
 3. Measurement based with dynamic circuits (real-time feed-forward) ($\sim 8\mu\text{s}$ / $\sim 7.1\mu\text{s}$)
 4. Hybrid (combine unitary and dynamic) ($\sim 6.9\mu\text{s}$)
- What changes in the circuit:
 1. Extra ancilla qubits needed
 2. Depths of the circuit: 2Q gate and measurement layers
- What features could be used to improve:
 1. Parallel ifs for larger state preparation
 2. Different measurement types
 3. Stretch DD
 4. Visualization (beta) for optimization and debugging

Summary

1. Parallel ifs enable utility scale experiments
2. More than one type of measurement enabled: `MidCircuitMeasure` instruction that maps to `measure_2`
3. Added `Stretch` as durations for `Delay` instructions for deferred timing resolution
4. Circuit timing visualization (beta) on dynamic circuits returned to users



