HDF5 Virtual Object Layer (VOL) Connector Author Guide

HDF5 1.12.0

*** PRELIMINARY ***

The HDF Group

9th December 2019



CONTENTS

Contents

1	Intr	oducti	on	1
2	\mathbf{Cre}	ating a	New Connector	1
	2.1		ew	1
	2.2	Source	s Of Information	1
	2.3		y vs Plugin vs Internal	2
	2.4	Build I	Files / VOL Template	3
	2.5		lass_t Boilerplate	3
	2.6	Initiali	zation and Shutdown	3
	2.7	Map S	torage to HDF5 File Objects	4
	2.8	Fill In	VOL Callbacks	4
	2.9	Testing	g Your Connector	4
	2.10	Passth	rough Connectors	4
		- ~		
3			nector Interface Reference	4
	3.1	Mappi	ng the API to the Callbacks	6
	3.2		ctor Information Callbacks	7
		3.2.1	info: size	7
		3.2.2	info: copy	8
		3.2.3	info: cmp	8
		3.2.4	info: free	8
		3.2.5	info: to_str	8
	9.9	3.2.6	info: from_str	8
	3.3		Wrap Callbacks	9
		3.3.1	wrap: get_object	9
		3.3.2	wrap: get_wrap_ctx	9
		3.3.3	wrap: wrap_object	
		3.3.4 $3.3.5$	1 0	10 10
	3.4			10
	5.4	3.4.1		10
		3.4.2		11
		3.4.3		11
		3.4.4		11
		3.4.5		12
		3.4.6		13
		3.4.7	*	14
		3.4.8		$\frac{14}{14}$
	3.5	Datase		14
		3.5.1		15
		3.5.2		15
		3.5.3	dataset: read	16
		3.5.4	dataset: write	16
		3.5.5	dataset: get	16
		3.5.6	dataset: specific	17
		3.5.7	dataset: optional	18
		3.5.8	dataset: close	18
	3.6	Dataty	pe Callbacks	19
		3.6.1	datatype: commit	19
		3.6.2	datatype: open	20
		3.6.3	datatype: get	20
		3.6.4	datatype: specific	21
		3.6.5	datatype: optional	22
		3.6.6	datatype: close	22
	3.7	File Ca	allbacks	22
		3.7.1	file: create	23
		3.7.2	file: open	23
		3.7.3	file: get	23
		3.7.4	file: specific	24

CONTENTS

	3.7.5	file: optional	26
	3.7.6	file: close	26
3.8	Group	Callbacks	26
	3.8.1	group: create	27
	3.8.2	group: open	27
	3.8.3	group: get	27
	3.8.4	group: specific	28
	3.8.5	group: optional	29
	3.8.6	group: close	29
3.9	Link (Callbacks	29
	3.9.1	link: create	30
	3.9.2	link: copy	30
	3.9.3	link: move	31
	3.9.4	link: get	31
	3.9.5	link: specific	32
	3.9.6	link: optional	33
3.10	Object	t Callbacks	33
		object: open	34
		object: copy	34
		object: get	35
		object: specific	35
		object: optional	36
3.11		st (Async) Callbacks	37
		request: wait	37
		request: notify	37
		request: cancel	38
		request: specific	38
		request: optional	38
		request: free	38
3 12		Callbacks	39
0.12		blob: put	39
		blob: get	39
		blob: specific	39
		blob: optional	40
3 13		nal Generic Callback	40
0.10	Option	del concre cumpack	10
4 Nev	v VOL	API Routines	40
4.1	H5VL	public.h	40
	4.1.1	H5VLregister_connector	41
	4.1.2	H5VLregister_connector_by_name	41
	4.1.3	H5VLregister_connector_by_value	41
	4.1.4	H5VLis_connector_registered	41
	4.1.5	H5VLget_connector_id	42
	4.1.6	H5VLget_connector_name	42
	4.1.7	H5VLclose	42
	4.1.8	H5VLunregister_connector	42
4.2	H5VL	connector.h	43
	4.2.1	H5VLobject	43
	4.2.2	H5VLget_file_type	43
	4.2.3	H5VLpeek_connector	43
Appen	dix A	Mapping of VOL Callbacks to HDF5 API Calls	44
Annon	div B	Callback Wrapper API Calls for Passthrough Connector Authors	47

1. INTRODUCTION CONTENTS

1 Introduction

The Virtual Object Layer (VOL) is an abstraction layer in the HDF5 library which intercepts all API calls that could potentially access objects in an HDF5 container and forwards those calls to object drivers referred to as *VOL connectors*. The architecture of this feature is described in the VOL User Guide and VOL Architecture and Internals Documentation and will not be duplicated here.

This guide is for people who are interested in developing their own VOL connector for the HDF5 library. It is assumed that the reader has good knowledge of the VOL architecture obtained by reading the VOL architectural design document.

This is a preliminary version of this document. The final version will be released with the HDF5 1.12.0 release in late 2019.

2 Creating a New Connector

2.1 Overview

Creating a new VOL connector can be a complicated process. You will need to map your storage system to the HDF5 data model through the lens of the VOL and this may involve some impedence mismatch that you will have to work around. The good news is that the HDF5 library has been re-engineered to handle arbitrary, connector-specific data structures via the VOL callbacks, so no knowledge of the library internals is necessary to write a VOL connector.

Writing a VOL connector requires these things:

- 1. Decide on library vs plugin vs internal.
- 2. Set up your build/test files (CMake, Autotools, etc.).
- 3. Fill in some boilerplate information in your H5VL_class_t struct.
- 4. Decide how you will perform any necessary initialization needed by your storage system.
- 5. Map Storage to HDF5 File Objects
- 6. Create implementations for the callbacks you need to support.
- 7. Test the connector.

Each of the steps listed above is decribed in more detail in this section of the document.

The "model then implement" steps can be performed iteratively. You might begin by only supporting files, datasets, and groups and only allowing basic operations on them. In some cases, this may be all that is needed. As your needs grow, you can repeat those steps and increase the connector's HDF5 API coverage at a pace that makes sense for your users.

Also, note that this document only covers writing VOL connectors using the C programming language. It is often possible to write connectors in other programming languages (e.g.; Python) via the language's C interop facilities, but that topic is out of scope for this document.

2.2 Sources Of Information

Use of the VOL, including topics such as registration and loading VOL plugins, is described in the VOL User Guide.

Public header files you will need to be familiar with include:

H5VLpublic.h Public VOL header.

H5VLconnector.h Main connector author header. Contains definitions for the main VOL

struct and callbacks, enum values, etc.

H5VLconnector_passthru.h Helper routines for passthrough connector authors.

H5VLnative.h Native VOL connector header. May be useful if your connector will at-

tempt to implement native HDF5 API calls that are handled via the op-

tional callbacks.

H5PLextern.h Needed if your connector will be built as a plugin.

Many VOL connectors can be found on The HDF Group's Bitbucket server, located at https://bitbucket.hdfgroup.org/projects/HDF5VOL. Not all of these VOL connectors are supported by THe HDF Group and the level of completeness varies, but the connectors found there can serve as examples of working implementations.

2.3 Library vs Plugin vs Internal

When building a VOL connector, you have several options:

Library

The connector can be built as a normal shared or static library. Software that uses your connector will have to link to it just like any other library. This can be convenient since you don't have to deal with plugin paths and searching for the connector at runtime, but it also means that software which uses your connector will have to be built and linked against it.

Plugin

You can also build your connector as a dynamically loaded plugin. The mechanism for this is the same mechanism used to dynamically load HDF5 filter plugins. This can allow use of your connector via the VOL environment variable, without modifying the application, but requires your plugin to be discoverable at runtime. See the VOL User Guide for more information about using HDF5 plugins.

To build your connector as a plugin, you will have to include H5PLextern.h (a public header distributed with the library) and implement the H5PLget_plugin_type() and H5PLget_plugin_info() calls, both of which are trivial to code up. It also often requires your connector to be built with certain compile/link options. The VOL connector template does all of these things.

To show how easy this is to accomplish, here is the complete implementation of those functions in the template VOL connector:

```
H5PL_type_t H5PLget_plugin_type(void) {return H5PL_TYPE_V0L;}
const void *H5PLget_plugin_info(void) {return &template_class_g;}
```

The HDF5 library's plugin loading code will call H5PLget_plugin_type() to determine the type of plugin (e.g.; filter, VOL) and H5PLget_plugin_info() to get the class struct, which allows the library to query the plugin for its name and value to see if it has found a requested plugin. When a match is found, the library will use the class struct to register the connector and map its callbacks.

For the HDF5 library to be able to load an external plugin dynamically, the plugin developer has to define two public routines with the following name and signature:

```
H5PL_type_t H5PLget_plugin_type(void)
const void *H5PLget_plugin_info(void)
```

H5PLget_plugin_type should return the library type which should always be H5PL_TYPE_V0L. H5PLget_plugin_info should return a pointer to the plugin structure defining the VOL plugin with all the callbacks. For example, consider an external plugin defined as:

```
static const H5VL_class_t H5VL_log_g = {
1, /* version */
502, /* value */
```

```
4 "log", /* name */
5 ...
6 }
```

The plugin would implement the two routines as:

```
H5PL_type_t H5PLget_plugin_type(void) {return H5PL_TYPE_VOL;}
const void *H5PLget_plugin_info(void) {return &H5VL_log_g;}
```

Internal

Your VOL connector can also be constructed as a part of the HDF5 library. This works in the same way as the stdio and multi virtual file drivers (VFDs) and does not require knowledge of HDF5 internals or use of non-public API calls. You simply have to add your connector's files to the Makefile.am and/or CMakeLists.txt files in the source distribution's src directory. This requires maintaining a private build of the library, though, and is not recommended.

2.4 Build Files / VOL Template

We have created a template VOL connector that includes both Autotools and CMake build files. The constructed VOL connector includes no real functionality, but can be registered and loaded as a plugin.

The VOL template can be found here:

```
https://bitbucket.hdfgroup.org/projects/HDF5VOL/repos/template
```

The purpose of this template is to quickly get you to the point where you can begin filling in the callback functions and writing tests. You can copy this code to your own repository to serve as the basis for your new connector.

2.5 H5VL_class_t Boilerplate

Several fields in the H5VL_class_t struct will need to be filled in.

In HDF5 1.12.0, version will be 1, indicating version 1 of the H5VL_class_t struct.

Every connector needs a name and value. The library will use these when loading and registering the connector (as described in the VOL User Guide), so they should be unique in your ecosystem.

VOL connector values are integers, with a maximum value of 65535. Values from 0 to 255 are reserved for internal use by The HDF Group. The native VOL connector has a value of 0.

As is the case with HDF5 filters, The HDF Group can register the value you've chosen for your VOL connector so that others don't use it. Please contact help@hdfgroup.org for help with this. We currently do not register connector names.

The cap_flags field is currently not fully utilized. In the future, this will be most likely be used to indicate which callbacks and capabilities are supported by the VOL connector, but for now this struct field contains few flags, a list of which can be found in H5VLconnector.h.

2.6 Initialization and Shutdown

You'll need to decide how to perform any initialization and shutdown tasks that are required by your connector. There are initialize and terminate callbacks in the <code>H5VL_class_t</code> struct to handle this. They are invoked when the connector is registered and unregistered, respectively. If this is unsuitable, you may have to create custom connector-specific API calls to handle initialization and termination. It may also be useful to perform operations in a custom API call used to set the VOL connector in the fapl.

2.7 Map Storage to HDF5 File Objects

The most difficult part of designing a new VOL connector is going to determining how to support HDF5 file objects and operaions using your storage system. There isn't much specific advice to give here, as each connector will have unique needs, but a forthcoming "tutorial" connector will set up a simple connector and demonstrate this process.

2.8 Fill In VOL Callbacks

For each file object you support in your connector (including the file itself), you will need to create a data struct to hold whatever file object metadata that are needed by your connector. For example, a data structure for a VOL connector based on text files might have a file struct that contains a file pointer for the text file, buffers used for cacheing data, etc. Pointers to these data structures are where your connector's state is stored and are returned to the HDF5 library from the create/open/etc. callbacks such as dataset create.

Once you have your data structures, you'll need to create your own implementations of the callback functions and map them via your H5VL_class_t struct.

2.9 Testing Your Connector

At the time of writing, some of the HDF5 library tests have been abstracted out of the library with their native-file-format-only sections removed and added to a VOL test suite available here:

```
https://bitbucket.hdfgroup.org/projects/HDF5VOL/repos/vol-tests
```

This is an evolving set of tests, so see the documentation in that repository for instructions as to its use. You may want to clone and modify and/or extend these tests for use with your own connector.

In the future, we plan to modify the HDF5 test suite that ships with the library to use a future VOL capabilities flags scheme to selectively run tests that a particular connector supports. As this is a large task, it may be some time before that work is complete.

2.10 Passthrough Connectors

Coming Soon

3 VOL Connector Interface Reference

Each VOL connector should be of type H5VL_class_t, Listing 1.

```
/* Class information for each VOL driver */
   typedef struct H5VL_class_t {
2
       /* Overall connector fields & callbacks */
3
                                            /* VOL connector class struct version # */
       unsigned int version;
4
                                            /* Value to identify connector
5
       H5VL_class_value_t value;
       const char *name;
                                            /* Connector name (MUST be unique!)
                                                                                     */
6
       unsigned cap_flags;
                                            /* Capability flags for connector
                                                                                     */
       herr_t (*initialize)(hid_t vipl_id); /* Connector initialization callback
                                                                                     */
                                            /* Connector termination callback
                                                                                     */
       herr_t (*terminate)(void);
10
       /* VOL framework */
11
       H5VL_info_class_t
                                            /* VOL info fields & callbacks */
                             info_cls;
12
       H5VL_wrap_class_t
                             wrap_cls;
                                            /* VOL object wrap / retrieval callbacks */
13
14
       /* Data Model */
15
16
       H5VL_attr_class_t
                             attr_cls;
                                            /* Attribute (H5A*) class callbacks */
17
       H5VL_dataset_class_t dataset_cls;
                                           /* Dataset (H5D*) class callbacks */
       H5VL_datatype_class_t datatype_cls; /* Datatype (H5T*) class callbacks */
```

```
H5VL_file_class_t
                              file_cls;
                                             /* File (H5F*) class callbacks
19
       H5VL_group_class_t
                              group_cls;
                                             /* Group (H5G*) class callbacks */
20
       H5VL_link_class_t
                              link_cls;
                                             /* Link (H5L*) class callbacks
21
                                             /* Object (H5O*) class callbacks */
       H5VL_object_class_t
                              object_cls;
22
23
       /* Infrastructure / Services */
24
       H5VL_request_class_t request_cls;
                                             /* Asynchronous request class callbacks */
25
       H5VL_blob_class_t
                              blob_cls;
                                             /* 'blob' callbacks */
26
27
       /* Catch-all */
28
       herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments); /* Optional
29
            callback */
   } H5VL_class_t;
```

Listing 1: VOL connector class, H5VLpublic.h

The version field is the version of the H5VL_class_t struct. This is identical to how the version field is used in the H5Z_class2_t struct for filters.

The value field is a unique integer identifier that should be greater than 256 for external, non-library connectors. Setting it in the VOL structure is required.

The name field is a string that uniquely identifies the VOL connector name. Setting it in the VOL structure is required.

The cap_flags field will be used to hold bitwise capability/feature flags that can be used with a future query API call to determine which operations and capabilities are supported by a the VOL connector. This feature is currently under development.

The initialize field is a function pointer to a routine that a connector implements to set up or initialize access to the connector. Implementing this function by the connector is not required since some connectors do not require any set up to start accessing the connector. In that case, the value of the function pointer should be set to NULL. Connector specific variables that are required to be passed from users should be passed through the VOL initialize property list. Generic properties can be added to this property class for user-defined connectors that cannot modify the HDF5 library to add internal properties. For more information consult the property list reference manual pages.

The terminate field is a function pointer to a routine that a connector implements to terminate or finalize access to the connector. Implementing this function by the connector is not required since some connectors do not require any termination phase to the connector. In that case, the value of the function pointer should be set to NULL. Connector specific variables that are required to be passed from users should be passed through the VOL terminate property list. Generic properties can be added to this property class for user-defined connectors that cannot modify the HDF5 library to add internal properties. For more information consult the property list reference manual pages.

The rest of the fields in the H5VL_class_t struct are "subclasses" that define all the VOL function callbacks that are mapped to from the HDF5 API layer. Those subclasses are categorized into two categories, Data Model and Services. Data Model classes are those that provide functionality for accessing an HDF5 container and objects in that container as defined by the HDF5 data model. Service classes are those that provide services for users that are not related to the data model specifically. Asynchronous operations, for example, are a service that most connectors can implement, so we add a class for it in the VOL structure. If a service becomes generic enough and common among many connectors, a class for it should be added to the VOL structure. However, many connectors can/will provide services that are not shared by other connectors. A good way to support these services is through an optional callback in the VOL structure which can be a hook from the API to the connector that provides those services, passing any necessary arguments needed without the HDF5 library having to worry about supporting that service. A similar API operation to allow users to use that service will be added. This API call would be similar to an "ioctl" call where any kind of operation can be supported and passed down to the connector that has enough knowledge from the user to interpret the type of the operation. All classes and their defined callbacks will be detailed in the following sub-sections.

To handle that large set of API routines, each class in the Data Model category has three generic callbacks, get, specific, and optional to handle the three set of API operations outline above respectively. The callbacks will have a va_list argument to handle the different set of parameters that could be passed in. The get and specific callbacks also have an op_type that contain an enum of the type of operation that is

requested to be performed. Using that type, the va_list argument can be parsed. The optional callback is a free for all callback where anything from the API layer is passed in directly. This callback is used to support connector specific operations in the API that other connectors should or would not know about. More information about types and the arguments for each type will be detailed in the corresponding class arguments.

3.1 Mapping the API to the Callbacks

The callback interface defined for the VOL has to be general enough to handle all the HDF5 API operations that would access the file. Furthermore, it has to capture future additions to the HDF5 library with little to no changes to the callback interface. Changing the interface often whenever new features are added would be discouraging to connector developers since that would mean reworking their VOL connector structure. To remedy this issue, every callback will contain two parameters:

- A data transfer property list (DXPL) which allows that API to put some properties on for the connectors to retrieve if they have to for particular operations, without having to add arguments to the VOL callback function.
- A pointer to a request (void **req) to handle asynchronous operations if the HDF5 library adds support for them in future releases. That pointer is set by the VOL connector to a request object it creates to manage progress on that asynchronous operation. If the req is NULL, that means that the API operation is blocking and so the connector would not execute the operation asynchronously. If the connector does not support asynchronous operations, it needs not to worry about this field and leaves it unset.

In order to keep the number of the VOL object classes and callbacks concise and readable, it was decided not to have a one-to-one mapping between API operation and callbacks. The parameter names and types will be detailed when describing each callback in their respective sections.

The HDF5 library provides several routines to access an object in the container. For example, to open an attribute on a group object, the user could use H5Aopen() and pass the group identifier directly where the attribute needs to be opened. Alternatively, the user could use H5Aopen_by_name() or H5Aopen_by_idx() to open the attribute, which provides a more flexible way of locating the attribute, whether by a starting object location and a path or an index type and traversal order. All those types of accesses usually map to one VOL callback with a parameter that indicates the access type. In the example of opening an attribute, the three API open routine will map to the same VOL open callback but with a different location parameter. The same applies to all types of routines that have multiple types of accesses. The location parameter is a structure defined in Listing 2.

```
/*
    * Structure to hold parameters for object locations.
    * either: BY_SELF, BY_NAME, BY_IDX, BY_TOKEN
3
   typedef struct H5VL_loc_params_t {
       H5I_type_t obj_type; /* The object type of the location object */
       H5VL_loc_type_t type; /* The location type */
8
       union { /* parameters of the location */
9
           H5VL_loc_by_token_t
                                  loc_by_token;
10
           H5VL_loc_by_name_t
                                  loc_by_name;
11
           H5VL_loc_by_idx_t
                                  loc_by_idx;
12
       }loc_data;
13
   } H5VL_loc_params_t
14
15
16
    * Types for different ways that objects are located in an
17
    * HDF5 container.
18
19
    typedef enum H5VL_loc_type_t {
20
       /* starting location is the target object */
21
       H5VL_OBJECT_BY_SELF,
22
23
       /* location defined by object and path in <code>H5VL_loc_by_name_t */</code>
24
       H5VL_OBJECT_BY_NAME,
```

```
/* location defined by object, path, and index in H5VL_loc_by_idx_t */
27
       H5VL_OBJECT_BY_IDX,
28
29
       /* location defined by token (e.g. physical address) in H5VL_loc_by_token_t */
30
       H5VL_OBJECT_BY_TOKEN,
31
   } H5VL_loc_type_t;
32
33
   typedef struct H5VL_loc_by_name {
34
       const char *name; /* The path relative to the starting location */
35
       hid_t lapl_id; /* The link access property list */
36
   }H5VL_loc_by_name_t;
37
38
   typedef struct H5VL_loc_by_idx {
39
       const char *name; /* The path relative to the starting location */
40
       H5_index_t idx_type; /* Type of index */
41
       H5_iter_order_t order; /* Index traversal order */
42
       hsize_t n; /* Position in index */
43
       hid_t lapl_id; /* The link access property list */
44
   }H5VL_loc_by_idx_t;
45
46
   typedef struct H5VL_loc_by_token {
47
       void *token; /* arbitrary token (physical address of location in native VOL) */
48
   }H5VL_loc_by_token_t;
```

Listing 2: Structure to hold parameters for object locations, H5VLconnector.h

3.2 Connector Information Callbacks

This section's callbacks involve the connector-specific information that will be associated with the VOL in the fapl via H5Pset_fapl() et al. This data is copied into the fapl so the library needs these functions to manage this in a way that prevents resource leaks.

The to_str and from_str callbacks are used to convert the connector-specific data to and from a configuration string. There is no official way to construct VOL configuration strings, so the format used (JSON, XML, getopt-style processing, etc.) is up to the connector author. These connector configuration strings can be used to set up a VOL connector via mechanisms like command-line parameters and environment variables.

```
typedef struct H5VL_info_class_t {
    size_t size;
    void * (*copy)(const void *info);
    herr_t (*cmp)(int *cmp_value, const void *info1, const void *info2);
    herr_t (*free)(void *info);
    herr_t (*to_str)(const void *info, char **str);
    herr_t (*from_str)(const char *str, void **info);
} H5VL_info_class_t;
```

Listing 3: Info class for connector information routines, H5VLconnector.h

3.2.1 info: size

The size field indicates the size required to store any special information that the connector needs.

If the connector requires no special information, set this field to zero.

```
Signature:

size_t size;
```

3.2.2 info: copy

The copy callback is invoked when the connector is selected for use with H5Pset_fapl(), the connector-specific set call, etc. Where possible, the information should be deep copied in such a way that the original data can be freed.

Signature:

```
void * (*copy)(const void *info);

Arguments:
info (IN): The connector-specific info to copy.
```

3.2.3 info: cmp

The cmp callback is uesd to determine if two connector-specific data structs are identical and helps the library manage connector resources.

Signature:

```
herr_t (*cmp)(int *cmp_value, const void *info1, const void *info2);

Arguments:
cmp_value (OUT): A strcmp-like compare value.
info1 (IN): The 1st connector-specific info to copy.
info2 (IN): The 2nd connector-specific info to copy.
```

3.2.4 info: free

The free callback is used to clean up the connector-specific information that was copied when set in the fapl via the copy callback.

Signature:

```
herr_t (*free)(void *info);

Arguments:
info (IN): The connector-specific info to free.
```

3.2.5 info: to_str

The to_str callback converts a connector-specific information structure to a connector-specific configuration string. It is the opposite of the from_str callback.

Signature:

```
herr_t (*to_str)(const void *info, char **str);

Arguments:
info (IN): The connector-specific info to convert to a configuration string.
str (OUT): The constructed configuration string.
```

3.2.6 info: from_str

The to_str callback converts a connector-specific configuration string to a connector-specific information structure. It is the opposite of the to_str callback.

Signature:

```
herr_t (*from_str)(const char *str, void **info);
```

Arguments: str (IN): The connector-specific configuration string. info (OUT): The connector-specific info generated from the configuration string.

3.3 Object Wrap Callbacks

The object wrap callbacks are used by passthrough connectors to wrap/unwrap objects and contexts when passing them up and down the VOL chain.

```
typedef struct H5VL_wrap_class_t {
    void * (*get_object)(const void *obj);
    herr_t (*get_wrap_ctx)(const void *obj, void **wrap_ctx);
    void * (*wrap_object)(void *obj, H5I_type_t obj_type, void *wrap_ctx);
    void * (*unwrap_object)(void *obj);
    herr_t (*free_wrap_ctx)(void *wrap_ctx);
} H5VL_wrap_class_t;
```

Listing 4: Wrap class for object wrapping routines, H5VLconnector.h

3.3.1 wrap: get_object

Retrieves an underlying object.

```
Signature:
```

```
void * (*get_object)(const void *obj);
```

Arguments:

obj (IN): Object being unwrapped.

3.3.2 wrap: get_wrap_ctx

Get a VOL connector's object wrapping context.

Signature:

```
herr_t (*get_wrap_ctx)(const void *obj, void **wrap_ctx);

Arguments:
obj (IN): Object for which we need a context.
wrap_ctx (OUT): Context.
```

3.3.3 wrap: wrap_object

Asks a connector to wrap an underlying object.

Signature:

```
void * (*wrap_object)(void *obj, H5I_type_t obj_type, void *wrap_ctx);

Arguments:
obj (IN): Object being wrapped.
obj_type (IN): Object type (see H5Ipublic.h).
wrap_ctx (IN): Context.
```

3.3.4 wrap: unwrap_object

Unwrap an object from connector.

```
Signature:

void * (*unwrap_object)(void *obj);

Arguments:
obj (IN): Object being unwrapped.
```

3.3.5 wrap: free_wrap_ctx

Release a VOL connector's object wrapping context.

```
Signature:
```

```
herr_t (*free_wrap_ctx)(void *wrap_ctx);

Arguments:
wrap_ctx (IN): Context to be freed.
```

3.4 The Attribute Function Callbacks

The attribute API routines (H5A) allow HDF5 users to create and manage HDF5 attributes. All the H5A API routines that modify the HDF5 container map to one of the attribute callback routines in this class that the connector needs to implement.

```
typedef struct H5VL_attr_class_t {
       void *(*create)(void *obj, const H5VL_loc_params_t *loc_params, const char *attr_name, hid_t
           type_id, hid_t space_id, hid_t acpl_id, hid_t aapl_id, hid_t dxpl_id, void **req);
       void *(*open)(void *obj, const H5VL_loc_params_t *loc_params, const char *attr_name, hid_t
           aapl_id, hid_t dxpl_id, void **req);
      herr_t (*read)(void *attr, hid_t mem_type_id, void *buf, hid_t dxpl_id, void **req);
      herr_t (*write)(void *attr, hid_t mem_type_id, const void *buf, hid_t dxpl_id, void **req);
       herr_t (*get)(void *obj, H5VL_attr_get_t get_type, hid_t dxpl_id, void **req, va_list
6
           arguments);
       herr_t (*specific)(void *obj, const H5VL_loc_params_t *loc_params, H5VL_attr_specific_t
           specific_type, hid_t dxpl_id, void **req, va_list arguments);
       herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);
       herr_t (*close) (void *attr, hid_t dxpl_id, void **req);
   } H5VL_attr_class_t;
10
```

Listing 5: Structure for attribute callback routines, H5VLconnector.h

3.4.1 attr: create

The create callback in the attribute class creates an attribute object in the container of the location object and returns a pointer to the attribute structure containing information to access the attribute in future calls.

```
Signature:

void *(*create)(void *obj, H5VL_loc_params_t *loc_params,

const char *attr_name, hid_t type_id, hid_t space_id,

hid_t acpl_id, hid_t aapl_id,

hid_t dxpl_id, void **req);

Arguments:
```

obj	(IN): Pointer to an object where the attribute needs to be created or where the look-up
	of the target object needs to start.
loc_params	(IN): Pointer to the location parameters as explained in Section 3.1.
$attr_name$	(IN): The name of the attribute to be created.
${ t type_id}$	(IN): The datatype of the attribute.
${ t space_id}$	(IN): The dataspace of the attribute.
$acpl_id$	(IN): The attribute creation property list.
$aapl_id$	(IN): The attribute access property list.
$\mathtt{dxpl_id}$	(IN): The data transfer property list.
req	(IN/OUT): A pointer to the asynchronous request of the operation created by the con-
	nector.

3.4.2 attr: open

The open callback in the attribute class opens an attribute object in the container of the location object and returns a pointer to the attribute structure containing information to access the attribute in future calls.

```
Signature:
   void *(*open)(void *obj, H5VL_loc_params_t *loc_params,
       const char *attr_name, hid_t aapl_id, hid_t dxpl_id, void **req);
Arguments:
               (IN): Pointer to an object where the attribute needs to be opened or where the look-up
 obj
               of the target object needs to start.
               (IN): Pointer to the location parameters as explained in Section 3.1.
 loc_params
 \verb|attr_name|
               (IN): The name of the attribute to be opened.
 aapl_id
               (IN): The attribute access property list.
 dxpl_id
               (IN): The data transfer property list.
               (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
               nector.
```

3.4.3 attr: read

The read callback in the attribute class reads data from the attribute object and returns an herr_t indicating success or failure.

3.4.4 attr: write

The write callback in the attribute class writes data to the attribute object and returns an herr_t indicating success or failure.

3.4.5 attr: get

The get callback in the attribute class retrieves information about the attribute as specified in the get_type parameter. It returns an herr_t indicating success or failure.

```
Signature:
      herr_t (*get)(void *obj, H5VL_attr_get_t get_type, hid_t dxpl_id,
          void **req, va_list arguments);
  The get_type argument is an enum:
  /* types for attribute GET callback */
  typedef enum H5VL_attr_get_t {
2
      H5VL_ATTR_GET_ACPL,
                                            /* creation property list
3
                                                                                 */
      H5VL_ATTR_GET_INFO,
                                            /* info
4
      H5VL_ATTR_GET_NAME,
                                            /* access property list
                                                                                 */
5
      H5VL_ATTR_GET_SPACE,
                                            /* dataspace
                                                                                 */
6
      H5VL_ATTR_GET_STORAGE_SIZE,
                                            /* storage size
      H5VL_ATTR_GET_TYPE
                                            /* datatype
                                                                                 */
  } H5VL_attr_get_t;
   Arguments:
                 (IN): An attribute or location object where information needs to be retrieved from.
    obj
                 (IN): The type of the information to retrieve.
    get_type
    dxpl_id
                 (IN): The data transfer property list.
                 (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
    req
                 nector.
    arguments
                 (IN/OUT): argument list containing parameters and output pointers for the get opera-
```

The arguments argument contains a variable list of arguments depending on the get_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_ATTR_GET_ACPL, to retrieve the attribute creation property list of the attribute specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the attribute creation property list.
- H5VL_ATTR_GET_INFO, to retrieve the attribute info:
 - 1. H5VL_loc_params_t *loc_params (IN): Pointer to the location parameters explained in Section 3.1.
 - 2. H5A_info_t *ainfo (OUT): info structure to fill the attribute info in.
- H5VL_ATTR_GET_NAME, to retrieve an attribute name on a particular object specified in obj:
 - 1. H5VL_loc_params_t *loc_params (IN): Pointer to the location parameters explained in Section 3.1. The type could be either H5VL_OBJECT_BY_SELF meaning obj is the attribute, or H5VL_OBJECT_BY_IDX meaning the attribute to retrieve the name for should be looked up using the index information on the object in obj and the index information in loc_params.

- 2. size_t buf_size (IN): the size of the buffer to store the name in.
- 3. void *buf (OUT): Buffer to store the name in.
- 4. ssize_t *ret_val (OUT): return the actual size needed to store the fill attribute name.
- H5VL_ATTR_GET_SPACE, to retrieve the dataspace of the attribute specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the attribute dataspace.
- H5VL_ATTR_GET_STORAGE_SIZE, to retrieve the storage size of the attribute specified in obj:
 - 1. hsize_t *ret (OUT): buffer for the storage size of the attribute in the container.
- H5VL_ATTR_GET_TYPE, to retrieve the datatype of the attribute specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the attribute datatype.

3.4.6 attr: specific

The specific callback in the attribute class implements specific operations on HDF5 attributes as specified in the specific_type parameter. It returns an herr_t indicating success or failure.

```
Signature:
          herr_t (*specific)(void *obj, H5VL_loc_params_t *loc_params, H5VL_attr_specific_t
              specific_type, hid_t dxpl_id, void **req, va_list arguments);
  The specific_type argument is an enum:
  /* types for attribute SPECFIC callback */
  typedef enum H5VL_attr_specific_t {
      H5VL_ATTR_DELETE,
                                            /* H5Adelete(_by_name/idx)
                                                                                */
3
      H5VL_ATTR_EXISTS,
                                            /* H5Aexists(_by_name)
                                                                                */
4
      H5VL_ATTR_ITER,
                                            /* H5Aiterate(_by_name)
                                                                                */
5
      H5VL_ATTR_RENAME
                                            /* H5Arename(_by_name)
                                                                                */
6
  } H5VL_attr_specific_t;
  Arguments:
                     (IN): The location object where the operation needs to happen.
    obj
    loc_params
                     (IN): A pointer to the location parameters as explained in Section 3.1.
                     (IN): The type of the operation.
    specific_type
                     (IN): The data transfer property list.
    dxpl_id
                     (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
    req
    arguments
                     (IN/OUT): argument list containing parameters and output pointers for the get opera-
                     tion.
```

The arguments argument contains a variable list of arguments depending on the specific_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_ATTR_DELETE, to delete an attribute on an object:
 - 1. char *attr_name (IN): the name of the attribute to delete.
- H5VL_ATTR_EXISTS, to check if an attribute exists on a particular object specified in obj:
 - 1. char *attr_name (IN): the attribute name to check.
 - 2. htri_t *ret (OUT): existence result, 0 if false, 1 if true.
- H5VL_ATTR_ITER, to iterate over all attributes of an object and call a user-specified callback on each one:
 - 1. H5_index_t idx_type (IN): Type of index.

- 2. H5_iter_order_t order (IN): Order in which to iterate over index.
- 3. hsize_t *idx (IN/OUT): Initial and return offset within index.
- 4. H5A_operator2_t op (IN): User-defined function to pass each attribute to.
- 5. void *op_data (IN/OUT): User data to pass through to and to be returned by iterator operator function.
- H5VL_ATTR_RENAME, to rename an attribute on an object:
 - 1. char *old_name (IN): the original name of the attribute.
 - 2. char *new_name (IN): the new name to assign for the attribute.

3.4.7 attr: optional

The optional callback in the attribute class implements connector specific operations on an HDF5 attribute. It returns an herr_t indicating success or failure.

```
herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);

Arguments:
obj (IN): The container or object where the operation needs to happen.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each connector should be able to parse the va_list arguments if it has connector specific operations to implement and determine the type of the operation and the parameters through a predefined schema.

3.4.8 attr: close

The close callback in the attribute class terminates access to the attribute object and free all resources it was consuming, and returns an herr_t indicating success or failure.

```
Arguments:

attr (IN): Pointer to the attribute object.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
```

3.5 Dataset Callbacks

The dataset API routines (H5D) allow HDF5 users to create and manage HDF5 datasets. All the H5D API routines that modify the HDF5 container map to one of the dataset callback routines in this class that the connector needs to implement.

```
typedef struct H5VL_dataset_class_t {
       void *(*create)(void *obj, const H5VL_loc_params_t *loc_params, const char *name, hid_t
           lcpl_id, hid_t type_id, hid_t space_id, hid_t dcpl_id, hid_t dapl_id, hid_t dxpl_id, void
       void *(*open)(void *obj, const H5VL_loc_params_t *loc_params, const char *name, hid_t dapl_id,
           hid_t dxpl_id, void **req);
       herr_t (*read)(void *dset, hid_t mem_type_id, hid_t mem_space_id, hid_t file_space_id, hid_t
           dxpl_id, void * buf, void **req);
       herr_t (*write)(void *dset, hid_t mem_type_id, hid_t mem_space_id, hid_t file_space_id, hid_t
           dxpl_id, const void * buf, void **req);
       herr_t (*get)(void *obj, H5VL_dataset_get_t get_type, hid_t dxpl_id, void **req, va_list
           arguments);
       herr_t (*specific)(void *obj, H5VL_dataset_specific_t specific_type, hid_t dxpl_id, void
           **req, va_list arguments);
       herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);
       herr_t (*close) (void *dset, hid_t dxpl_id, void **req);
   } H5VL_dataset_class_t;
10
```

Listing 6: Structure for dataset callback routines, H5VLconnector.h

3.5.1 dataset: create

The create callback in the dataset class creates a dataset object in the container of the location object and returns a pointer to the dataset structure containing information to access the dataset in future calls.

```
Signature:
   void *(*create)(void *obj, H5VL_loc_params_t *loc_params, const char *name, hid_t lcpl_id,
        hid_t type_id, hid_t space_id, hid_t dcpl_id, hid_t dapl_id, hid_t dxpl_id, void **req);
Arguments:
               (IN): Pointer to an object where the dataset needs to be created or where the look-up of
 obj
               the target object needs to start.
               (IN): Pointer to the location parameters as explained in Section 3.1. The type can be
 loc_params
               only H5VL_OBJECT_BY_SELF in this callback.
               (IN): The name of the dataset to be created.
 name
               (IN): The link creation property list.
 lcpl_id
               (IN): The datatype of the dataset.
 type_id
               (IN): The dataspace of the dataset.
 space_id
 dcpl_id
               (IN): The dataset creation property list.
 dapl_id
               (IN): The dataset access property list.
 dxpl_id
               (IN): The data transfer property list.
               (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
               nector.
```

3.5.2 dataset: open

The open callback in the dataset class opens a dataset object in the container of the location object and returns a pointer to the dataset structure containing information to access the dataset in future calls.

```
Signature:

void *(*open)(void *obj, H5VL_loc_params_t *loc_params, const char *name, hid_t dapl_id, hid_t dxpl_id, void **req);

Arguments:
```

eds to be opened or where the look-up of
plained in Section 3.1. The type can be
uest of the operation created by the con-

3.5.3 dataset: read

The read callback in the dataset class reads data from the dataset object and returns an herr_t indicating success or failure.

```
Signature:
   herr_t (*read)(void *dset, hid_t mem_type_id, hid_t mem_space_id,
       hid_t file_space_id, hid_t dxpl_id, void *buf, void **req);
Arguments:
 dset
                  (IN): Pointer to the dataset object.
                  (IN): The memory datatype of the data.
 mem_type_id
                  (IN): The memory dataspace selection.
 mem_space_id
                  (IN): The file dataspace selection.
 file_space_id
                  (IN): The data transfer property list.
 dxpl_id
 buf
                  (OUT): Data buffer to be read into.
                  (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
                  nector.
```

3.5.4 dataset: write

The write callback in the dataset class writes data to the dataset object and returns an herr_t indicating success or failure.

```
Signature:
   herr_t (*write)(void *dset, hid_t mem_type_id, hid_t mem_space_id,
       hid_t file_space_id, hid_t dxpl_id, const void *buf, void **req);
Arguments:
                  (IN): Pointer to the dataset object.
 dset
 mem_type_id
                  (IN): The memory datatype of the data.
 mem_space_id
                  (IN): The memory dataspace selection.
                  (IN): The file dataspace selection.
 file_space_id
 dxpl_id
                  (IN): The data transfer property list.
                  (IN): Data buffer to be written from.
 buf
                  (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
                  nector.
```

3.5.5 dataset: get

The get callback in the dataset class retrieves information about the dataset as specified in the get_type parameter.It returns an herr_t indicating success or failure.

```
Signature:

herr_t (*get)(void *dset, H5VL_dataset_get_t get_type,
```

```
hid_t dxpl_id, void **req, va_list arguments);
   The get_type argument is an enum:
   /* types for dataset GET callback */
   typedef enum H5VL_dataset_get_t {
       H5VL_DATASET_GET_DAPL,
                                            /* access property list
                                                                                 */
3
       H5VL_DATASET_GET_DCPL,
                                            /* creation property list
                                                                                 */
4
       H5VL_DATASET_GET_OFFSET,
                                            /* offset
                                                                                 */
5
       H5VL_DATASET_GET_SPACE,
                                            /* dataspace
                                                                                 */
6
       H5VL_DATASET_GET_SPACE_STATUS,
                                            /* space status
                                                                                 */
       H5VL_DATASET_GET_STORAGE_SIZE,
                                            /* storage size
                                                                                 */
       H5VL_DATASET_GET_TYPE
                                            /* datatype
                                                                                 */
9
  } H5VL_dataset_get_t;
10
   Arguments:
                 (IN): The dataset object where information needs to be retrieved from.
    dset
                 (IN): The type of the information to retrieve.
    get_type
    dxpl_id
                 (IN): The data transfer property list.
                 (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
    req
                 nector.
                 (IN/OUT): argument list containing parameters and output pointers for the get opera-
    arguments
```

The arguments argument contains a variable list of arguments depending on the get_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_DATASET_GET_DAPL, to retrieve the dataset access property list of the dataset specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the dataset access property list.
- H5VL_DATASET_GET_DCPL, to retrieve the dataset creation property list of the dataset specified in obj:
 - hid_t *ret_id (OUT): buffer for the identifier of the dataset creation property list.
- H5VL_DATASET_GET_OFFSET, to retrieve the offset of the dataset specified in obj in the container:
 - 1. haddr_t *ret (OUT): buffer for the offset of the dataset in the container.
- H5VL_DATASET_GET_SPACE, to retrieve the dataspace of the dataset specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the dataset dataspace.
- H5VL_DATASET_GET_SPACE_STATUS, to retrieve the information whether space has been allocated for the dataset:
 - 1. H5D_space_status_t *allocation (OUT): buffer for the space status.
- H5VL_DATASET_GET_STORAGE_SIZE, to retrieve the storage size of the dataset specified in obj:
 - 1. hsize_t *ret (OUT): buffer for the storage size of the dataset in the container.
- H5VL_DATASET_GET_TYPE, to retrieve the datasype of the dataset specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the dataset datatype.

3.5.6 dataset: specific

The specific callback in the dataset class implements specific operations on HDF5 datasets as specified in the specific_type parameter. It returns an herr_t indicating success or failure.

```
Signature:

herr_t (*specific)(void *obj, H5VL_file_specific_t specific_type, hid_t dxpl_id, void **req, va_list arguments);
```

```
The specific_type argument is an enum:
  /* types for dataset SPECFIC callback */
1
  typedef enum H5VL_dataset_specific_t {
2
      H5VL_DATASET_SET_EXTENT,
                                            /* H5Dset_extent
                                                                                 */
3
      H5VL_DATASET_FLUSH,
                                            /* H5Dflush
                                                                                 */
      H5VL_DATASET_REFRESH
                                            /* H5Drefresh
5
  } H5VL_dataset_specific_t;
   Arguments:
                      (IN): The dset where the operation needs to happen.
    obj
                     (IN): The type of the operation.
    specific_type
                      (IN): The data transfer property list.
    dxpl_id
                     (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
    req
                     nector.
                     (IN/OUT): argument list containing parameters and output pointers for the get opera-
    arguments
                      tion.
```

The arguments argument contains a variable list of arguments depending on the specific_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_DATASET_SET_EXTENT, changes the extent of the dataset dimensions:
 - 1. hsize_t size (IN): Array containing the new magnitude of each dimension of the dataset.
- H5VL_DATASET_FLUSH, flushes a dataset:
 - 1. hid_t dset_id (IN): The dataset ID. Needed so that the refreshed data can be associated with the old ID.
- H5VL_DATASET_REFRESH, clears a dataset's buffers and reloads from disk:
 - 1. hid_t dset_id (IN): The dataset ID. Needed so that the refreshed data can be associated with the old ID.

3.5.7 dataset: optional

The optional callback in the dataset class implements connector specific operations on an HDF5 dataset. It returns an herr_t indicating success or failure.

```
herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);

Arguments:
obj (IN): The container or object where the operation needs to happen.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each connector should be able to parse the valist arguments if it has connector specific operations to implement and determine the type of the operation and the parameters through a predefined schema.

3.5.8 dataset: close

The close callback in the dataset class terminates access to the dataset object and free all resources it was consuming and returns an herr_t indicating success or failure.

```
Arguments:

dset (IN): Pointer to the dataset object.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
```

3.6 Datatype Callbacks

The HDF5 datatype routines (H5T) allow users to create and manage HDF5 datatypes. Those routines are divided into two categories. One that operates on all types of datatypes but do not modify the contents of the container (all in memory), and others that operate on named datatypes by accessing the container. When a user creates an HDF5 datatype, it is still an object in memory space (transient datatype) that has not been added to the HDF5 containers. Only when a user commits the HDF5 datatype, it becomes persistent in the container. Those are called named/committed datatypes. The transient H5T routines should work on named datatypes nevertheless.

All the H5T API routines that modify the HDF5 container map to one of the named datatype callback routines in this class that the connector needs to implement.

Listing 7: Structure for datatype callback routines, H5VLconnector.h

3.6.1 datatype: commit

The commit callback in the named datatype class creates a datatype object in the container of the location object and returns a pointer to the datatype structure containing information to access the datatype in future calls.

```
Signature:

void *(*commit)(void *obj, H5VL_loc_params_t *loc_params,

const char *name, hid_t type_id, hid_t lcpl_id, hid_t tcpl_id,

hid_t tapl_id, hid_t dxpl_id, void **req);

Arguments:
```

obj	(IN): Pointer to an object where the datatype needs to be committed or where the look-up
	of the target object needs to start.
loc_params	(IN): Pointer to location parameters as explained in Section 3.1. In this call, the location
	type is always H5VL_OBJECT_BY_SELF.
name	(IN): The name of the datatype to be created.
$type_id$	(IN): The transient datatype identifier to be committed.
$lcpl_id$	(IN): The link creation property list.
$tcpl_id$	(IN): The datatype creation property list.
$tapl_id$	(IN): The datatype access property list.
$dxpl_id$	(IN): The data transfer property list.
req	(IN/OUT): A pointer to the asynchronous request of the operation created by the con-
	nector.

3.6.2 datatype: open

The open callback in the named datatype class opens a previously committed datatype object in the container of the location object and returns a pointer to the datatype structure containing information to access the datatype in future calls.

```
Signature:
   void *(*open) (void *obj, H5VL_loc_params_t *loc_params,
       const char * name, hid_t tapl_id, hid_t dxpl_id, void **req);
Arguments:
 obj
               (IN): Pointer to an object where the datatype needs to be opened or where the look-up
               of the target object needs to start.
               (IN): Pointer to location parameters as explained in Section 3.1. In this call, the location
 loc_params
               type is always H5VL_OBJECT_BY_SELF.
               (IN): The name of the datatype to be opened.
 tapl_id
               (IN): The datatype access property list.
 dxpl_id
               (IN): The data transfer property list.
               (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
               nector.
```

3.6.3 datatype: get

The get callback in the named datatype class retrieves information about the named datatype as specified in the get_type parameter.It returns an herr_t indicating success or failure.

```
obj (IN): The named datatype to retrieve information from.

get_type (IN): The type of the information to retrieve.

dxpl_id (IN): The data transfer property list.

req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.

arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

The arguments argument contains a variable list of arguments depending on the get_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_DATATYPE_GET_BINARY, to retrieve the serialized original transient HDF5 datatype that was committed, or return the size that is required for it be serialized if the passed in buffer is NULL. The HDF5 library provides two functions to encode and decode datatypes in their transient form, H5Tencode() and H5Tdecode(). When a datatype is committed, the connector is required to keep the serialized form of the transient datatype stored somewhere in the container (which is usually the case anyway when committing a named datatype), so it can be retrieved with this call. This is needed to generate the higher level HDF5 datatype identifier that allows all the H5T "transient" routines to work properly on the named datatype.
 - 1. ssize_t *nalloc (OUT): buffer to store the total size of the serialized datatype.
 - 2. void *buf (OUT): buffer to store the serialized datatype.
 - 3. size_t size (IN): size of the passed in buffer.
- H5VL_DATATYPE_GET_TCPL, to retrieve the datatype creation property list:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the type creation property list.

3.6.4 datatype: specific

The specific callback in the datatype class implements specific operations on HDF5 named datatypes as specified in the specific_type parameter. It returns an herr_t indicating success or failure.

```
Signature:
       herr_t (*specific)(void *obj, H5VL_loc_params_t *loc_params, H5VL_object_specific_t
            specific_type, hid_t dxpl_id, void **req, va_list arguments);
The specific_type argument is an enum:
/* types for datatype SPECFIC callback */
typedef enum H5VL_datatype_specific_t {
   H5VL_DATATYPE_FLUSH,
   H5VL_DATATYPE_REFRESH
} H5VL_datatype_specific_t;
Arguments:
                  (IN): The container or object where the operation needs to happen.
 obj
 loc_params
                  (IN): Pointer to location parameters as explained in Section 3.1.
 specific_type
                  (IN): The type of the operation.
                  (IN): The data transfer property list.
 dxpl_id
                  (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
                  nector.
 arguments
                  (IN/OUT): argument list containing parameters and output pointers for the get opera-
```

The arguments argument contains a variable list of arguments depending on the specific_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_DATATYPE_FLUSH, flushes a datatype:
 - 1. hid_t type_id (IN): The datatype ID. Needed so that the refreshed data can be associated with the old ID.

- H5VL_DATATYPE_REFRESH, clears a datatype's buffers and reloads from disk:
 - 1. hid_t type_id (IN): The datatype ID. Needed so that the refreshed data can be associated with the old ID.

3.6.5 datatype: optional

The optional callback in the datatype class implements connector specific operations on an HDF5 datatype. It returns an herr_t indicating success or failure.

```
herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);

Arguments:
obj (IN): The container or object where the operation needs to happen.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each connector should be able to parse the valist arguments if it has connector specific operations to implement and determine the type of the operation and the parameters through a predefined schema.

3.6.6 datatype: close

The close callback in the named datatype class terminates access to the datatype object and free all resources it was consuming and returns an herr_t indicating success or failure.

```
Signature:

herr_t (*close) (void *dt, hid_t dxpl_id, void **req);

Arguments:
dt (IN): Pointer to the datatype object.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
```

3.7 File Callbacks

The file API routines (H5F) allow HDF5 users to create and manage HDF5 containers. All the H5F API routines that modify the HDF5 container map to one of the file callback routines in this class that the connector needs to implement.

Listing 8: File class for file API routines, H5VLconnector.h

3.7.1 file: create

The create callback in the file class should create a container and returns a pointer to the file structure created by the connector containing information to access the container in future calls.

```
Signature:
   void *(*create)(const char *name, unsigned flags, hid_t fcpl_id, hid_t fapl_id, hid_t
        dxpl_id, void **req);
Arguments:
           (IN): The name of the container to be created.
 name
 flags
           (IN): The creation flags of the container.
 fcpl_id
           (IN): The file creation property list.
 fapl_id
           (IN): The file access property list.
           (IN): The data transfer property list.
 dxpl_id
           (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
           nector.
```

3.7.2 file: open

The open callback in the file class should open a container and returns a pointer to the file structure created by the connector containing information to access the container in future calls.

```
Signature:

void *(*open)(const char *name, unsigned flags, hid_t fapl_id, hid_t dxpl_id, void **req);

Arguments:

name (IN): The name of the container to open.

flags (IN): The open flags of the container.

fapl_id (IN): The file access property list.

dxpl_id (IN): The data transfer property list.

req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
```

3.7.3 file: get

The get callback in the file class should retrieve information about the container as specified in the get_type parameter. It returns an herr_t indicating success or failure.

```
Signature:
      herr_t (*get)(void *obj, H5VL_file_get_t get_type, hid_t dxpl_id,
          void **req, va_list arguments);
  The get_type argument is an enum:
  /* types for all file get API routines */
  typedef enum H5VL_file_get_t {
2
      H5VL_FILE_GET_CONT_INFO,
                                          /* file get container info
3
      H5VL_FILE_GET_FAPL,
                                          /* file access property list
4
      H5VL_FILE_GET_FCPL,
                                          /* file creation property list
5
      H5VL_FILE_GET_FILENO,
                                          /* file number
6
      H5VL_FILE_GET_INTENT,
                                          /* file intent
      H5VL_FILE_GET_NAME,
                                          /* file name
                                          /* object count in file
      H5VL_FILE_GET_OBJ_COUNT,
```

```
H5VL_file_get_t;

Arguments:
obj (IN): The container or object where information needs to be retrieved from.
get_type (IN): The type of the information to retrieve.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.

The arguments argument contains a variable list of arguments depending on the get type parameters.
```

The arguments argument contains a variable list of arguments depending on the get_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_OBJECT_GET_CONT_INFO, get information about the container that the object belongs to:
 - 1. H5VL_file_cont_info_t *info (OUT): pointer to the file container info structure returned.
- H5VL_FILE_GET_FAPL, to retrieve the file access property list:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the file access property list.
- H5VL_FILE_GET_FCPL, to retrieve the file creation property list:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the file creation property list.
- H5VL_FILE_GET_FILENO, to retrieve the file's file number:
 - 1. unsigned long *fileno (OUT): buffer for the file number.
- H5VL_FILE_GET_INTENT, get access intent of the container:
 - 1. unsigned *intent_flags (OUT): buffer for the intent flags value.
- H5VL_FILE_GET_NAME, get container name an object belongs to:
 - 1. H5I_type_t type (IN): the object type in obj.
 - 2. size_t size (IN): size of the buffer for the file name.
 - 3. char *name (OUT): buffer for the file name.
 - 4. ssize_t *ret (OUT): buffer for the entire size of the file name.
- H5VL_FILE_GET_OBJ_COUNT:, to retrieve the object count in the container:
 - 1. unsigned types (IN): type of objects to look for.
 - 2. ssize_t *ret (OUT): buffer for the object count.
- H5VL_FILE_GET_OBJ_IDS:, to retrieve object identifiers in the container:
 - 1. unsigned types (IN): type of objects to look for.
 - 2. size_t max_objs (IN): maximum number of objects to open.
 - 3. hid_t *oid_list (OUT): buffer for the object identifiers.
 - 4. ssize_t *ret (OUT): buffer for the object count.

3.7.4 file: specific

The specific callback in the file class implements specific operations on HDF5 files as specified in the specific_type parameter. It returns an herr_t indicating success or failure.

```
Signature:

herr_t (*specific)(void *obj, H5VL_file_specific_t specific_type, hid_t dxpl_id, void **req, va_list arguments);
```

The specific_type argument is an enum:

```
/* types for file SPECIFIC callback */
1
   typedef enum H5VL_file_specific_t {
2
       H5VL_FILE_POST_OPEN,
                                            /* Adjust file after open, with wrapping context */
3
       H5VL_FILE_FLUSH,
                                            /* Flush file
                                                                             */
       H5VL_FILE_REOPEN,
                                            /* Reopen the file
                                                                             */
5
       H5VL_FILE_MOUNT,
                                            /* Mount a file
                                                                             */
6
                                            /* Unmount a file
       H5VL_FILE_UNMOUNT,
                                                                             */
                                            /* Check if a file is accessible */
       H5VL_FILE_IS_ACCESSIBLE,
                                            /* Delete a file
       H5VL_FILE_DELETE,
       H5VL_FILE_IS_EQUAL
                                            /* Check if two files are the same */
10
   } H5VL_file_specific_t;
11
```

Arguments:

obj (IN): The container or object where the operation needs to happen.

specific_type (IN): The type of the operation.

dxpl_id (IN): The data transfer property list.

req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.

arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.

The arguments argument contains a variable list of arguments depending on the specific_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_FILE_POST_OPEN, adjust a file after opening it:
- H5VL_FILE_FLUSH, flushes all buffers associated with the container to disk:
 - 1. H5I_type_t obj_type (IN): The object type of obj on which the flush operation was called.
 - 2. H5F_scope_t scope (IN): The scope of the flushing action.
- H5VL_FILE_REOPEN, reopens a file:
 - 1. void *file (IN): pointer to the reopened file (same type of pointer as is returned from the connector's create/open callbacks).
- H5VL_FILE_MOUNT, Mounts a file on the location object:
 - 1. H5I_type_t type (IN): the object type in obj.
 - 2. char *name (IN): name of the group onto which the file specified by file is to be mounted.
 - 3. void *child (IN): child file to be mounted (same type of pointer as is returned from the connector's create/open callbacks).
 - 4. hid_t *fmpl_id (IN): file mount property list.
- H5VL_FILE_UNMOUNT, un-mounts a file from the location object:
 - 1. H5I_type_t type (IN): the object type in obj.
 - 2. char *name (IN): name of the mount point.
- H5VL_FILE_IS_ACCESSIBLE, checks if a container is accessible using a specific file access property list:
 - 1. hid_t *fapl_id (IN): file access property list.
 - 2. char *name (IN): name of the container to check.
 - 3. htri_t *result (OUT): buffer for the result; 0 if no, 1 if yes.
- H5VL_FILE_DELETE, deletes a file:
 - 1. H5I_type_t obj_type (IN): The object type of obj on which the flush operation was called.
 - 2. H5F_scope_t scope (IN): The scope of the flushing action.
- H5VL_FILE_IS_EQUAL, check if one file is equal to another:

- 1. H5I_type_t obj_type (IN): The object type of obj on which the flush operation was called.
- 2. H5F_scope_t scope (IN): The scope of the flushing action.

3.7.5 file: optional

The optional callback in the file class implements connector specific operations on an HDF5 container. It returns an herr_t indicating success or failure.

```
herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);

Arguments:
obj (IN): The container or object where the operation needs to happen.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each connector should be able to parse the va_list arguments if it has connector specific operations to implement and determine the type of the operation and the parameters through a predefined schema.

3.7.6 file: close

The close callback in the file class should terminate access to the file object and free all resources it was consuming, and returns an herr_t indicating success or failure.

```
Arguments:
file (IN): Pointer to the file.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
```

3.8 Group Callbacks

The group API routines (H5G) allow HDF5 users to create and manage HDF5 groups. All the H5G API routines that modify the HDF5 container map to one of the group callback routines in this class that the connector needs to implement.

Listing 9: Structure for group callback routines, H5VLconnector.h

3.8.1 group: create

The create callback in the group class creates a group object in the container of the location object and returns a pointer to the group structure containing information to access the group in future calls.

```
Signature:
    void *(*create)(void *obj, H5VL_loc_params_t *loc_params, const char *name, hid_t gcpl_id,
        hid_t gapl_id, hid_t dxpl_id, void **req);
Arguments:
               (IN): Pointer to an object where the group needs to be created or where the look-up of
 obj
               the target object needs to start.
               (IN): Pointer to the location parameters as explained in Section 3.1. The type can be
 loc_params
               only H5VL_OBJECT_BY_SELF in this callback.
               (IN): The name of the group to be created.
 name
               (IN): The group creation property list. It contains all the group creation properties in
 dcpl_id
               addition to the link creation property list of the create operation (an hid_t) that can be
               retrieved with the property H5VL_GRP_LCPL_ID.
 gapl_id
               (IN): The group access property list.
               (IN): The data transfer property list.
 dxpl_id
               (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
```

3.8.2 group: open

The open callback in the group class opens a group object in the container of the location object and returns a pointer to the group structure containing information to access the group in future calls.

```
Signature:
   void *(*open)(void *obj, H5VL_loc_params_t *loc_params,
       const char*name, hid_t gapl_id, hid_t dxpl_id, void **req);
Arguments:
               (IN): Pointer to an object where the group needs to be opened or where the look-up of
 obj
               the target object needs to start.
               (IN): Pointer to the location parameters as explained in Section 3.1. The type can be
 loc_params
               only H5VL_OBJECT_BY_SELF in this callback.
 name
               (IN): The name of the group to be opened.
               (IN): The group access property list.
 dapl_id
               (IN): The data transfer property list.
 dxpl_id
 req
               (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
               nector.
```

3.8.3 group: get

The get callback in the group class retrieves information about the group as specified in the get_type parameter. It returns an herr_t indicating success or failure.

```
Signature:

herr_t (*get)(void *obj, H5VL_group_get_t get_type, hid_t dxpl_id, void **req, va_list arguments);

The get_type argument is an enum:

/* types for all group get API routines */
```

```
typedef enum H5VL_group_get_t {
   H5VL_GROUP_GET_GCPL,
                                         /* group creation property list */
   H5VL_GROUP_GET_INFO
                                         /* group info
} H5VL_group_get_t;
Arguments:
              (IN): The group object where information needs to be retrieved from.
 obj
              (IN): The type of the information to retrieve.
 get_type
              (IN): The data transfer property list.
 dxpl_id
              (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
              nector.
              (IN/OUT): argument list containing parameters and output pointers for the get opera-
 arguments
              tion.
```

The arguments argument contains a variable list of arguments depending on the get_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_GROUP_GET_GCPL, to retrieve the group creation property list of the group specified in obj:
 - 1. hid_t *ret_id (OUT): buffer for the identifier of the group creation property list.
- H5VL_GROUP_GET_INFO, to retrieve the attribute info:
 - 1. H5VL_loc_params_t *loc_params (IN): Pointer to the location parameters explained in Section 3.1.
 - 2. H5G_info_t *group_info (OUT): info structure to fill the group info in.

3.8.4 group: specific

The specific callback in the group class implements specific operations on HDF5 groups as specified in the specific_type parameter. It returns an herr_t indicating success or failure.

```
Signature:
       herr_t (*specific)(void *obj, H5VL_loc_params_t *loc_params, H5VL_object_specific_t
            specific_type, hid_t dxpl_id, void **req, va_list arguments);
The specific_type argument is an enum:
/* types for group SPECFIC callback */
typedef enum H5VL_group_specific_t {
   H5VL_GROUP_FLUSH,
    H5VL_GROUP_REFRESH
} H5VL_group_specific_t;
Arguments:
                   (IN): The container or object where the operation needs to happen.
 obj
 loc_params
                   (IN): Pointer to the location parameters as explained in Section 3.1.
 specific_type
                  (IN): The type of the operation.
                   (IN): The data transfer property list.
 dxpl_id
                   (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
                  nector.
 arguments
                   (IN/OUT): argument list containing parameters and output pointers for the get opera-
                  tion.
```

The arguments argument contains a variable list of arguments depending on the specific_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_GROUP_FLUSH, flushes a group:
 - 1. hid_t grp_id (IN): The group ID. Needed so that the refreshed data can be associated with the old ID.
- H5VL_GROUP_REFRESH, clears a group's buffers and reloads from disk:

1. hid_t grp_id (IN): The group ID. Needed so that the refreshed data can be associated with the old ID.

3.8.5 group: optional

The optional callback in the group class implements connector specific operations on an HDF5 group. It returns an herr_t indicating success or failure.

```
herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);

Arguments:
obj (IN): The container or object where the operation needs to happen.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each connector should be able to parse the va_list arguments if it has connector specific operations to implement and determine the type of the operation and the parameters through a predefined schema.

3.8.6 group: close

The close callback in the group class terminates access to the group object and frees all resources it was consuming, and returns an herr_t indicating success or failure.

```
Signature:

herr_t (*close)(void *group, hid_t dxpl_id, void **req);

Arguments:
group (IN): Pointer to the group object.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
```

3.9 Link Callbacks

The link API routines (H5L) allow HDF5 users to create and manage HDF5 links. All the H5L API routines that modify the HDF5 container map to one of the link callback routines in this class that the connector needs to implement.

Listing 10: Structure for link callback routines, H5VLconnector.h

3.9.1 link: create

The create callback in the group class creates a hard, soft, external, or user-defined link in the container. It returns an herr_t indicating success or failure.

```
Signature:
      herr_t (*create)(H5VL_link_create_type_t create_type, void *obj,
          H5VL_loc_params_t *loc_params, hid_t lcpl_id,
          hid_t lapl_id, hid_t dxpl_id, void **req);
  The create_type argument is an enum:
  /* link create types for VOL */
  typedef enum H5VL_link_create_type_t {
2
      H5VL_LINK_CREATE_HARD, /* Hard Link
      H5VL_LINK_CREATE_SOFT, /* Soft Link
                                                  */
                            /* External / UD Link */
      H5VL_LINK_CREATE_UD
  } H5VL_link_create_type_t;
   Arguments:
    create_type
                   (IN): type of the link to be created.
                   (IN): Pointer to an object where the link needs to be created from.
    obj
                   (IN): Pointer to the location parameters as explained in Section 3.1 for the source object.
    loc_params
    lcpl_id
                   (IN): The link creation property list. It contains all the link creation properties in
                   addition to other API parameters depending on the creation type, which will be detailed
                   (IN): The link access property list.
    lapl_id
    dxpl_id
                   (IN): The data transfer property list.
                   (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
    req
                   nector.
```

As mentioned in the argument list, the lcpl_id contains the parameters for the link creation operation depending on the creation type:

- H5VL_LINK_CREATE_HARD contains two properties:
 - 1. H5VL_LINK_TARGET (with type void*): The target object where the hard link needs to be created to.
 - 2. H5VL_LINK_TARGET_LOC_PARAMS (with type H5VL_loc_params_t): The location parameters as explained in Section 3.1 for the target object.
- H5VL_LINK_CREATE_SOFT contains one property:
 - 1. H5VL_LINK_TARGET_NAME (with type char*): The target link where the soft link should point to.
- \bullet <code>H5VL_LINK_CREATE_UD</code> contains two properties:
 - 1. H5VL_LINK_TYPE (with type H5L_type_t): The user defined link class. H5L_TYPE_EXTERNAL suggests an external link is to be created.
 - 2. H5VL_LINK_UDATA (with type void*): User supplied link information (contains the external link buffer for external links).
 - 3. H5VL_LINK_UDATA_SIZE (with type size_t): size of the udata buffer.

3.9.2 link: copy

The copy callback in the link class copies a link within the HDF5 container. It returns an herr_t indicating success or failure.

Signature:

```
herr_t (*copy)(void *src_obj, H5VL_loc_params_t *loc_params1, void *dst_obj,
        H5VL_loc_params_t *loc_params2, hid_t lcpl_id, hid_t lapl_id, hid_t dxpl_id, void
        **req);
Arguments:
 src_obj
                (IN): original/source object or file.
 loc_params1
                (IN): Pointer to the location parameters for the source object as explained in Section 3.1.
                The type can be only H5VL_OBJECT_BY_NAME in this callback.
 dst_obj
                (IN): destination object or file.
                (IN): Pointer to the location parameters for the destination object as explained in Sec-
 loc_params1
                tion 3.1. The type can be only H5VL_OBJECT_BY_NAME in this callback.
                (IN): The link creation property list.
 lcpl_id
 lapl_id
                (IN): The link access property list.
 dxpl_id
                (IN): The data transfer property list.
                (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
                nector.
```

3.9.3 link: move

The move callback in the link class moves a link within the HDF5 container. It returns an herr_t indicating success or failure.

```
Signature:
   herr_t (*move)(void *src_obj, H5VL_loc_params_t *loc_params1, void *dst_obj,
        H5VL_loc_params_t *loc_params2, hid_t lcpl_id, hid_t lapl_id, hid_t dxpl_id, void
        **req);
Arguments:
                 (IN): original/source object or file.
 src_obj
 loc_params1
                 (IN): Pointer to the location parameters for the source object as explained in Section 3.1.
                 The type can be only H5VL_OBJECT_BY_NAME in this callback.
 dst_obj
                 (IN): destination object or file.
                 (IN): Pointer to the location parameters for the destination object as explained in Sec-
 loc_params1
                 tion 3.1. The type can be only H5VL_OBJECT_BY_NAME in this callback.
 lcpl_id
                 (IN): The link creation property list.
 lapl_id
                 (IN): The link access property list.
 dxpl_id
                 (IN): The data transfer property list.
                 (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
                 nector.
```

3.9.4 link: get

The get callback in the link class retrieves information about links as specified in the get_type parameter. It returns an herr_t indicating success or failure.

```
H5VL_LINK_GET_VAL
                             /* link value
} H5VL_link_get_t;
Arguments:
               (IN): The file or group object where information needs to be retrieved from.
 obj
               (IN): Pointer to the location parameters for the source object as explained in Section 3.1.
 loc_params
               The type can be only H5VL_OBJECT_BY_NAME or H5VL_OBJECT_BY_IDX in this callback.
 get_type
               (IN): The type of the information to retrieve.
               (IN): The data transfer property list.
 dxpl_id
               (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
               (IN/OUT): argument list containing parameters and output pointers for the get opera-
 arguments
               tion.
```

The arguments argument contains a variable list of arguments depending on the get_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_LINK_GET_INFO, to retrieve the link info from the link specified in the loc_params:
 - 1. H5L_info_t *linfo (OUT): pointer to info structure to fill.
- H5VL_LINK_GET_NAME, to retrieve the name of the link specified by the index information in loc_params (loc_params is of type H5VL_OBJECT_BY_IDX only with this type):
 - 1. char* name (OUT): buffer to copy the name into.
 - 2. size_t size (IN): size of the buffer name, if 0, return only the buffer size needed.
 - 3. ssize_t *ret (OUT): buffer to return the length of the link name.
- H5VL_LINK_GET_VAL, to retrieve the link value from the link specified in the loc_params:
 - 1. void *buf (OUT): buffer to put the value into.
 - 2. size_t size (IN): size of the passed in buffer.

3.9.5 link: specific

The specific callback in the link class implements specific operations on HDF5 links as specified in the specific_type parameter. It returns an herr_t indicating success or failure.

```
Signature:
       herr_t (*specific)(void *obj, H5VL_loc_params_t *loc_params, H5VL_link_specific_t
            specific_type, hid_t dxpl_id, void **req, va_list arguments);
The specific_type argument is an enum:
/* types for link SPECIFIC callback */
typedef enum H5VL_link_specific_t {
   H5VL_LINK_DELETE,
                            /* H5Ldelete(_by_idx)
                                                               */
   H5VL_LINK_EXISTS,
                            /* link existence
                                                               */
                             /* H5Literate/visit(_by_name)
   H5VL_LINK_ITER
                                                                     */
} H5VL_link_specific_t;
Arguments:
                   (IN): The location object where the operation needs to happen.
 obj
                   (IN): Pointer to the location parameters as explained in Section 3.1.
 loc_params
 specific_type
                  (IN): The type of the operation.
 dxpl_id
                   (IN): The data transfer property list.
                   (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
                   (IN/OUT): argument list containing parameters and output pointers for the get opera-
 arguments
                   tion.
```

The arguments argument contains a variable list of arguments depending on the specific_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_LINK_DELETE, to remove a link specified in the location parameter from an HDF5 container.
- H5VL_LINK_EXISTS, to determine whether the link specified in the loc_params exits (loc_params is of type H5VL_OBJECT_BY_NAME only with this type):
 - 1. htri_t *ret (OUT): buffer for the existence of the link (0 for no, 1 for yes).
- H5VL_LINK_ITER, to iterate over all links starting at the location provided and call a user-specified callback on each one:
 - 1. hbool_t recursive (IN): whether to recursively follow links into subgroups of the specified group.
 - 2. H5_index_t idx_type (IN): Type of index.
 - 3. H5_iter_order_t order (IN): Order in which to iterate over index.
 - 4. hsize_t *idx_p (IN/OUT): iteration position where to start and return position where an interrupted iteration may restart.
 - 5. H5L_iterate_t op (IN): User-defined function to pass each link to.
 - 6. void *op_data (IN/OUT): User data to pass through to and to be returned by iterator operator function.

3.9.6 link: optional

The optional callback in the link class implements connector specific operations on an HDF5 link. It returns an herr_t indicating success or failure.

```
herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);

Arguments:
obj (IN): The container or object where the operation needs to happen.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each connector should be able to parse the va_list arguments if it has connector specific operations to implement and determine the type of the operation and the parameters through a predefined schema.

3.10 Object Callbacks

The object API routines (H5O) allow HDF5 users to manage HDF5 group, dataset, and named datatype objects. All the H5O API routines that modify the HDF5 container map to one of the object callback routines in this class that the connector needs to implement.

Listing 11: Structure for object callback routines, H5VLconnector.h

3.10.1 object: open

The open callback in the object class opens the object in the container of the location object and returns a pointer to the object structure containing information to access the object in future calls.

```
Signature:
   void *(*open)(void *obj, H5VL_loc_params_t *loc_params,
       H5I_type_t *opened_type, hid_t dxpl_id, void **req);
Arguments:
                (IN): Pointer to a file or group where the object needs to be opened or where the look-up
 obj
                of the target object needs to start.
                (IN): Pointer to location parameters as explained in Section 3.1.
 loc_params
                (OUT): buffer to return the type of the object opened (H51_GROUP or H51_DATASET or
 opened_type
                H5I_DATATYPE).
                (IN): The data transfer property list.
 dxpl_id
 req
                (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
                nector.
```

3.10.2 object: copy

The copy callback in the object class copies the object from the source object to the destination object. It returns an herr_t indicating success or failure.

```
Signature:
      herr_t (*copy)(void *src_obj, H5VL_loc_params_t *loc_params1,
          const char *src_name, void *dst_obj,
2
          H5VL_loc_params_t *loc_params2, const char *dst_name,
          hid_t ocpypl_id, hid_t lcpl_id, hid_t dxpl_id, void **req);
  Arguments:
                   (IN): Pointer to location of the source object to be copied.
    src_obj
                   (IN): Pointer to location parameters as explained in Section 3.1. The type should only
    loc_params1
                   be H5VL_OBJECT_BY_SELF for this callback.
                   (IN): Name of the source object to be copied.
    src_name
                   (IN): Pointer to location of the destination object.
    dst_obj
                   (IN): Pointer to location parameters as explained in Section 3.1. The type should only
    loc_params2
                   be H5VL_OBJECT_BY_SELF for this callback.
                   (IN): Name to be assigned to the new copy.
    dst_name
    ocpypl_id
                   (IN): The object copy property list.
    lcpl_id
                   (IN): The link creation property list.
    dxpl_id
                   (IN): The data transfer property list.
                   (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
    req
                   nector.
```

3.10.3 object: get

The get callback in the object class retrieves information about the object as specified in the get_type parameter.It returns an herr_t indicating success or failure.

```
Signature:
    herr_t (*get)(void *obj, H5VL_loc_params_t *loc_params,
       H5VL_object_get_t get_type, hid_t dxpl_id,
       void **req, va_list arguments);
The get_type argument is an enum:
/* type for object GET callback */
typedef enum H5VL_object_get_t {
    H5VL_OBJECT_GET_FILE,
                                     /* object's file
                                                                       */
   H5VL_OBJECT_GET_NAME,
                                    /* object name
                                                                       */
   H5VL_OBJECT_GET_TYPE
                                    /* object type
} H5VL_object_get_t;
Arguments:
               (IN): A location object where information needs to be retrieved from.
 obj
               (IN): Pointer to location parameters as explained in Section 3.1.
 loc_params
 get_type
               (IN): The type of the information to retrieve.
 dxpl_id
               (IN): The data transfer property list.
               (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
 req
               (IN/OUT): argument list containing parameters and output pointers for the get opera-
 arguments
               tion.
```

The arguments argument contains a variable list of arguments depending on the get_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_OBJECT_GET_FILE, to retrieve a file for a referenced object:
 - 1. void **ret (OUT): pointer to buffer to return the file.
- H5VL_OBJECT_GET_NAME, to retrieve a name for a referenced object:
 - 1. ssize_t *ret (OUT): buffer to return the length of the name.
 - 2. char* name (OUT): buffer to copy the name into.
 - 3. size_t size (IN): size of the buffer name, if 0, return only the buffer size needed.
- H5VL_OBJECT_GET_TYPE, to retrieve object type a reference points to:
 - 1. H50_type_t *type (OUT): buffer to return the object type.

3.10.4 object: specific

The specific callback in the object class implements specific operations on HDF5 objects as specified in the specific_type parameter. It returns an herr_t indicating success or failure.

```
H5VL_OBJECT_EXISTS,
                                         /* H50exists_by_name
      H5VL_OBJECT_LOOKUP,
                                         /* Lookup object
                                                                            */
5
      H5VL_OBJECT_VISIT,
                                         /* H50visit(_by_name)
                                                                            */
6
      H5VL_OBJECT_FLUSH,
                                         /* H5{D|G|O|T}flush
                                                                            */
      H5VL_OBJECT_REFRESH
                                         /* H5{D|G|O|T}refresh
  } H5VL_object_specific_t;
   Arguments:
                      (IN): The location object where the operation needs to happen.
    obj
                      (IN): Pointer to location parameters as explained in Section 3.1.
    loc_params
    specific_type
                      (IN): The type of the operation.
                      (IN): The data transfer property list.
    dxpl_id
                      (IN/OUT): A pointer to the asynchronous request of the operation created by the con-
    req
                      nector.
    arguments
                      (IN/OUT): argument list containing parameters and output pointers for the get opera-
                      tion.
```

The arguments argument contains a variable list of arguments depending on the specific_type parameter. The following list shows the argument list, in order, for each type:

- H5VL_OBJECT_CHANGE_REF_COUNT, to update the reference count for the object in obj:
 - 1. int ref_count (IN): reference count to set on the object.
- H5VL_OBJECT_EXISTS, to check if an object with name specified in loc_params (type H5VL_OBJECT_BY_NAME)
 exists:
 - 1. htri_t *ret (OUT): existence result, 0 if false, 1 if true.
- H5VL_OBJECT_LOOKUP, Look up an object:
 - 1. void *token (IN): The object's token.
- H5VL_OBJECT_VISIT, to iterate over all objects starting at the location provided and call a user-specified callback on each one:
 - 1. H5_index_t idx_type (IN): Type of index.
 - 2. H5_iter_order_t order (IN): Order in which to iterate over index.
 - 3. H50_iterate_t op (IN): User-defined function to pass each object to.
 - 4. void *op_data (IN/OUT): User data to pass through to and to be returned by iterator operator function.
 - 5. unsigned fields (IN): Fields in H5O_info_t struct to return.
- H5VL_OBJECT_FLUSH, flushes a object:
 - 1. hid_t obj_id (IN): The object ID. Needed so that the refreshed data can be associated with the old ID.
- H5VL_OBJECT_REFRESH, clears an object's buffers and reloads from disk:
 - 1. hid_t obj_id (IN): The object ID. Needed so that the refreshed data can be associated with the old ID.

3.10.5 object: optional

The optional callback in the object class implements connector specific operations on an HDF5 object. It returns an herr_t indicating success or failure.

```
herr_t (*optional)(void *obj, hid_t dxpl_id, void **req, va_list arguments);

Arguments:
obj (IN): The container or object where the operation needs to happen.
dxpl_id (IN): The data transfer property list.
req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.
arguments (IN/OUT): argument list containing parameters and output pointers for the get operation.
```

Each connector should be able to parse the va_list arguments if it has connector specific operations to implement and determine the type of the operation and the parameters through a predefined schema.

3.11 Request (Async) Callbacks

```
typedef struct H5VL_request_class_t {
    herr_t (*wait)(void *req, uint64_t timeout, H5ES_status_t *status);
    herr_t (*notify)(void *req, H5VL_request_notify_t cb, void *ctx);
    herr_t (*cancel)(void *req);
    herr_t (*specific)(void *req, H5VL_request_specific_t specific_type, va_list arguments);
    herr_t (*optional)(void *req, va_list arguments);
    herr_t (*free)(void *req);
} H5VL_request_class_t;
```

Listing 12: Structure for async request callback routines, H5VLconnector.h

3.11.1 request: wait

Wait (with a timeout) for an async operation to complete. Releases the request if the operation has completed and the connector callback succeeds.

```
Signature:
   herr_t (*wait)(void *req, uint64_t timeout, H5ES_status_t *status);
The status argument is an enum (from H5ESpublic.h):
/* Asynchronous operation status */
typedef enum H5ES_status_t {
   H5ES_STATUS_IN_PROGRESS, /* Operation has not yet completed
                                                                                 */
   H5ES_STATUS_SUCCEED,
                           /* Operation has completed, successfully
                                                                                 */
   H5ES_STATUS_FAIL,
                            /* Operation has completed, but failed
                                                                                 */
   H5ES_STATUS_CANCELED
                            /* Operation has not completed and was canceled
                                                                                 */
} H5ES_status_t;
Arguments:
            (IN): The async request on which to wait.
 req
            (IN): The timeout value.
 timeout
            (IN): The status.
 status
```

3.11.2 request: notify

Registers a user callback to be invoked when an asynchronous operation completes. Releases the request if connector callback succeeds.

Signature:

```
herr_t (*notify)(void *req, H5VL_request_notify_t cb, void *ctx);
The cb argument is a function pointer:
   typedef herr_t (*H5VL_request_notify_t)(void *ctx, H5ES_status_t status);
Arguments:
       (IN): The async request that will receive the notify callback.
 req
       (IN): The notify callback for the request.
 cb
 ctx
       (IN): The request's context.
```

3.11.3 request: cancel

Cancels an asynchronous operation. Releases the request if connector callback succeeds.

Signature:

```
herr_t (*cancel)(void *req);
Arguments:
 req (IN): The async request to be cancelled.
```

3.11.4 request: specific

Perform a specific operation on an asynchronous request.

```
Signature:
   herr_t (*specific)(void *req, H5VL_request_specific_t specific_type, va_list arguments);
The specific_type argument is an enum:
/* types for async request SPECIFIC callback */
typedef enum H5VL_request_specific_t {
   H5VL_REQUEST_WAITANY,
                                    /* Wait until any request completes */
   H5VL_REQUEST_WAITSOME,
                                    /* Wait until at least one requesst completes */
   H5VL_REQUEST_WAITALL
                                    /* Wait until all requests complete */
} H5VL_request_specific_t;
Arguments:
                  (IN): The async request on which to perform the operation.
 req
                  (IN): The specific operation to perform.
 specific_type
                  (IN/OUT): argument list containing parameters and output pointers for the operation.
 arguments
```

request: optional

Perform a connector-specific operation for a request.

```
Signature:
   herr_t (*optional)(void *req, va_list arguments);
Arguments:
              (IN): The async request on which to perform the operation.
              (IN/OUT): argument list containing parameters and output pointers for the operation.
```

3.11.6 request: free

Frees an asynchronous request.

```
Signature:
   herr_t (*free)(void *req);
Arguments:
 req (IN): The async request to be freed.
```

Blob Callbacks 3.12

```
typedef struct H5VL_blob_class_t {
   herr_t (*put)(void *obj, const void *buf, size_t size, void *blob_id, void *ctx);
   herr_t (*get)(void *obj, const void *blob_id, void *buf, size_t size, void *ctx);
   herr_t (*specific)(void *obj, void *blob_id, H5VL_blob_specific_t specific_type, va_list
        arguments);
   herr_t (*optional)(void *obj, void *blob_id, va_list arguments);
} H5VL_blob_class_t;
```

Listing 13: Structure for blob callback routines, H5VLconnector.h

3.12.1 blob: put

Put a blob through the VOL.

```
Signature:
```

```
herr_t (*put)(void *obj, const void *buf, size_t size, void *blob_id, void *ctx);
Arguments:
 obj
           (IN): Pointer to the blob container.
 buf
           (IN): Pointer to the blob.
 size
           (IN): Size of the blob.
           (OUT): Pointer to the blob's connector-specific ID.
 blob_id
           (IN): Connector-specific blob context.
 ctx
```

3.12.2 blob: get

Get a blob through the VOL.

```
Signature:
```

```
herr_t (*get)(void *obj, const void *blob_id, void *buf, size_t size, void *ctx);
Arguments:
           (IN): Pointer to the blob container.
 obj
 blob_id
           (IN): Pointer to the blob's connector-specific ID.
           (IN/OUT): Pointer to the blob.
 buf
 size
           (IN): Size of the blob.
           (IN): Connector-specific blob context.
 ctx
```

blob: specific 3.12.3

Perform a defined operation on a blob via the VOL.

```
Signature:
```

```
herr_t (*specific)(void *obj, void *blob_id, H5VL_blob_specific_t specific_type, va_list
    arguments);
```

```
The specific_type argument is an enum:
  typedef enum H5VL_blob_specific_t {
      H5VL_BLOB_DELETE,
                                        /* Delete a blob (by ID) */
2
      H5VL_BLOB_GETSIZE,
                                        /* Get size of blob */
3
      H5VL_BLOB_ISNULL,
                                        /* Check if a blob ID is "null" */
      H5VL_BLOB_SETNULL
                                        /* Set a blob ID to the connector's "null" blob ID value */
5
  } H5VL_blob_specific_t;
   Arguments:
    obj
                     (IN): Pointer to the blob container.
                     (IN): Pointer to the blob's connector-specific ID.
    blob\_id
                     (IN): The operation to perform.
    specific_type
                     (IN/OUT): argument list containing parameters and output pointers for the operation.
    arguments
```

3.12.4 blob: optional

Perform a connector-specific operation on a blob via the VOL.

```
Signature:

herr_t (*optional)(void *obj, void *blob_id, va_list arguments);

Arguments:
obj (IN): Pointer to the blob container.
blob_id (IN): Pointer to the blob's connector-specific ID.
arguments (IN/OUT): argument list containing parameters and output pointers for the operation.
```

3.13 Optional Generic Callback

A generic optional callback is provided for services that are specific to a connector.

The optional callback has the following definition. It returns an herr_t indicating success or failure.

```
Arguments:

obj (IN): The container or object where the operation needs to happen.

dxpl_id (IN): The data transfer property list.

req (IN/OUT): A pointer to the asynchronous request of the operation created by the connector.

arguments (IN/OUT): argument list containing parameters and output pointers for the operation.
```

4 New VOL API Routines

New API routines have been added to the HDF5 library to manage VOL connectors. This section details each new API call and explains their intended usage. Additionally, a set of API calls that map directly to the VOL callbacks themselves have been added to aid in the development of passthrough connectors which can be stacked and/or split. A list of these API calls is given in an appendix.

4.1 H5VLpublic.h

The API calls in this header are for VOL management and general use (i.e., not limited to VOL connector authors).

4.1.1 H5VLregister_connector

Signature: hid_t H5VLregister_connector(const H5VL_class_t *cls, hid_t vipl_id); Arguments: cls (IN): A pointer to the connector structure to register. vipl_id (IN): An ID for a VOL initialization property list (vipl).

Registers a user-defined VOL connector with the HDF5 library and returns an identifier for that connector (H5I_INVALID_HID on errors). This function is used when the application has direct access to the connector it wants to use and is able to obtain a pointer for the connector structure to pass to the HDF5 library.

4.1.2 H5VLregister_connector_by_name

```
Signature:

hid_t H5VLregister_by_name(const char *connector_name, hid_t vipl_id);

Arguments:

name (IN): The connector name to search for and register.

vipl_id (IN): An ID for a VOL initialization property list (vipl).
```

Registers a VOL connector with the HDF5 library given the name of the connector and returns an identifier for it (H5I_INVALID_HID on errors). If the connector is already registered, the library will create a new identifier for it and returns it to the user; otherwise the library will search the plugin path for a connector of that name, loading and registering it, returning an ID for it, if found. See the VOL User Guide for more information on loading plugins and the search paths.

4.1.3 H5VLregister_connector_by_value

```
Signature:

hid_t H5VLregister_by_value(H5VL_class_value_t connector_value, hid_t vipl_id);

Arguments:

connector_value (IN): The connector value to search for and register.

vipl_id (IN): An ID for a VOL initialization property list (vipl).
```

Registers a VOL connector with the HDF5 library given a value for the connector and returns an identifier for it (H5I_INVALID_HID on errors). If the connector is already registered, the library will create a new identifier for it and returns it to the user; otherwise the library will search the plugin path for a connector of that name, loading and registering it, returning an ID for it, if found. See the VOL User Guide for more information on loading plugins and the search paths.

4.1.4 H5VLis_connector_registered

```
Signature:

htri_t H5VLis_connector_registered(const char *name);

Arguments:
name (IN): The connector name to check for.
```

Checks if a VOL connector is registered with the library given the connector name and returns TRUE/FALSE on success, otherwise it returns a negative value.

4.1.5 H5VLget_connector_id

Signature: hid_t H5VLget_connector_id(const char *name); Arguments: name (IN): The connector name to check for.

Given a connector name that is registered with the library, this function returns an identifier for the connector. If the connector is not registered with the library, a negative value is returned. The identifier must be released with a call to <code>H5VLclose()</code>.

4.1.6 H5VLget_connector_name

```
Signature:

ssize_t H5VLget_connector_name(hid_t id, char *name/*out*/, size_t size);

Arguments:
id (IN): The object identifier to check.
name (OUT): Buffer pointer to put the connector name. If NULL, the library just returns the size required to store the connector name.
size (IN): the size of the passed in buffer.
```

Retrieves the name of a VOL connector given an object identifier that was created/opened with it. On success, the name length is returned.

4.1.7 H5VLclose

```
Signature:
herr_t H5VLclose(hid_t connector_id);

Arguments:
connector_id (IN): A valid identifier of the connector to close.
```

Shuts down access to the connector that the identifier points to and release resources associated with it.

4.1.8 H5VLunregister_connector

```
Signature:
herr_t H5VLunregister(hid_t connector_id);

Arguments:
connector_id (IN): A valid identifier of the connector to unregister.
```

Unregisters a connector from the library and return a positive value on success otherwise return a negative value. The native VOL connector cannot be unregistered (this will return a negative herr_t value).

4.2 H5VLconnector.h

This functionality is intended for VOL connector authors and includes helper functions that are useful for writing connectors. Callback equivalent functions can be found in H5VLconnector_passthru.h. A list of these functions is included as an appendix to this document.

4.2.1 H5VLobject

```
Signature:

void *H5VLget_object(hid_t obj_id);

Arguments:
obj_id (IN): identifier of the object to dereference.
```

Retrieves a pointer to the VOL object from an HDF5 file or object identifier.

4.2.2 H5VLget_file_type

```
Signature:

hid_t H5VLget_file_type(void *file_obj, hid_t connector_id, hid_t dtype_id);

Arguments:
file_obj (IN): pointer to a file or file object's connector-specific data.
connector_id (IN): A valid identifier of the connector to use.
dtype_id (IN): A valid identifier for the type.
```

Returns a copy of the dtype_id parameter but with the location set to be in the file. Returns a negative value (H5I_INVALID_HID) on errors.

4.2.3 H5VLpeek_connector

```
Signature:

hid_t H5VLpeek_connector_id(const char *name);

Arguments:
name (IN): name of the connector to query.
```

Retrieves the ID for a registered VOL connector. This is done without duplicating the ID and transferring ownership to the caller (as it normally the case in the HDF5 library). The ID returned from this operation should not be closed. This is intended for use by VOL connectors to find their own ID.

Returns a negative value (H5I_INVALID_HID) on errors.

Appendix A Mapping of VOL Callbacks to HDF5 API Calls

VOL Callback	HDF5 API Call
FILE	
create	H5Fcreate
open	H5Fopen
get	H5Fget_access_plist
	H5Fget_create_plist
	H5Fget_fileno
	H5Fget_intent
	H5Fget_name
	H5Fget_obj_count
	H5Fget_obj_ids
specific	H5Fdelete
	H5Fflush
	H5Fis_accessible
	H5Fis_hdf5 (deprecated, hard-coded to use native connector)
	H5Fmount
	H5Freopen
close	H5Funmount H5Fclose
GROUP	1101 Close
	H5Gcreate1 (deprecated)
create	H5Gcreate2
	H5Gcreate_anon
open	H5Gopen1 (deprecated)
Орен	H5Gopen2
get	H5Gget_create_plist
800	H5Gget_info
	H5Gget_info_by_idx
	H5Gget_info_by_name
	H5Gget_num_objs (deprecated)
specific	H5Gflush
_	H5Grefresh
close	H5Gclose
DATASET	
create	H5Dcreate1 (deprecated)
	H5Dcreate2
open	H5Dopen1 (deprecated)
	H5Dopen2
read	H5Dread
write	H5Dwrite
get	H5Dget_access_plist
	H5Dget_create_plist
	H5Dextend
	H5Dget_offset
	H5Dget_space
	H5Dget_space_status
	H5Dget_storage_size
:e-	H5Dget_type
specific	H5Dextend (deprecated) H5Dflush
	H5Drusn H5Drefresh
	H5Drefresh H5Dset_extent
close	H5Dclose H5Dclose
OBJECT	119DCIOSE
	H5Oopen
open	H5Oopen_by_addr
	H5Oopen_by_idx
	11000pon_by_max

	H5Oopen_by_name
copy	H5Ocopy
get	N/A
specific	H5Odecr_refcount
	H5Oexists_by_name
	H5Oflush
	H5O_incr_refcount
	H5Orefresh
	H5Ovisit_by_name1 (deprecated)
	H5Ovisit_by_name2
	H5Ovisit1 (deprecated)
	H5Ovisit2
close	H5Oclose
LINK	
create	H5Glink (deprecated)
	H5Glink2 (deprecated)
	H5Lcreate_hard
	H5Lcreate_soft
	H5Lcreate_ud
	H5Olink
copy	H5Lcopy
move	H5Gmove (deprecated)
	H5Gmove2 (deprecated)
	H5Lmove
get	H5Gget_linkval (deprecated)
8	H5Lget_info
	H5Lget_info_by_idx
	H5Lget_name_by_idx
	H5Lget_val
	H5Lget_val_by_idx
specific	H5Gunlink (deprecated)
~ F	H5Ldelete
	H5Ldelete_by_idx
	H5Lexists
	H5Literate
	H5Literate_by_name
	H5Lvisit
	H5Lvisit_by_name
DATATYPE	
commit	H5Tcommit1 (deprecated)
	H5Tcommit2
	H5Tcommit_anon
open	H5Topen1 (deprecated)
-	H5Topen2
get	H5Tget_create_plist
specific	H5Tflush
r	H5Trefresh
close	H5Tclose
ATTRIBUTE	
create	H5Acreate1 (deprecated)
210000	H5Acreate2
	H5Acreate_by_name
open	H5Aopen
	H5Aopen_by_idx
	H5Aopen_by_name
	H5Aopen_idx (deprecated)
	H5Aopen_name (deprecated)
man d	
read	H5Aread
write	H5Awrite
get	H5Aget_get_create_plist

	H5Aget_info H5Aget_info_by_idx H5Aget_info_by_name H5Aget_name
	H5Aget_name_by_idx H5Aget_space H5Aget_storage_size
	H5Aget_type
specific	H5Adelete_by_idx H5Adelete_by_name H5Aexists H5Aexists_by_name H5Aiterate1 (deprecated) H5Aiterate2 H5Aiterate_by_name H5Arename H5Arename H5Arename
close	H5Aclose

Table 1: Breakdown of HDF5 API calls by VOL callback

Appendix B Callback Wrapper API Calls for Passthrough Connector Authors

From H5VL_connector_passthru.h

```
/* Helper routines for VOL connector authors */
   herr_t H5VLcmp_connector_cls(int *cmp, hid_t connector_id1, hid_t connector_id2);
   hid_t H5VLwrap_register(void *obj, H5I_type_t type);
   herr_t H5VLretrieve_lib_state(void **state);
   herr_t H5VLrestore_lib_state(const void *state);
   herr_t H5VLreset_lib_state(void);
   herr_t H5VLfree_lib_state(void *state);
   /* Pass-through callbacks */
   void *H5VLget_object(void *obj, hid_t connector_id);
   herr_t H5VLget_wrap_ctx(void *obj, hid_t connector_id, void **wrap_ctx);
   void *H5VLwrap_object(void *obj, H5I_type_t obj_type, hid_t connector_id, void *wrap_ctx);
   void *H5VLunwrap_object(void *obj, hid_t connector_id);
   herr_t H5VLfree_wrap_ctx(void *wrap_ctx, hid_t connector_id);
15
16
   /* Public wrappers for generic callbacks */
17
   herr_t H5VLinitialize(hid_t connector_id, hid_t vipl_id);
   herr_t H5VLterminate(hid_t connector_id);
   herr_t H5VLget_cap_flags(hid_t connector_id, unsigned *cap_flags);
   herr_t H5VLget_value(hid_t connector_id, H5VL_class_value_t *conn_value);
22
   /* Public wrappers for info fields and callbacks */
23
   herr_t H5VLcopy_connector_info(hid_t connector_id, void **dst_vol_info, void *src_vol_info);
24
   herr_t H5VLcmp_connector_info(int *cmp, hid_t connector_id, const void *info1,
25
       const void *info2);
26
   herr_t H5VLfree_connector_info(hid_t connector_id, void *vol_info);
27
   herr_t H5VLconnector_info_to_str(const void *info, hid_t connector_id, char **str);
28
   herr_t H5VLconnector_str_to_info(const char *str, hid_t connector_id, void **info);
   /* Public wrappers for attribute callbacks */
   void *H5VLattr_create(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id, const
        char *attr_name, hid_t type_id, hid_t space_id, hid_t acpl_id, hid_t aapl_id, hid_t dxpl_id,
       void **req);
   void *H5VLattr_open(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id, const char
        *name, hid_t aapl_id, hid_t dxpl_id, void **req);
   herr_t H5VLattr_read(void *attr, hid_t connector_id, hid_t dtype_id, void *buf, hid_t dxpl_id,
       void **req);
   herr_t H5VLattr_write(void *attr, hid_t connector_id, hid_t dtype_id, const void *buf, hid_t
       dxpl_id, void **req);
   herr_t H5VLattr_get(void *obj, hid_t connector_id, H5VL_attr_get_t get_type, hid_t dxpl_id, void
        **req, va_list arguments);
   herr_t H5VLattr_specific(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id,
       H5VL_attr_specific_t specific_type, hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLattr_optional(void *obj, hid_t connector_id, hid_t dxpl_id, void **req, va_list
38
       arguments):
   herr_t H5VLattr_close(void *attr, hid_t connector_id, hid_t dxpl_id, void **req);
39
40
   /* Public wrappers for dataset callbacks */
41
   void *H5VLdataset_create(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id, const
        char *name, hid_t lcpl_id, hid_t type_id, hid_t space_id, hid_t dcpl_id, hid_t dapl_id, hid_t
       dxpl_id, void **req);
   void *H5VLdataset_open(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id, const
        char *name, hid_t dapl_id, hid_t dxpl_id, void **req);
   herr_t H5VLdataset_read(void *dset, hid_t connector_id, hid_t mem_type_id, hid_t mem_space_id,
       hid_t file_space_id, hid_t plist_id, void *buf, void **req);
   herr_t H5VLdataset_write(void *dset, hid_t connector_id, hid_t mem_type_id, hid_t mem_space_id,
       hid_t file_space_id, hid_t plist_id, const void *buf, void **req);
   herr_t H5VLdataset_get(void *dset, hid_t connector_id, H5VL_dataset_get_t get_type, hid_t dxpl_id,
       void **req, va_list arguments);
```

```
herr_t H5VLdataset_specific(void *obj, hid_t connector_id, H5VL_dataset_specific_t specific_type,
       hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLdataset_optional(void *obj, hid_t connector_id, hid_t dxpl_id, void **req, va_list
        arguments):
   herr_t H5VLdataset_close(void *dset, hid_t connector_id, hid_t dxpl_id, void **req);
49
50
   /* Public wrappers for file callbacks */
51
   void *H5VLfile_create(const char *name, unsigned flags, hid_t fcpl_id, hid_t fapl_id, hid_t
52
       dxpl_id, void **req);
   void *H5VLfile_open(const char *name, unsigned flags, hid_t fapl_id, hid_t dxpl_id, void **req);
53
   herr_t H5VLfile_get(void *file, hid_t connector_id, H5VL_file_get_t get_type, hid_t dxpl_id, void
        **req, va_list arguments);
   herr_t H5VLfile_specific(void *obj, hid_t connector_id, H5VL_file_specific_t specific_type, hid_t
       dxpl_id, void **req, va_list arguments);
   herr_t H5VLfile_optional(void *obj, hid_t connector_id, hid_t dxpl_id, void **req, va_list
        arguments):
   herr_t H5VLfile_close(void *file, hid_t connector_id, hid_t dxpl_id, void **req);
57
58
   /* Public wrappers for group callbacks */
59
   void *H5VLgroup_create(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id, const
60
        char *name, hid_t lcpl_id, hid_t gcpl_id, hid_t gapl_id, hid_t dxpl_id, void **req);
   void *H5VLgroup_open(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id, const
       char *name, hid_t gapl_id, hid_t dxpl_id, void **req);
   herr_t H5VLgroup_get(void *obj, hid_t connector_id, H5VL_group_get_t get_type, hid_t dxpl_id, void
       **req, va_list arguments);
   herr_t H5VLgroup_specific(void *obj, hid_t connector_id, H5VLgroup_specific_t specific_type,
       hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLgroup_optional(void *obj, hid_t connector_id, hid_t dxpl_id, void **req, va_list
64
       arguments);
   herr_t H5VLgroup_close(void *grp, hid_t connector_id, hid_t dxpl_id, void **req);
65
66
   /* Public wrappers for link callbacks */
67
   herr_t H5VLlink_create(H5VL_link_create_type_t create_type, void *obj, const H5VL_loc_params_t
        *loc_params, hid_t connector_id, hid_t lcpl_id, hid_t lapl_id, hid_t dxpl_id, void **req,
       va_list arguments);
   herr_t H5VLlink_copy(void *src_obj, const H5VL_loc_params_t *loc_params1, void *dst_obj, const
       H5VL_loc_params_t *loc_params2, hid_t connector_id, hid_t lcpl_id, hid_t lapl_id, hid_t
       dxpl_id, void **req);
   herr_t H5VLlink_move(void *src_obj, const H5VL_loc_params_t *loc_params1, void *dst_obj, const
       H5VL_loc_params_t *loc_params2, hid_t connector_id, hid_t lcpl_id, hid_t lapl_id, hid_t
       dxpl_id, void **req);
   herr_t H5VLlink_get(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id,
       H5VL_link_get_t get_type, hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLlink_specific(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id,
       H5VL_link_specific_t specific_type, hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLlink_optional(void *obj, hid_t connector_id, hid_t dxpl_id, void **req, va_list
        arguments);
74
   /* Public wrappers for object callbacks */
75
   void *H5VLobject_open(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id,
76
       H5I_type_t *opened_type, hid_t dxpl_id, void **req);
   herr_t H5VLobject_copy(void *src_obj, const H5VL_loc_params_t *loc_params1, const char *src_name,
        void *dst_obj, const H5VL_loc_params_t *loc_params2, const char *dst_name, hid_t connector_id,
       hid_t ocpypl_id, hid_t lcpl_id, hid_t dxpl_id, void **req);
   herr_t H5VLobject_get(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id,
       H5VL_object_get_t get_type, hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLobject_specific(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id,
       H5VL_object_specific_t specific_type, hid_t dxpl_id, void **req, va_list arguments);
   herr_t H5VLobject_optional(void *obj, hid_t connector_id, hid_t dxpl_id, void **req, va_list
       arguments);
81
   /* Public wrappers for named datatype callbacks */
82
   void *H5VLdatatype_commit(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id,
        const char *name, hid_t type_id, hid_t lcpl_id, hid_t tcpl_id, hid_t tapl_id, hid_t dxpl_id,
        void **req);
   void *H5VLdatatype_open(void *obj, const H5VL_loc_params_t *loc_params, hid_t connector_id, const
```

REFERENCES REFERENCES

```
char *name, hid_t tapl_id, hid_t dxpl_id, void **req);
    herr_t H5VLdatatype_get(void *dt, hid_t connector_id, H5VL_datatype_get_t get_type, hid_t dxpl_id,
        void **req, va_list arguments);
    herr_t H5VLdatatype_specific(void *obj, hid_t connector_id, H5VL_datatype_specific_t
        specific_type, hid_t dxpl_id, void **req, va_list arguments);
    herr_t H5VLdatatype_optional(void *obj, hid_t connector_id, hid_t dxpl_id, void **req, va_list
        arguments):
    herr_t H5VLdatatype_close(void *dt, hid_t connector_id, hid_t dxpl_id, void **req);
88
89
    /* Public wrappers for asynchronous request callbacks */
90
    herr_t H5VLrequest_wait(void *req, hid_t connector_id, uint64_t timeout, H5ES_status_t *status);
91
    herr_t H5VLrequest_notify(void *req, hid_t connector_id, H5VL_request_notify_t cb, void *ctx);
    herr_t H5VLrequest_cancel(void *req, hid_t connector_id);
93
    herr_t H5VLrequest_specific(void *req, hid_t connector_id, H5VL_request_specific_t specific_type,
        va_list arguments);
    herr_t H5VLrequest_optional(void *req, hid_t connector_id, va_list arguments);
    herr_t H5VLrequest_free(void *req, hid_t connector_id);
96
97
    /* Public wrappers for blob callbacks */
98
    herr_t H5VLblob_put(void *obj, hid_t connector_id, const void *buf, size_t size, void *blob_id,
        void *ctx);
    herr_t H5VLblob_get(void *obj, hid_t connector_id, const void *blob_id, void *buf, size_t size,
100
        void *ctx);
    herr_t H5VLblob_specific(void *obj, hid_t connector_id, void *blob_id, H5VL_blob_specific_t
        specific_type, va_list arguments);
102
    /* Public wrappers for generic 'optional' callback */
103
    herr_t H5VLoptional(void *obj, hid_t connector_id, hid_t dxpl_id, void **req, va_list arguments);
104
```

References