

2301 Fluid Mechanics Notes  
Based on the autumn 2011 lectures  
by Prof E R Johnson .

To the times that we suffered for the  
sake of understanding mathematics and  
to which we shall be rewarded for it.

Ein Omer.

3/10/11

What about?

Magma Dynamics: - dynamics of the interior of Earth.  
- dynamo theory.


Plasma: - Sun, star and fusion.

Blood: - Biofluid dynamics.

Atmosphere + Oceans

- Meteorology
- Climate

Eg:



"Air resistance"

- flow past bodies
- Cars
- Planes

/ Geophysical Fluid Dynamics  
"GFD".

Books

A first course in Fluid Dynamics  
A. R. Patterson, Cambridge.

Ideal and Incompressible Fluid Dynamics.

— — —

$\underline{u}(x, y, z, t)$  Clay Institute.

$$\frac{\partial \underline{u}}{\partial t} + (\underline{u} \cdot \nabla) \underline{u} = -\nabla p + D \nabla^2 \underline{u}$$

$$\nabla \cdot \underline{u} = 0 \quad (\text{Navier Stokes})$$

Either

$\exists \underline{u}(x, y, z, 0)$  smooth, bdd.  
But  $|\underline{u}| \rightarrow \infty$  at  $t = t_0 > 0$ .

Or

No such  $\underline{u}(x, y, z, 0)$  exists.

— — —

How does a plane fly?

Geometry of wind cross section.

Speed  $\leftarrow$  directly proportional to  $\underline{u}$ .

Directly proportional density  $\rightarrow$  It is the product of  $K_p A V$ .

— — —

How fast does a surface water travel?

Depth:  $h$


Gravity:  $g$

Wavelength:  $\lambda$ .



$$[c] = [T^{-1}]$$


$$[g] = [T^{-2}]$$



Short waves, deep waters:


$$\lambda/h \ll 1$$

( $\sim (gh)^{1/2}$  → speed a wave travels  
(different lengths, different speeds)).



Max speed  $c = \sqrt{g\lambda}$

$\uparrow$  make them longer





Long waves on shallow water:

$$\lambda/h \gg 1$$


$\sim (gh)^{1/2}$  All waves travel at same speed.

$$\begin{aligned}
 C &= \sqrt{gh} \\
 &= [(9.8 \text{ m/sec}^{-2} \times 4 \times 10^3 \text{ m})]^{1/2} \\
 &= [4 \times 10^4 \text{ m}^2 \text{ sec}^{-2}]^{1/2} \\
 &= 200 \text{ m sec}^{-1}.
 \end{aligned}$$




-/-

Green's law:



Speed  $\times$  Energy Density  
 $cH^2$



Energy a quadratic equation:

$$cH^2 = \text{constant}$$

$$H^2 \propto c^{-1}, H \propto c^{-1/2}, c \propto h^{1/2}, H \propto h^{-1/4}$$

$$4\text{km} \rightarrow 0.4\text{m}$$

$h$  decreases so  $H$  increase by 10.



## Chapter 1


### Specification and Kinematics

Continuum - a substance that we take arbitrary small volumes of and whose properties remain the same.


We do so ( $\lim_{V \rightarrow 0}$  exist).

Take a volume  $V$ , measure "its" mass  $m$ , and define its density  $\bar{\rho} = m/V$ .

Could take  $V > V_1 > V_2 \dots$  and defines the density at some point common to this sequence:  
 $\rho = \lim_{V \rightarrow 0} (m/V)$ .




This is a good approximation to reality provided we are interested in motions at scales large compared to the mean free path.



mean free path.

We will restrict attention to invicid fluids (fluids that are not viscous). A fluids are invicid if it cannot support a shear stress.



Due to friction on bottom, opposing.

Summary


- 1) Continuum: We can discuss infinitesimal volume of fluid.

2) Inviscid : The fluid cannot support a shear stress.

3) Incompressible : The volume of the fluid element remains the same throughout the motion.

A element composed of the same fluid has the same. Hence density is constant.

a) This does not mean that the density is the same everywhere.



b) This is a good approximation provided speeds are small compare with the speed of sound (700 m/s) i.e. the Mach number of the flow; (typical speed : sound speed =  $m$ ) is small ( $\ll 1$ ),  $m < 1$  supersonic,  $m > 1$  supersonic.

To describe the flow we have two choices.


a) Lagrangian labelling - Label all particles + follow their motions i.e follows particle path.

Strength - Conservation laws easy.

Drawback - Simple motion can have complicated paths.

b) Eulerian description - set up fixed axes, we

define a velocity field  $\mathbf{u}(x, y, z, t)$  by defining the velocity  $\mathbf{u}$  at time  $t$  to be the velocity of the fluid element (or fluid particle) that is at  $x$  at time  $t$ .



Strengths - velocity is a vector field; we can use vector calculus.


Drawback - conservation laws become a little more complicated.

We do the same thing for density  $\rho(x, y, z, t)$ , i.e. although in incompressible flow, each particle maintains its own density, the Eulerian density (at a point) can change as different particles occupy that point at different times.

Of course, in homogeneous fluid,  $\rho = \text{constant}$ .

There are three ways of increasing or decreasing a motion:

- 1) Particle path: the path traced out by the fluid element during a given time interval.



2) Streakline / Filament line : the locus of all particles, that have passed through a given point in a given time interval.








6/10/11

$\lim_{\delta V \rightarrow 0}$  Continuum,

$$\lim_{\delta V \rightarrow 0} \left( \frac{\Delta M}{\Delta V} \right) = \rho.$$




A transmit a shear stress to B.



A does not transmit shear (tangential) stress:  
(force unit area).


NOT VISCOUS - INVISCOUS



Eulerian:  $u(x, t)$  = velocity of particle that happens to be at  $x$  at time  $t$ .

### Visualise :



- 1) Particle path : Path traced out by a fluid element in a given time interval.



Infinitesimal  
fluid element

- 2) Streakline : The locus of all particle that have passed through a given point in a given time interval

- 3) Streamline : Line whose tangent gives the direction of velocity at that point.



Suppose we are given a velocity field  $\underline{u}(r, t)$

Particle Path satisfy

$$\frac{dr}{dt} = \underline{u}(r, t) \text{ with } r = r_0 \text{ at } t=0.$$

Example :

Consider the two-dimensional velocity field.

$$\underline{u}(r, t) = \begin{pmatrix} 1 \\ -2te^{-t^2} \end{pmatrix}$$

2D flow field : field independent of the third direction i.e. the same in each  $x-y$  plane.

We shall also take the velocity components in the normal direction to be zero.


In cartesian it is conventional to write:

$$\underline{u}(x, y, z, t) = u(x, y, z, t) \hat{i} + v(x, y, z, t) \hat{j} + w(x, y, z, t) \hat{k}$$

$$\text{i.e. } \underline{u} = \begin{pmatrix} u \\ v \\ w \end{pmatrix}$$

2D flow -  $w \equiv 0$ ,  $u = u(x, y, t)$ ,  $v = v(x, y, t)$

Flow is the same at each  $z$ :



$$\text{Now: } \underline{u}(\underline{r}, t) = \hat{i} - 2t e^{-t^2} \hat{j}$$

$$\text{So: } \frac{d\underline{r}}{dt} = \underline{u}(r, t).$$

$$\text{i.e. } \frac{dx}{dt} = u, \quad \frac{dy}{dt} = v.$$

$$\text{Hence: } u = 1 \\ v = -2t e^{-t^2}.$$

$$\text{So: } \frac{dx}{dt} = 1 \quad \text{and} \quad \frac{dy}{dt} = -2t e^{-t^2}.$$

$$\text{i.e. } x = t + x_0 \quad \text{and} \quad y = e^{-t^2} + y_0.$$

What is the path traced out by the particle released from  $(1, 1)$  at  $t = 0$ ?

$$\text{At } t = 0, x = 1 \text{ so } x_0 = 1, y = 1 \text{ so } y_0 = 0$$


Thus p.p (particle path) is:

$$x = 1 + t \\ y = e^{-t^2}.$$

Parameterised by time  $t$ .

[Use Parametric Plot : Mathematica]

$$\text{Here } t = x - 1 \text{ so } y = e^{-(x-1)^2}$$



What is the streakline traced out particles released from  $(1, 1)$  at time  $\tau < 0$  when viewed at time  $t = 0$ ?

Particle Path :  $x = t + x_0$ .  
 $y = e^{-t^2} + y_0$ .

At  $\tau$ , particle in locus was at  $(1, 1)$ . [That's when it was emitted].

$$1 = \tau + x_0, \quad 1 = e^{-\tau^2} + y_0.$$


$$\text{i.e } x_0 = 1 - \tau, \quad y_0 = 1 - e^{-\tau^2}$$

The particle is at  $(x, y)$  at time  $t$  when

$$x = t + 1 - \tau, \quad y = e^{-t^2} + 1 - e^{-\tau^2}$$

$$\text{So at } t = 0 \text{ it is at } x = 1 - \tau, \quad y = 1 - e^{-\tau^2}$$



Parameterised by time of emission. Sufficiently simple that we can eliminate  $\tau$ .



Emitted at  $\tau < 0$ , look at  $t = 0$

$\rightarrow / \rightarrow$

Streamline.



$$\lim_{\substack{P \rightarrow 0 \\ \Delta s \rightarrow 0}} \frac{r(s + \Delta s) - r(s)}{\Delta s} = \frac{dr}{ds}.$$

Parameterise  $\Gamma$  on  $s$ .

$$\frac{d\Gamma}{ds} = \underline{u}(\Gamma, t)$$

This the streamline at  $t=t_0$ , are given by solving

$$\frac{d\Gamma}{ds} = \underline{u}(\Gamma, t_0)$$


Example: For our velocity field, what are the streamline at  $t=0$ ?

$$\frac{dx}{ds} = u(x, y, 0) = 1,$$

$$\frac{dy}{ds} = v(x, y, 0) = -2te^{-t^2} \Big|_{t=0} = 0.$$

$$\therefore y = \text{const}$$

$$x = s + x_0$$




\* At  $t=0$ ,  $\underline{u} = \underline{\xi}$ ; i.e.: The tangent to streamline does give the velocity field!

In a steady flow, all these are the same.

Steady:  $\frac{\partial \underline{u}}{\partial t} = 0$ . (Does not say  $\underline{u} = 0$ )

## 2. Conservation of Mass

Suppose a fluid of constant density  $\rho$  flows through a tube of cross-sectional area  $A$ . Suppose the fluid velocity is uniform and unidirectional of size  $V$  at each cross-section:



The amount of mass between the two stations is fixed.

In a time interval  $dt$  an amount

$$\rho A_1 V_1 dt$$

of mass crosses station 1.

The amount crossing  $A_2$  in time  $dt$  is:

$$\rho A_2 V_2 dt.$$

By conservation of mass, these are the same  
so  $A_1 V_1 = A_2 V_2$ .

### Flux


Or in terms of flux, the rate at which mass crosses  $A_1$  is:

$$\frac{\rho A_1 V_1 dt}{dt} = \rho A_1 V_1$$

This must equal the flux across  $A_2$  i.e

$$\rho A_2 V_2$$

The tube can be any surface that fluid does not cross



Streamtube is formed by taking a closed loop of particles and drawing the streamline

eminating from them. Flow cannot cross the tube as it is tangential to streamlines.


-/-

If area halves, speed doubles.

In 2D: - Because third velocity component,  $w=0$  streamlines compress only in xy plane so we have:

$$U_1 D_1 = U_2 D_2$$

where  $D$  is the distance between streamlines i.e. speed inversely proportional to the separation of the streamlines.




10/10/11

Theorem 1: If  $f$  is continuous in  $[a, b]$  and  $\int_c^d f = 0$  for each  $(c, d) \subset [a, b]$  then  $f = 0$  on  $[a, b]$ .

Proof: Suppose  $\exists x \in [a, b]$  st  $f(x) \neq 0$  w.l.o.g we can take  $f(x) > 0$ .

Write  $S = \frac{1}{2}f(x) > 0$ . Hence  $\exists \epsilon > 0$  st if  $x \in (x - \epsilon, x + \epsilon)$  then  $|f(x) - f(x)| < S = \frac{1}{2}f(x)$  i.e:  $0 < \frac{1}{2}f(x) < f(x) < \frac{3}{2}f(x)$ .



$$\text{Thus } \int_{x-\epsilon}^{x+\epsilon} f(x) dx > \int_{x-\epsilon}^{x+\epsilon} \frac{1}{2}f(x) dx$$

$$\begin{aligned} \text{RHS} &= 2\epsilon \frac{1}{2}f(x) \\ &= \epsilon f(x) > 0. \end{aligned}$$

But  $\int_c^d f = 0 \forall (c, d) \subset [a, b]$  so contradiction  
so  $\forall x$  i.e  $f \equiv 0$  in  $[a, b]$ .

This result extends immediately to n dimension

Ausatz: Suppose we wish to derive an equation  $f = 0$  for a fluid in 3D.


Let the fluid occupy a domain  $D$  in 3D.

Take an arbitrary subdomain  $V$  of  $D$   
 ↳ Terribly important

Show that  $\int_V f$  vanishes. Then  $f \equiv 0$  in  $D$  because  $V$  is arbitrary i.e.  $\int_V f = 0$  for every subdomain  $V$  of  $D$ .

### Conservation of Mass

Consider a fluid occupying a domain  $D$  with surface  $S$ .





Consider a small element  $dS$  of  $S$  with outward pointing unit normal  $\hat{n}$ .

Let the velocity field in  $D$  be  $\underline{u}$

Take the density of the fluid to be constant and equal to  $\rho$  everywhere.

Then in time  $\delta t \ll 1$ , an amount mass  $\rho(\underline{u} \cdot \hat{n}) dS \delta t$  crosses  $dS$ .





$$\text{Volume} = \text{Area of Base} \times \text{Height} \\ = ds' (\underline{u} \cdot \hat{n}) st.$$

Note that:  $(\underline{u} \cdot \hat{n}) st$  - component of  $\underline{u} st$  in the direction  $\hat{n}$  i.e height.

The total mass passing out of  $V$  is

$$\int_S \rho(\underline{u} \cdot \hat{n}) ds st = \rho st \int_S \underline{u} \cdot \hat{n} ds.$$

(  $\rho st \int_S \underline{u} \cdot \hat{n} ds$  = Outward mass flux across  $ds'$ . )

But to conserve mass in  $V$ , this must be zero, i.e  $\int_S \underline{u} \cdot \hat{n} ds = 0$ .

Divergence theorem says that  $\int_V \nabla \cdot \underline{u} dV = 0$

Thus we have, if subregions  $V$  of  $D$ ,  $\int_V \nabla \cdot \underline{u} dV = 0$

Thus by theorem 1  $\nabla \cdot \underline{u} = 0$  in  $D$ .

- - -

In  $2D$ : If  $\underline{u} = u(x, y) \hat{i} + v(x, y, t) \hat{j}$  then

$$\nabla \cdot \underline{u} = \frac{\partial u}{\partial x} + \frac{\partial v}{\partial y}$$


- - -

So, D  $\underline{u} = 7x\hat{i} - 5y\hat{j}$ . - Not incompressible!

$$\frac{\partial u}{\partial x} + \frac{\partial v}{\partial y} = 7 - 5 = 2 \neq 0.$$

i.e compressible (non-constant  $\rho$ )

In 3D :  $\frac{\partial u}{\partial x} + \frac{\partial v}{\partial y} + \frac{\partial w}{\partial z} = 0.$



$$\nabla \cdot \underline{u} = \frac{1}{r} \frac{\partial}{\partial r} (r u_r) + \frac{1}{r} \frac{\partial u_\theta}{\partial \theta}$$

Reminder : Green's lemma :



Consider a closed region  $A$  in the plane bounded by a curve  $C$ , taken counter-clockwise:

$$\int_A \left( \frac{\partial u}{\partial x} + \frac{\partial v}{\partial y} \right) dA = \int \text{line integral.}$$

where  $\underline{u} = u\hat{i} + v\hat{j}$ .

Thus in 2D, incompressible flow.

$$\oint_C u dy - v dx = 0.$$

for any closed curve  $C$ .  
—/—

Note:  $d\underline{r} = dx\hat{i} + dy\hat{j}$

Note:  $\underline{u} = u\hat{i} + v\hat{j}$ .

Consider the vector field:

$$\begin{aligned}\underline{F} &= -v\hat{i} + u\hat{j} \\ &= \hat{k} \wedge (u\hat{i} + v\hat{j}) \\ &= \hat{k} \wedge \underline{u}.\end{aligned}$$

i.e rotates  $\underline{u}$  by  $90^\circ$ .

Hence:  $\oint C \underline{F} \cdot d\underline{r} = 0$  for all closed vector field.

i.e  $\underline{F}$  is derivable from a potential.

i.e  $\exists \psi$  st  $\underline{F} = \nabla \psi$  i.e  $\hat{k} \wedge \underline{u} = \nabla \psi$

i.e  $\underline{u} = -k \wedge \nabla \psi$

—/—



13/10/11

Incompressibility (constant density)

$$\Rightarrow \nabla \cdot \underline{u} = 0 \quad [\Rightarrow \exists \underline{A} \text{ st } \underline{u} = \nabla \wedge \underline{A}]$$

— —

$$\text{In 2D: } \underline{u} = u(x, y) \hat{i} + v(x, y) \hat{j}$$


$$\nabla \cdot \underline{u} = \frac{\partial u}{\partial x} + \frac{\partial v}{\partial y}$$

$$\text{If } \frac{\partial u}{\partial x} + \frac{\partial v}{\partial y} = 0 \Rightarrow \exists \tau \text{ st } \underline{u} = -\hat{k} \wedge \nabla \tau = \hat{x} \tau \wedge \hat{k}.$$

— —

$$\text{First: } |\underline{u}| = |\nabla \tau|$$

$\nabla \tau$  is  $\perp^r$  to level arises or isolines of  $\tau$ .  
90 degrees to  $\tau$



$$c_3 > c_2 > c_1$$

Second:  $\underline{u}, \nabla \tau$  are  $\perp^r$  (both  $x, y$  plane). In fact  $\underline{u}$  is  $\nabla \tau$  rotated  $\pi/2$  clockwise.

Finally:  $\underline{u}$  is tangent to isoline  $\gamma = C$  for any  $C$ , i.e. isolines  $\gamma = C$  are streamlines, i.e. we have shown that incompressible flow  $\exists$  a function  $\gamma$  whose isoline are s'lines

— —

Example: Show that  $\underline{u} = x\hat{i} - y\hat{j}$  satisfies the continuity equation, find a streamline, sketch some s'lines (and suggest a flow).

Continuity equation:  $\frac{\partial u}{\partial x} + \frac{\partial v}{\partial y} = 0$

Hence  $u = x$ ,  $v = -y$ .

$$\Rightarrow \frac{\partial u}{\partial x} = 1, \quad \frac{\partial v}{\partial y} = -1$$

Thus  $\frac{\partial u}{\partial x} + \frac{\partial v}{\partial y} = 0$  as required.

Hence  $\exists \gamma$  st  $\underline{u} = -k \wedge \nabla \gamma$  (Note:  $\hat{k} \wedge \hat{i} = \hat{j}$ ,  $\hat{k} \wedge \hat{j} = \hat{i}$ )

So:  $\underline{u} = -k \wedge \nabla \gamma$

$$= \frac{\partial \gamma}{\partial y} \hat{i} - \frac{\partial \gamma}{\partial x} \hat{j}$$

$$= u\hat{i} + v\hat{j}$$

$$\Rightarrow u = \frac{\partial \psi}{\partial y} \quad \text{and} \quad v = -\frac{\partial \psi}{\partial x}$$

For this example  $u = x$ , thus  $\frac{\partial \psi}{\partial y} = x$ .

So  $\psi = xy + f(x)$  where  $f$  is an arbitrary function of  $x$ .

This implies :  $\frac{\partial \psi}{\partial x} = y + f'(x)$ .

$$\text{But } \frac{\partial \psi}{\partial x} = -v = f'(x)$$


Comparing gives  $f'(x) = 0$  i.e  $f$  is constant w.l.o.g we can take the function  $f = 0$ .

[w.l.o.g since  $u = -k \Delta \psi$ , so adding a constant to  $\psi$  does not change  $u$ ]

$\psi$  is unique to within an additive constant, hence the streamfunction  $\psi$  is

$$\psi = xy.$$

Streamlines; the lines  $\psi = \text{constant}$  i.e  $xy = c$ . (Rectangular hyperbola)




or  $u = x$ , so if  $x > 0, u > 0$ .

Since  $|u| = |\nabla \phi|$ , speed is directly proportional to  $|\nabla \phi|$  or equivalently  $|u|$  is inversely proportional to the separation of lines of  $\phi$ .

There is stagnation point flow as the origin is a stagnation point where  $u = 0$ .

This flow could be 2 colliding jets of equal strength can be an example of this flow.

Flow condition at a solid boundary



Solid  $\Rightarrow$  impermeable  
i.e. no flow through the boundary.

The mass of fluid passing through  $dS$  in time  $dt$  is:

$$\rho(\underline{u} \cdot \hat{n}) dS dt$$

or there is a mass flux (rate at which mass crosses  $dS$ )

For no mass,  $\underline{u} \cdot \hat{n} = 0$  on  $S$ . On a solid boundary:  $\underline{u} \cdot \hat{n} = 0$  i.e. velocity is tangential to surface.

[If the fluid is also viscous, additionally the tangential component to  $\underline{u}$  vanishes also so  $\underline{u} = 0$  on a solid boundary.]


$\rightarrow$  Stokes  $\leftarrow$  (Real fluids) } Aside for 3<sup>rd</sup> year course

In terms of the S'fu:

$$\hat{n} \cdot \underline{u} = -\hat{n} \cdot (\hat{k} \wedge \nabla \psi)$$

$$= -(\hat{n} \wedge \hat{k}) \cdot \nabla \psi$$

$$= -\frac{\partial \psi}{\partial s} \quad \begin{matrix} \text{along the surface} \\ \text{(direction derivative)} \end{matrix}$$




$\hat{n}$  - unit tangent surface

But  $\underline{u} \cdot \hat{n} = 0$ , so  $\frac{\partial \psi}{\partial s} = 0$  along a solid boundary  
 i.e.  $\psi = \text{constant}$  on solid bdry.

Equivalently any line  $t$  constant has  $\underline{u}$  tangential, i.e. can be a solid bdy i.e. on a solid boundary,  $\psi = \text{const}$ . Any line  $t = \text{constant}$  can be replaced by solid bdy without affecting an inviscid flow.

Solid bdy:  $\underline{u} \cdot \hat{n} = 0$  or  $\psi = \text{constant}$ .


Ex:  $u = x$ ,  $v = -y$ ,  $\psi = xy$  (<sup>w/o</sup>-without)



Replace any s'line by solid boundary (in inviscid flow) w/o changing flow.

Here we obtain a jet hitting a wall - stagnation point flow.

e.g.: Front and rear stagnation points in uniform flow past a circular cylinder:



F.S.T - Front stagnation point.

R.S.T - Rear stagnation point.

Ex 2 : (Same question in ex. 1.)


$$\text{Now } u = 2y, v = 2x$$

$$\text{Thus } \frac{\partial \psi}{\partial y} = u = 2y.$$

$$\text{So } \psi = y^2 + f(x)$$

$$\text{So } \frac{\partial \psi}{\partial x} = f'(x). \Rightarrow \psi = x^2 + y^2$$

i.e. circles centre O radius a :



i.e saucepan or beaker on a turntable.

Rotating as a solid body;  $u = -2\hat{k} \propto r$ , where


$$\psi = r^2, \quad r = \sqrt{x^2 + y^2}.$$

---

Reds in cylindrical polar co-ords.

$\underline{u} = -k \wedge \nabla \psi \Leftarrow$  co-ordinates free.

$$\nabla \psi = \frac{\partial \psi}{\partial r} \hat{r} + \frac{1}{r} \frac{\partial \psi}{\partial \theta} \hat{\theta}.$$



$$\hat{k} \wedge \hat{r} = \hat{\theta}$$

$$\hat{k} \wedge \hat{\theta} = \hat{r}$$

$$\underline{u} = -\hat{k} \wedge \nabla \psi$$

$$= -\frac{\partial \psi}{\partial r} \hat{\theta} + \frac{1}{r} \frac{\partial \psi}{\partial \theta} \hat{r}$$


Comparing:

$$u_r = \frac{1}{r} \frac{\partial \psi}{\partial \theta}, \quad u_\theta = -\frac{\partial \psi}{\partial r}$$

Worth remembering

We have  $\psi = r^2$  in our example.

Thus,  $u_r = \frac{1}{r} \frac{\partial \psi}{\partial \theta} = 0$ .




and  $u_0 = -\frac{\partial \psi}{\partial r} = -2r$ .


Velocity increasing with  $r$

A physical interpretation of the stream function. The volume flux in a clockwise direction across any line joining a point P to a point Q in a flow field is given by:

$$\psi(Q) - \psi(P)$$



[c.f work done is independent of path]



Hence try:  $\underline{n} = dy \hat{i} - dx \hat{j}$  so  $\underline{n} \cdot dr = 0$

Normal vector but not unit normal vector.

Volume flux crossing a length  $dS$ .

$$\int_P^Q (\underline{u} \cdot \hat{\underline{n}}) dS.$$

$$\begin{aligned} \text{Thus : } \hat{\underline{n}} &= \frac{dy \hat{i} - dx \hat{j}}{\sqrt{dx^2 + dy^2}} \\ &= \frac{dy}{ds} \hat{i} - \frac{dx}{ds} \hat{j} \end{aligned}$$


Thus total flux crossing line P and Q in clockwise direction is :

$$\begin{aligned} &\int_P^Q (\underline{u} \cdot \hat{\underline{n}}) dS' \\ &= \int_P^Q \left( \frac{\partial \Psi}{\partial y} \hat{i} - \frac{\partial \Psi}{\partial x} \hat{j} \right) \cdot \left( \frac{dy}{ds} \hat{i} - \frac{dx}{ds} \hat{j} \right) ds' \\ &= \int_P^Q \left( \frac{\partial \Psi}{\partial x} \frac{dx}{ds} + \frac{\partial \Psi}{\partial y} \frac{dy}{ds} \right) ds' \\ &= \int_P^Q \frac{d\Psi}{ds} ds' \\ &= \Psi(Q) - \Psi(P). \end{aligned}$$



Aside : On  $(x, y)$ .

$\frac{d}{ds} (\chi(x(s), y(s)))$   
 $= \frac{\partial \chi}{\partial x} \frac{dx}{ds} + \frac{\partial \chi}{\partial y} \frac{dy}{ds}$  via chain rule.

On 1 boundary :



On 2 boundaries :



-/-

What are the dimensions of  $\tau$ ?

Volume / Unit time per unit width.

$$L^3 T^{-1} L^{-1}$$

i.e.  $L^2 T^{-1}$  i.e. an area flux.

-(-)

17/10/11


$$\text{Vorticity} : \underline{\omega} = \nabla \times \underline{u}$$

### Example of streamfunction

1. Perhaps the simplest flow is a uniform stream.



W.l.o.g take the  $x$ -axis in the direction of the flow



Then  $u = U$ ,  $v = 0$ , so

$$\frac{\partial \psi}{\partial y} = u = U$$

$$\text{So } \psi = Uy + f(x)$$


$$\text{So : } \frac{\partial \psi}{\partial x} = f'(x)$$

$$\text{But } \frac{\partial \psi}{\partial x} = -v = 0$$

$$\text{So } f'(x) = 0$$

Hence we can take  $f = 0$ .

$$\text{So } \psi = Uy.$$



Flux across  $x=0$  is  $2U$  i.e. Length  $\times$  Speed.

Flux across PQ must also be  $2U$  because:

- 1) No fluid escapes across  $y=0$  as they are streamlines (and so no normal flow i.e. could replace by solid bdry)

OR

$$2) \text{ Flux} = \psi(Q) - \psi(P) = 2U - 0 = 2U.$$

2. Another example of stream function:


Iso tropic source - this has stream-function:

$$\psi = m\theta.$$

This gives:  $\underline{u} = u_r \hat{r} + u_\theta \hat{\theta}$  where


$$u_r = \frac{1}{r} \frac{\partial \psi}{\partial \theta}, \quad u_\theta = -\frac{\partial \psi}{\partial r}$$

Hence:  $u_r = \frac{m}{r}, \quad u_\theta = 0.$



The velocity field is the same in all direction i.e independent of  $\theta$  i.e it is isotropic.


Now consider any circuit containing the origin:



the flux of  $C$  is going around any closed curve containing the origin  $O$  increases by  $2\pi$ . So  $\Phi(Q) - \Phi(P) = m(\theta(Q) - \theta(P)) = 2\pi m$ .

-/-

If



$$\text{Speed} = u/a$$

$$\text{Length} = 2\pi a$$


$$\begin{aligned}\text{Flux} &= 2\pi a(u/a) \\ &= 2\pi u.\end{aligned}$$

The flux is independent of  $a$ .

$$\underline{u} \cdot \hat{\underline{n}} = \underline{u} \cdot \hat{\underline{l}} = u_r = \frac{u}{a}.$$

-/-

If curve does not circle the origin:



$\theta(P) = \theta(Q) \Rightarrow \text{Flux} = 0$  i.e. no net flux across  $C$ .

[ $m$  = rate at which fluid is created i.e: strength of the source].

By taking successive smaller circles we see that only at the origin fluid is created and it is created there at a volume flux  $2\pi m$ . We call  $2\pi m$  the strength of the source i.e a source of strength  $m$  has  $\Phi = \frac{m\theta}{2\pi}$ .

In this case the strength is  $m$ .

If  $U_r = \frac{m}{2\pi r}$  singular at the origin but well behaved everywhere else.

If  $\Phi = m\theta$ , strength =  $2\pi m$

If  $\Phi = \frac{m}{2\pi}r\theta$ , strength =  $2\pi m/2\pi$


If  $\Phi = 4\theta$ , strength =  $4\pi m$

3) Example of another streamfunction :

Combine these: i.e an isotropic source of strength  $2\pi m$  in a uniform stream of speed  $U$ .


Take x-axis in direction of stream

Take origin at the source.



Notice:

- Source dominates at origin (for  $r$  sufficiently small).
- Stream dominates if  $r$  sufficiently large,  $u_r = \frac{m}{r}$



$$\chi = U_y + m\theta.$$


Stagnation point: If  $\underline{u} = 0 \Rightarrow u_\theta = 0$   
 $\Rightarrow \frac{\partial \chi}{\partial r} = 0$  and  $u_r = 0 \Rightarrow \frac{\partial \chi}{\partial \theta} = 0$ .

$$\text{Flux} = \text{Width} \times \text{Speed} = 2w \times U = 2\pi m$$

So  $w = \frac{\pi m}{U}$

20/10/10

## 2. Local motion at a point



Consider the initially square element  $ABCD$  with  $0 < h \ll 1$ .

Consider motion in the time interval  $0 < st \ll 1$  so that the flow is effectively steady.

Reminder: Taylor's theorem:

$$f(x) = f(0) + x f'(0) + R_2$$

$$R_2 = \frac{1}{2} f''(s)x^2 \quad \text{for } s \in (0, x)$$

i.e.  $f(x) = a + bx$  plus an error of order  $x^2$  where  $a = f(0)$ ,  $b = f'(0)$

What is the effect of an arbitrary, incompressible velocity field  $\mathbf{u}(x, y, t)$  do to our infinitesimal element?

From Taylor's theorem (in 2D)

$$\begin{aligned} u &= U + \alpha x + \beta y \\ v &= V + \gamma x + \delta y \end{aligned} \quad \left. \begin{array}{l} \text{with error over } ABCD \\ \text{of order } h^2 \end{array} \right\}$$

where:  $U = u(0,0)$ ,  $\alpha = \frac{\partial u}{\partial x}(0,0)$ ,  $\beta = \frac{\partial u}{\partial y}(0,0)$

where:  $V = v(0,0)$ ,  $\gamma = \frac{\partial v}{\partial x}(0,0)$ ,  $\delta = \frac{\partial v}{\partial y}(0,0)$

Now  $u$  is incompressible, so  $\frac{\partial u}{\partial x} + \frac{\partial v}{\partial y} = 0$ .  
everywhere

In particular  $\alpha + \delta = 0$ .

Useful to write:

$$\begin{aligned} \beta &= \theta - \phi \\ \gamma &= \theta + \phi. \end{aligned}$$

Then  $\theta = \frac{1}{2}(\gamma + \beta)$ ,  $\phi = \frac{1}{2}(\gamma - \beta)$

$$\Rightarrow \theta = \frac{1}{2}\left(\frac{\partial v}{\partial x} + \frac{\partial u}{\partial y}\right), \quad \phi = \frac{1}{2}\left(\frac{\partial v}{\partial x} - \frac{\partial u}{\partial y}\right)$$

Now:

$$\begin{pmatrix} u \\ v \end{pmatrix} = \begin{pmatrix} U \\ V \end{pmatrix} + \begin{pmatrix} \alpha & \beta \\ \gamma & \delta \end{pmatrix} \begin{pmatrix} x \\ y \end{pmatrix}$$

In time  $St$ , a point  $(\vec{x})$  within  $ABCD$   
moves by an amount:


$$\begin{pmatrix} s_x \\ s_y \end{pmatrix} = \begin{pmatrix} u \\ v \end{pmatrix} dt$$

$$= \begin{pmatrix} u \\ v \end{pmatrix} dt + \begin{pmatrix} \alpha & \beta \\ \gamma & \delta \end{pmatrix} \begin{pmatrix} x \\ y \end{pmatrix} dt.$$

i.e :


$$\begin{pmatrix} s_x \\ s_y \end{pmatrix} = \begin{pmatrix} u \\ v \end{pmatrix} dt + \left[ \alpha \begin{pmatrix} 1 & 0 \\ 0 & 1 \end{pmatrix} + \beta \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix} + \gamma \begin{pmatrix} 0 & -1 \\ 1 & 0 \end{pmatrix} \right] \begin{pmatrix} x \\ y \end{pmatrix} dt.$$

Term I : This term simply moves every point at speed  $\begin{pmatrix} u \\ v \end{pmatrix}$



Translation of the centre of mass (at speed  $u, v$ )

Term II :



this moves A by:

$$\begin{pmatrix} \delta x \\ \delta y \end{pmatrix} = \alpha \begin{pmatrix} 1 & 0 \\ 0 & -1 \end{pmatrix} \begin{pmatrix} h \\ 0 \end{pmatrix} dt$$
$$= \begin{pmatrix} \alpha h dt \\ 0 \end{pmatrix}$$

Thus C moves by:

$$\begin{pmatrix} \delta x \\ \delta y \end{pmatrix} = \begin{pmatrix} -\alpha h dt \\ 0 \end{pmatrix}$$

At B:  $\begin{pmatrix} \delta x \\ \delta y \end{pmatrix} = \alpha \begin{pmatrix} 1 & 0 \\ 0 & -1 \end{pmatrix} \begin{pmatrix} 0 \\ h \end{pmatrix} dt$

$$= \begin{pmatrix} 0 \\ -\alpha h dt \end{pmatrix}$$

i.e. downwards exactly the same amount as A moves out.

At D:  $\begin{pmatrix} \delta x \\ \delta y \end{pmatrix} = \begin{pmatrix} 0 \\ \alpha h dt \end{pmatrix}$

Thus Term II stretches the square at a rate  $\alpha h$  in the x-direction and shrinks it at the same rate  $\alpha h$  in the y-direction, without moving the centre of mass, conserving volume as expected - a DILATION!

Note: A stretching in one direction and shrinking in the orthogonal direction (in 2D) at the same rate so as to conserve volume.


Term III :

$$\text{At } A, \begin{pmatrix} s_x \\ s_y \end{pmatrix} = \begin{pmatrix} 0 \\ \text{ohft} \end{pmatrix}$$

$$\text{At } C, \begin{pmatrix} s_x \\ s_y \end{pmatrix} = \begin{pmatrix} 0 \\ -\text{ohft} \end{pmatrix}$$

$$\text{At } B, \begin{pmatrix} s_x \\ s_y \end{pmatrix} = \begin{pmatrix} \text{ohft} \\ 0 \end{pmatrix}$$

$$\text{At } D, \begin{pmatrix} s_x \\ s_y \end{pmatrix} = \begin{pmatrix} -\text{ohft} \\ 0 \end{pmatrix}$$



i.e. another DILATION: stretching along line  $y = -x$ , both a rate  $\text{oh}$ , so as to preserve volume.

-/-

It appears that there are 2 DILATIONS. Term II and Term III. This is not so.

The combine effect of term II + III is the matrix:

$$\begin{pmatrix} \alpha & 0 \\ 0 & -\alpha \end{pmatrix}$$

This is a real symmetric matrix:

It possesses 2 real eigenvalues:

$$\begin{vmatrix} \alpha - \lambda & 0 \\ 0 & -\alpha - \lambda \end{vmatrix} = 0$$

$$\Rightarrow -(\alpha - \lambda)(\alpha - \lambda) - 0^2 = 0$$

$$\Rightarrow -\alpha^2 + \lambda - 0^2 = 0$$

$$\Rightarrow \lambda^2 = \alpha^2 + 0^2$$

Hence we have 2 equal and opposite eigenvalues

$$\lambda = \pm \sqrt{\alpha^2 + 0^2}$$

with eigenvectors  $\xi_1$  and  $\xi_2$  (say)

In the basis  $\xi_1, \xi_2$  the matrix has the form

$$\begin{pmatrix} \lambda_1 & 0 \\ 0 & -\lambda_1 \end{pmatrix}$$

Precisely the form of term III.

Thus expansion at rate  $\lambda_1$  along  $\xi_1$ , and  
and a contraction at rate  $\lambda_2$  along the  
orthogonal  $\xi_2$  i.e a DILATION

i.e sum of 2 DILATION

-/-



24/10/11

A Summary of what is done so far:

1)  $\underline{u}(x, y, z, t)$

2) Particles, Path, Streamlines, Streamlines

3) Incompressibility  $\Rightarrow \nabla \cdot \underline{u} = 0$  (in 3D)

4) Incompressibility + 2D  $\Rightarrow \underline{u} = u(x, y, t) \hat{i} + v(x, y, t) \hat{j} = u_r(r, \theta, t) \hat{e}_r + u_\theta(r, \theta, t) \hat{e}_\theta$ .

$\nabla \cdot \underline{u} = 0$  and in 2D  $\Rightarrow \frac{\partial u}{\partial x} + \frac{\partial v}{\partial y} = 0$

$\Rightarrow \exists \psi$  st  $\underline{u} = -\hat{k} \times \nabla \psi$  i.e


$$u = \frac{\partial \psi}{\partial y}, \quad v = -\frac{\partial \psi}{\partial x}$$

$$\text{or } u_r = \frac{1}{r} \frac{\partial \psi}{\partial \theta}, \quad u_\theta = -\frac{\partial \psi}{\partial r}$$

5) Local motion at a point - consists of a translation of centre of mass, a dilation, and ...

$$\begin{pmatrix} u \\ v \end{pmatrix} = \begin{pmatrix} 0 \\ 0 \end{pmatrix} + \left[ \underbrace{\begin{pmatrix} 1 & 0 \\ 0 & 1 \end{pmatrix} \alpha + \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix} \theta + \begin{pmatrix} 0 & -1 \\ 1 & 0 \end{pmatrix} \phi}_{(*)} \right] \begin{pmatrix} x \\ y \end{pmatrix}$$

Considering  $(*) \Rightarrow \begin{pmatrix} \alpha & \theta \\ 0 & -\alpha \end{pmatrix}$ , eigenvectors:  $\{\xi_1, \xi_2, \xi_1 \perp \xi_2\}$



Term IV:

A moves by an amount :

$$\begin{pmatrix} \delta x \\ \delta y \end{pmatrix} = \begin{pmatrix} u \\ v \end{pmatrix} dt$$

At B:

$$\begin{pmatrix} \delta x \\ \delta y \end{pmatrix} = \phi \begin{pmatrix} -h \\ o \end{pmatrix} dt.$$

Term IV contribute of A :


$$\phi \begin{pmatrix} o \\ h \end{pmatrix} dt$$

At A the radial arms have length h.

Point moved up distance  $\phi h dt$

Hence moved through an angle  $\phi dt$

i.e ABCD is rotating at a rate  $\phi$  in the anti-clockwise direction.



i.e. at a rate  $\frac{1}{2} \left( \frac{\partial u}{\partial x} - \frac{\partial u}{\partial y} \right)$  in the anti-clockwise direction.

— —

thus we have shown that motion at a point consist of 3 and only 3 things:

• Translation of C of M, a dilation, and a rotation about the C of M. [Notice for a solid : as above but no dilation].

— —

Notice:  $\frac{\partial u}{\partial x} - \frac{\partial u}{\partial y}$  is precisely the Z-component of  $\nabla \times \underline{u}$  i.e. curl  $\underline{u}$ .

It is traditional to write

$$\underline{\omega} = \nabla \times \underline{u}$$

Omega.

$\underline{\omega}$  is the vorticity of the flow i.e. rotation of the flow. [old name curl  $\underline{u}$  was rot  $\underline{u}$ ]

The component of  $\underline{\omega}$  usually written:

$$\underline{\omega} = \zeta \hat{i} + \eta \hat{j} + \zeta \hat{k}$$

(x<sub>i</sub>)      (eta)      (zeta)

In 2D,  $\underline{u} = u(x, y, t) \hat{i} + v(x, y, t) \hat{j}$ .

$$\underline{w} = \omega \hat{i} + 0 \hat{j} + \zeta \hat{k}$$

i.e  $\underline{w}$  is solely in  $z$ -direction with

$$w = \zeta \hat{k} \text{ and } z = \frac{\partial v}{\partial x} - \frac{\partial u}{\partial y}$$

and it gives twice the rate of rotation of a fluid element about its C of M [ $\phi = \frac{1}{2} \zeta$ ]  
i.e  $\zeta$  is proportional to the angular momentum of a fluid element its C of M.



We can only change the rate at which a fluid element is spinning (in 2D) by applying a torque i.e shear stress

But an inviscid fluid does not support a shear stress, so we cannot (in 2D) change the rate at which a fluid element spins, i.e a particle in 2D inviscid fluid retains its values of  $\zeta$  forever.



At  $t=0$

At  $t>0$

Consider a flow started from rest. Then initially  $\zeta = 0$  ( $\omega = 0$  at  $t = 0$ ) i.e every particle has vorticity zero.


Hence for all time, all particle have zero vorticity.

A number where  $\omega = 0$  everywhere is called IRRATIONAL, e.g any flow started from rest is irrotational. — the persistence of irrotationality ( $\zeta \equiv 0$ ).

$\nwarrow$  True in 3D - nothing to amplify.

-/-

Aside: In 3D:  $\omega \neq 0$ ,  $\frac{\partial}{\partial z} \neq 0$ .



$\Rightarrow \zeta$  increased


e.g: Hurricane  
Amplifier

Hurricane: Why in tropics not equator?

Why not at poles, northern oceans?

Why spin?

$\rightarrow$  Isaac Held



Heat Engine.

-/-

Thus we will concentrate on IRRATIONAL flow.

Then  $\nabla \cdot \underline{u} = 0$ .

Hence  $\exists \phi$  st  $\underline{u} = \nabla \phi$  i.e.  $\underline{u}$  is derivable from a potential, the velocity potential. (we are still in 2D or 3D).

In incompressible flow in 2D or 3D,  $\nabla \cdot \underline{u} = 0$ .

Substituting gives :

$$\nabla \cdot (\nabla \phi) = 0$$

i.e  $\nabla^2 \phi = 0$  .



Laplace's equation 2D and 3D.

The governing equation for 3D incompressible, irrotational flow.

All we need are boundary conditions.

On a solid boundary  $\underline{u} \cdot \hat{\underline{n}} = 0$ .

Substitute for  $\underline{u} = \nabla \phi$ ,  $\hat{\underline{n}} \cdot \nabla \phi = 0$  on a solid bdy i.e  $\frac{\partial \phi}{\partial n} = 0$  on a solid bdy.

i.e the normal derivatives of  $\phi$  vanishes on a solid bdy.

(The solution to Laplace's eqn with  $\frac{\partial \phi}{\partial n}$  specified in boundary i.e. Newman problem, is unique)

-/-

Example: What is velocity potential for a uniform stream?

Take x-axis in direction of stream.

$$u = U \hat{i} \text{ so } u = U, v = 0$$

$$\text{But } u = \nabla \phi = \frac{\partial \phi}{\partial x} \hat{i} + \frac{\partial \phi}{\partial y} \hat{j}$$

$$\text{So } u = \frac{\partial \phi}{\partial x}, v = \frac{\partial \phi}{\partial y}$$

$$\text{Hence } \frac{\partial \phi}{\partial x} = U.$$

$$\text{So } \phi = Ux + f(y)$$

$$\text{So } \frac{\partial \phi}{\partial y} = f'(y).$$

$$\text{But } \frac{\partial \phi}{\partial y} = v \text{ and } v = 0.$$


$$\text{So } f'(y) = 0$$

So  $f$  is constant.

Take  $f = 0$ .

$$\phi = U_x.$$

(Notice: satisfies Laplace's eqn).



equipotentials,  $\phi = \text{constant}$   
 $x = \text{const}$  here.

	Grooved	Bad
$\phi$ :	3D	Only irrotational
$\psi$ :	Does not require irrotationality	Only 2D.

What does  $\psi$  satisfy? (in 2D, irrotational flow).

$$2D: u = \frac{\partial \psi}{\partial y}, \quad v = -\frac{\partial \psi}{\partial x}$$

Irrot 2D :  $\zeta = 0$  ;

$$\frac{\partial v}{\partial x} - \frac{\partial u}{\partial y} = 0$$

Substituting :

$$\frac{\partial}{\partial x} \left( -\frac{\partial \psi}{\partial x} \right) - \frac{\partial}{\partial y} \left( \frac{\partial \psi}{\partial y} \right) = 0$$

$$\text{i.e } \frac{\partial^2 \psi}{\partial x^2} + \frac{\partial^2 \psi}{\partial y^2} = 0$$

$$\text{i.e } \nabla^2 \psi = 0$$

i.e if  $\psi$  satisfies Laplace's eqn also :

Remember the b.c. on a solid boundary for  $\psi$  is  $\psi = \text{constant}$  which is taken as  $\psi = 0$  if  $\psi$  only one boundary.

Check :

Uniform stream :  $\psi = Vy$  so  $\nabla^2 \psi = 0$ .

Stagnation point :  $\psi = xy$  so  $\nabla^2 \psi = 0$ .

If flow is 2D and irrotational, then you can choose to find  $\phi$  or  $\psi$ .

- whichever seem easier

- governing eqn is the same : Laplace .


- boundary conditions different.

Are  $\phi$  and  $\psi$  related ?

Yes! of course

$\underline{u} = \nabla \phi$  and  $\underline{u} = -\hat{k} \wedge \nabla \psi$ .

So  $\nabla \phi = -\hat{k} \wedge \nabla \psi$  } very famous. } Cauchy-Riemann  
 or  $\nabla \psi = \hat{k} \wedge \nabla \phi$  } eqns. without co-ordinates



Cauchy-Riemann equations:

$$u = \frac{\partial \phi}{\partial x} \quad \text{and} \quad u = \frac{\partial \psi}{\partial y}$$

$$\text{so} \quad \frac{\partial \phi}{\partial x} = \frac{\partial \psi}{\partial y}.$$

$$v = \frac{\partial \phi}{\partial y} \quad \text{and} \quad v = -\frac{\partial \psi}{\partial x}$$

$$\text{so} \quad \frac{\partial \phi}{\partial y} = -\frac{\partial \psi}{\partial x}.$$

In 2D, irrotational flow:

$$\frac{\partial \phi}{\partial x} = \frac{\partial \psi}{\partial y} \quad \text{and} \quad \frac{\partial \phi}{\partial y} = -\frac{\partial \psi}{\partial x}$$

the Cauchy-Riemann equations.

In polar form:

$$\underline{u} = \nabla \phi = \frac{\partial \phi}{\partial r} \hat{r} + \frac{1}{r} \frac{\partial \phi}{\partial \theta} \hat{\theta}$$

thus:  $\frac{\partial \phi}{\partial r} = \frac{1}{r} \frac{\partial \psi}{\partial \theta}$ ,  $\frac{1}{r} \frac{\partial \phi}{\partial \theta} = -\frac{\partial \psi}{\partial r}$

thus  $\phi$  and  $\psi$  are the real and imaginary parts of a differentiable complex function of the complex variable  $z = x + iy$ .

Traditionally this is called the COMPLEX VELOCITY POTENTIAL and written

$$w(z) = \phi(x, y, t) + i\psi(x, y, t)$$

lower case

$t$   $\sqrt{t}$

$$\text{where: } z = x + iy$$

$$\phi = \operatorname{Re}\{w(z)\}$$

$$\psi = \operatorname{Im}\{w(z)\}$$

Poised:

1) Real + Imag parts of a complex differentiable function, satisfy Laplace's eqn.

2) Constant surfaces intersect at right angles.

-/-

Check : Uniform stream :

$$\phi = U_x$$

$$\psi = U_y$$

$$\phi + i\psi = U(x+iy) = Uz \text{ (a function of } z \text{ alone).}$$

So  $w = Uz$  is the complex potential for a uniform stream.

Given  $w(z)$  how do we get  $\underline{u}$ ?

Consider

$$\frac{dw}{dz} = \frac{\partial}{\partial z} (\phi + i\psi) = \frac{\partial \phi}{\partial x} + i \frac{\partial \psi}{\partial x}$$
$$= u - iv.$$

So  $u + iv = \overline{\frac{\partial w}{\partial z}}$  bar = conjugate?

Eg:  
1) for  $w(z) = Uz$

$$\Rightarrow \frac{dw}{dz} = U$$
$$= u - iv.$$

So  $u = V$  and  $v = 0$  as expected.

2)  $w(z) = z^2$


$$\frac{dw}{dz} = 2z = 2x + iy$$

So  $u = 2x$ ,  $v = -2y$

$u = 0, v = 0$  only if  $z = 0$  (where  $\frac{dw}{dz} = 0$ )  
i.e. a stagnation point if and only if  $\frac{dw}{dz} = 0$   
Here only at  $z = 0$ .

$$w = z^2 = (x+iy)^2 = x^2 - y^2 + 2ixy$$

So  $\phi = x^2 - y^2$ ,  $\psi = 2xy$ .





27/10/11

Summary:

Irrotational:  $\nabla \cdot \underline{u} = 0 \Rightarrow \exists \underline{u} = \nabla \phi$

Incompressibility:  $\nabla \cdot \underline{u} = 0$  plus 2D:

$$\frac{\partial u}{\partial x} + \frac{\partial v}{\partial y} = 0.$$

i.e.  $\nabla \phi = -k \wedge \nabla \psi$  (Cauchy-Riemann)

$\Rightarrow \exists w(z)$  s.t.  $\frac{dw}{dz}$  exist and  $w = \phi + i\psi$ .


$$\frac{dw}{dz} = u - iv.$$

-/-

### Laurent Series

A function analytic or holomorphic within an annular region:  $R_0 < |z| < R_1$  has a unique expansion of the form:

$$\dots + \frac{a_r}{z^r} + \frac{a_1}{z} + a_0 + a_1 z + a_2 z^2 + \dots$$



i.e. all functions analytic in the annulus are simply linear combination of  $z^{\pm n}$ ,  $n = 0, 1, 2, 3, 4, \dots$

Apply this to the complex velocity  $u - iv$   
i.e.  $u - iv$  is a linear combination of  
 $z^{\pm n}$

These  $w(z)$ , the complex potential is simply a linear combination of the term:  $z^{\pm n}$   $n=0, 1, \dots$  and  $\log z$ .

i.e. over flow in any annular region (or a region that can be distorted into an annulus, or outside a single body (let  $R_1 \rightarrow \infty$ ) is simply a linear combination of the terms chosen from:

$$\{z^{\pm n}, \log z\}$$

Note that the coefficients in the sum can be complex.

In particular, in cylindrical coordinates

$$z = r e^{i\theta}$$

$$\begin{aligned} \text{So } z^n &= r^n e^{in\theta} \\ &= r^n \cos(n\theta) + i \sin(n\theta) \end{aligned}$$

$$\text{And } \log z = \underline{\log r} + i\underline{\theta}.$$

Now  $\phi = \operatorname{Re} w$  so  $\phi$  must be a linear combination of the terms drawn from the set:

$$\{r^n \cos(n\theta), r^n \sin(n\theta), (n=0, \pm 1, \pm 2, \dots), \log r, \theta\}.$$


Thus all solution (in an annular domain) of Laplace's eqn in polar co-ords are simply a linear combination of the terms,  $r^{\pm n} \cos(n\theta)$ ,  $r^{\pm n} \sin(n\theta)$ ,  $\log r$ ,  $\theta$ .

Similarly  $\Phi(x, y) = \operatorname{Im}(z)$  is only a linear combination of terms drawn from the set:

$$\{r^n \cos(n\theta), r^n \sin(n\theta), (n=0, \pm 1, \pm 2, \dots), \log r, \theta\}.$$

Example: Find the ideal (inviscid + incomp) 2D flow past a cylinder of radius  $a$  given that the flow at infinity is uniform with speed  $U$ .

Solution: Take Cartesian axes with  $Ox$  in direction of flow at infinity and origin of centre of cylinder.



Can solve either with  $\Phi$  or  $\Psi$ .

Choose  $\psi$  simply so we can draw some straight lines

Governing equations:  $\nabla^2 \psi = 0$  in  $r > a$ .

On the cylinder  $r = a$ , there is no flow through cylinder, recall that  $(\underline{u} \cdot \hat{\underline{n}} = 0)$  on boundary.

Therefore take:  $\psi = \text{const}$  at  $r = a$ .

But there is only one boundary so make  $\psi = 0$  on  $r = a$ .

As  $r \rightarrow \infty$   $\underline{u} \rightarrow \underline{U} \hat{\underline{z}}$ .

i.e.  $u \rightarrow U$ ,  $v \rightarrow 0$ .

i.e.  $\frac{\partial \psi}{\partial y} \rightarrow 0$  so  $\psi \rightarrow Uy + f(x)$

i.e.  $\frac{\partial \psi}{\partial x} \rightarrow f'(x)$ .

But  $\frac{\partial \psi}{\partial x} \rightarrow 0$

So  $f' = 0$  w.l.o.g  $f = 0$ .

Hence  $\psi \rightarrow Uy$  as  $r \rightarrow \infty$ .

Summary:

$\nabla^2 \psi = 0$        $r \rightarrow \infty$  a homogeneous ( $\psi = 0$  is a solution).

$\psi = 0$        $r = a$  a homogeneous ( $\psi = 0$  is a solution).

$\psi \rightarrow Ur \sin \theta$        $r \rightarrow \infty$  inhomogeneous ( $\psi \neq 0$  is not a solution).

Inhomogeneous b.c. says:

$\psi \rightarrow Ur \sin \theta$  as  $r \rightarrow \infty$ .  
from our set

Guess:

$$\psi = Ur \sin \theta + ar^5 \cos(3\theta) + br^3 \cos(3\theta)$$

( $n=1$ ) from our set      Not sol<sup>"</sup> to replace      Violates  $r \rightarrow \infty$

$$+ \frac{c}{r^3} \cos(3\theta) + \frac{B}{r} \sin \theta.$$

( $n=-1$ ) from our set  
cannot balance  $\sin \theta$  for even  $\theta$   
on  $r=a$



$$\leftarrow \psi = 0 \text{ on } r=a$$

$\theta$ .

So on  $r=a$


$$\psi = U a \sin \theta + \frac{B}{a} \sin \theta.$$

This is true for all  $\theta$  so:

$$U_a + \frac{B}{a} = 0 \quad \text{i.e. } B = -U_a a^2.$$

$$\text{i.e. } \psi = U_y + \left(1 - \frac{a^2}{r^2}\right)$$

$\psi = 0$  when  $y = 0$  and  $r = a$  as expected




Hence:

$$\psi = Ur \sin \theta - \frac{Ua^2}{r} \sin \theta.$$

$$\psi = Ur \sin \theta \left[ 1 - \frac{a^2}{r^2} \right]$$

31/10/11

Recall:



$$\tau = U_y \left( 1 - \frac{a^2}{r^2} \right)$$

$$= U_y - \frac{U a^2 y}{r^2}$$

Note that:

$$\frac{U a^2 y}{r^2} = \frac{U a^2 y \bar{z}}{|z|^2}$$

$$w(z) = U_z + \frac{U a^2}{z} \quad || w(z) \text{ comes from the set: } \{ z^{in}, \log z \}$$


$$\text{So } \tau = \operatorname{Im} \left[ U_z + \frac{U a^2}{z} \right] \quad || \tau, \phi \text{ comes from the set: } \{ r^{in} \cos(\omega t), r^{in} \sin(\omega t), \log r, \theta \}$$

So  $\phi = \operatorname{Re} \{ w(z) \}$

$$= U_x + \frac{U a^2 x}{r^2}$$

$\phi$  is conjugate to  $\tau$ .

Suppose that fluid is injected out of the body and the same condition previously.



$$\underline{u} \cdot \hat{n} = V \quad (\text{Notes previous had } V=0)$$

$$\frac{u}{\phi} \rightarrow U_i \quad \text{as } r \rightarrow \infty$$

$$\frac{\phi}{r} \rightarrow U_x = U \cos \theta \quad \text{as } r \rightarrow \infty \quad (\text{inhomogeneous})$$

$$\underline{u} \cdot \hat{n} = V \quad \text{on } r=a \quad (\text{inhomogeneous})$$

Same for all  $\theta$ .

$$\text{So } \phi = A \cos \theta + \frac{B}{r} \cos \theta + C \log(r)$$

Our basic solution :

1)  $\underline{z}'$ ,  $\underline{z}^c$ ,  $\underline{z}^s$  etc "singularities"  
 ↗ Dipole.

2)  $z^0$  - Nothing ;  $\frac{dw}{dz} = 0$

3)  $z$  :  $w(\theta) = U z$ ; uniform stream:  $\frac{dw}{dz} = U = u - c v$

$$4) w(z) = z^2 = [re^{i\theta}]^2$$


$$= r^2 \cos 2\theta + i r^2 \sin 2\theta.$$

$$\text{So } \psi = r^2 \sin 2\theta.$$

$$\text{So } \psi = 0 \text{ on } \theta = 0.$$

and with increasing  $\theta$ , next zero when  $\theta = \frac{\pi}{2}$   
hence:

Stagnation point flow:



$$\frac{dw}{dz} = 2z = 2x + 2iy$$

$$\Rightarrow u = 2x, v = -2y.$$


$$5) w(z) = z^3$$

$$\psi = r^3 \sin(3\theta)$$

$\psi = 0$  on  $\theta = 0$ , next zero when  
 $\theta = \frac{\pi}{3}$ .

$$6) w(z) = z^n$$

At  $\tau = 0$  on  $\theta = \frac{m\pi}{n}$ , at  $m = 0, \pm 1, \dots, \pm n$ .



thus in fundamental soln's, if  $n$  streamlines cross, they cross at an angle  $\frac{\pi}{n}$  in inviscid, incompressible flow.

Streamlines in the neighbourhood of a stagnation point:

Suppose we have a stag pt. in the flow.  
Move origin to that point.

In the neighbourhood of 0.

$$w(z) = a_0 + a_1 z + a_2 z^2 + a_3 z^3 + \dots$$

w.l.o.g we can take  $a_0 = 0$ .

At 0 (origin):


$$\frac{dw}{dz} = 0 \text{ (stagnant pt)} \text{ thus } a_1 = 0$$

Let the first non-zero term be  $a_n$ . Thus  $n \geq 2$  sufficiently to 0,  $w \sim a_n z^n$  for some complex  $a_n$ .

$$\text{Suppose } a_n = A e^{i\alpha}$$


$$\text{Then } w \sim A e^{i\alpha} r^ne^{i\theta} \\ = (A^{\frac{1}{n}} r)^n e^{in(\theta + \frac{\alpha}{n})}$$


i.e a fundamental soln,  $z^n$  rotated by  $\frac{\alpha}{n}$  and scaled  $A^{\frac{1}{n}}$



etc :

i.e exactly as before : n streamlines must cut at  $\frac{\alpha}{n}$ .





3 s'lines cut  
at  $\frac{\pi}{3}$ .

The remaining fundamental solution is


$$\log z.$$

If  $w(z) = m \log z$  (m real)

$$= m(\log r + i\theta)$$

$$= m \log r + ci\theta.$$

So  $\phi = m \log r$ ,  $\psi = ci\theta$ .



for m real  
ie  $\log r, \theta$  are conjugate functions - isotropic

source strength  $2\pi m$ .

Exercise: No other fundamental sol<sup>n</sup> is a source of fluid (consequence of Cauchy's thm).

$$\begin{aligned} \text{If } w(z) &= -cK \log z \quad (K \text{ real}) \\ &= -cK(\log r + i\theta) \\ &= K\theta - cK \log r. \end{aligned}$$


$$\phi = K\theta, \psi = -K \log r.$$

S'lines:  $\psi = \text{const}$

i.e.  $\log r = \text{const}$

i.e.  $r = \text{const}$

i.e. circles:



LINE VORTEX!

Aside:

$$\underline{\omega} = \text{curl } \underline{u}$$

$$= \zeta \hat{\underline{e}}_z + \eta \hat{\underline{e}}_y + \varphi \hat{\underline{e}}_x$$


How to let a solid body rotate  $\zeta = \varphi R$  everywhere.



$\curvearrowleft$  stick rotates.

---

the strength of a line (or point) vortex  
we measure the strength of ANY ROTATIONAL flow by its CIRCULATION about a closed contour  $C$  (say). the circulation is defined as:



$$\Gamma = \oint \underline{u} \cdot d\underline{l}$$

i.e sum of tangential velocity  $\times$  distance  
(c.f. work done going around a closed path).

Notice for irrotational flow this is zero

for all curves  $C$ .

[In 3D, if  $\underline{u} = \nabla\phi$ ;  $\int_A^B \underline{\nabla}\phi \cdot d\underline{l} = \phi(A) - \phi(B)$   
if  $A = B$  this is zero].

In 2D,  $\oint_C \underline{u} \cdot d\underline{l} = \int_A^A (\nabla \times \underline{u}) \cdot \hat{n} dA$ .


Both in 2D flow,  $\nabla \times \underline{u} = \zeta \hat{k}$  and  $\hat{n} = \hat{k}$   
so:

$$P = \int_A^A \zeta dA.$$

If  $\zeta = 0$  everywhere  $P = 0$  for all  $C$ .

For the point vortex:


$$\underline{w}(z) = -iK \hat{k} \log z.$$



Note that:  $\oint_{C_1} + \oint_{C_2} = 0$  so  $\oint_{C_1} = -\oint_{C_2}$

For a circuit around the origin, we can take the circuit to be a circle of radius  $a$  w.l.o.g.

$$P = \oint_{\theta=-\pi}^{\pi} \underline{u} \cdot d\underline{l}$$



Associated with a change  $d\theta$  in  $\theta$  is the vector:

$$d\underline{l} = (a d\theta) \hat{\theta}$$

and

$$\underline{u} = \nabla \phi$$

$$= \nabla (K \phi)$$

$$= K \nabla \phi$$

$$= K \left[ \frac{\partial}{\partial r} \hat{r} + \frac{1}{r} \frac{\partial}{\partial \theta} \hat{\theta} \right] \phi$$

$$= \frac{K}{r} \hat{\theta}$$

$$\text{On } r=a, \quad \underline{u} = \frac{K}{a} \hat{\underline{\theta}}$$

thus :

$$\begin{aligned} \Gamma &= \int_{-\pi}^{\pi} \frac{K}{a} \hat{\underline{\theta}} \cdot a d\theta \hat{\underline{\theta}} \\ &= 2\pi K. \end{aligned}$$

i.e line vortex has circulation  $2\pi K$

Exercise : Only fundamental soln with circulation.

Example : Consider a cylinder of radius  $a$ , in a stream of speed  $U$  where there is circulation  $K$  about the cylinder.

Take origin at the centre of the cylinder and axis  $Ox$  in the direction of the flow at infinity. Then:

$$\underline{w}(z) = U \underline{z} + \frac{Ua}{z} - \frac{iK}{2\pi} (\log z)$$


(satisfies Laplace's eq<sup>n</sup> because a sum of fundamental sol<sup>n</sup>  $\psi, \phi$ ).

Check :

$$\frac{dw}{dz} = U - \frac{Ua^2}{z} - \frac{ik}{2\pi z}$$

As  $z \rightarrow \infty$ ,  $\frac{dw}{dz} \rightarrow 0$  i.e.  $u \rightarrow 0$  and  $v \rightarrow 0$ . Thus b.c. (boundary conditions) at infinity is satisfied.

Take any circuit about the cylinder :



Then the circulation about C is:


$$2\pi \left( \frac{K}{2\pi} \right) = K.$$

as required, since only line vortex has circulation.


Remains to check at  $\underline{u} \cdot \hat{n} = 0$  on the cylinder  $r=a$ .

$$\text{i.e. } \underline{u} \cdot \hat{\underline{r}} = 0$$

$$\text{i.e. } u_\theta = 0 \text{ on } r=a.$$



Here is a nice way of doing this using complex variable:



At some point  $P$  the Cartesian components of velocity are:

$$\frac{dw}{dz} = u - iv.$$

Introduce  $x'$  and  $y'$  rotated by  $\theta$  degree anti-clockwise from  $x, y$ .

The  $\frac{dw}{dz'} = u' - iv'$  (the cartesian component along the dashed axis).

$$= u_r - i u_\theta.$$

$$\begin{aligned} \text{So } u_r - i u_\theta &= \frac{dw}{dz'} = \frac{dw}{dz} \frac{dz}{dz'} \\ &= e^{i\theta} \frac{dw}{dz} \end{aligned}$$

$$\text{Now: } z = e^{i\theta} z'$$

$$\text{so } \frac{dz}{dz'} = e^{i\theta}$$

$$\arg z' = \arg z - \theta$$

$$\arg z = \arg z' + \theta$$

$$\text{Thus: } u_r - \theta u_\theta = e^{i\theta} \frac{dw}{dz} \leftarrow \text{Very useful.}$$

In our example:

$$\frac{dw}{dz} = -\frac{Ua^2}{z^2} - \frac{iK}{2\pi z}.$$

On the cylinder,  $|z|=a$  i.e  $z = ae^{i\theta}$

$$\frac{dw}{dz} = U - Ue^{-i\theta} - \frac{ie^{-i\theta}}{2\pi z}$$


$$\text{so } e^{i\theta} \frac{dw}{dz} = Ue^{i\theta} - Ue^{-i\theta} - \frac{iK}{2\pi a}$$

$$= 2iU \sin \theta - \frac{iK}{2\pi a}$$


$$= u_r - iu_\theta.$$

Thus  $U_r = 0$  (as required)


and  $U_0 = \frac{K}{2\pi a} - 2U \sin \theta$ .



Tennis ball with "top spin".



So






5/11/11



Eg "Top spin" tennis:




$$\omega(z) = V \left( z + \frac{a^2}{z} \right) - \frac{cK}{2\pi} \log z.$$

$$V_y = Vy \left( 1 - \frac{a^2}{r^2} \right) - \frac{K}{2\pi} \log r$$

$$\Phi = V_z \left( 1 + \frac{a^2}{r^2} \right) + \frac{K}{2\pi} \theta.$$

$$\text{On } r=a, u_r=0, u_\theta = \frac{K}{2\pi a} - 2V \sin \theta.$$

When  $K=0$



At a stagnation point:

$$u = 0 \text{ and } \frac{du}{dz} = 0$$


$$\text{or } u=0, v=0$$

$$\text{or } u_r=0, u_\theta=0.$$

On the cy cylinder;  $r = a$ ,  $u_r = 0$  for all  $\theta$   
 so the stagnation points are where  $u_\theta = 0$

$$\text{i.e. } \frac{K}{2\pi a} = 2U \sin \theta.$$

$$\text{i.e. } \sin \theta = \frac{K}{4\pi a U}$$




For  $x > 0$ , there are between 0 and  $\pi$  (symmetric at  $\pi/2$ ).


On cy cylinder:

$$y = a \sin \theta = \frac{K}{4\pi a} \theta$$

$$\text{where } \frac{K}{4\pi a U} < 1$$



If  $\frac{K}{4\pi Va} = 1$



Stagnation points coincide at  $y=a$ .

If  $\frac{K}{4\pi Va} > 1$ , No roots  $\Rightarrow$  no stagnation point on the cylinder

Remember

$$w(z) = U \left( z + \frac{a^2}{z} \right) - \frac{iK}{2\pi} \log z$$

$$\frac{dw}{dz} = U \left( 1 - \frac{a^2}{z^2} \right) - \frac{iK}{2\pi z}$$

Stag points :

$$\frac{dw}{dz} = 0$$

$$\text{i.e. } U \left( 1 - \frac{a^2}{z^2} \right) - \frac{iK}{2\pi z} = 0.$$

Multiply by  $\frac{z^2}{Va^2}$

Quadratic in  $\frac{z}{a}$ , i.e.:

$$\left(\frac{z}{a}\right)^2 - \frac{iK}{2\pi Va} \left(\frac{z}{a}\right) - 1 = 0.$$

So 2 roots roots - product must be  $-1$ .

Then:


$$\frac{z}{a} = \frac{iK}{4\pi Va} \pm \sqrt{1 - \left(\frac{K}{4\pi Va}\right)^2}$$

If  $\frac{K}{4\pi Va} < 1$ : Already found  $(z_1, -\bar{z}_1)$

If  $\frac{K}{4\pi Va} > 1$ : Purely imaginary roots  
i.e.  $x=0$ ,  $y=y_1$

$$\Rightarrow \frac{z}{a} = iy_1, y_1 = y_1, z = x + iy_1$$

or  $\frac{i}{y_1}$




-/-  
Summary: choose  $\tau, \phi$  then:

- 1) Inhomogeneous.
- 2) Choose  $\{\tau^{\pm n} \cos(n\phi), r^{\pm n} \sin(n\phi), \log r, \phi\}$  with undetermined coefficient.
- 3) BC's give coefficients.

-/-  
The method of images

If the motion of a fluid in the  $xy$  plane is due to a distribution of singularities (e.g.: sources, sinks, vortices etc) and there is curve  $C$  in the plane then the system of singularities on one side of  $C$  is called the Image of the systems on the other side. If there is no flow through  $C$ :



No flow across C

$\Rightarrow$  System 1 image of system 2

$\Rightarrow$  C is a streamline.

$\Rightarrow$  May replace C by a solid boundary, without the flow outside C.

— —

Example: What is flow due to a source of strength m located at  $z = a$ , with a source wall along  $x = 0$ ?

Potential due source:


$$\omega_1(z) = \frac{m}{2\pi} \log(z-a)$$

Image is a source at  $z = -a$ .

$$\omega_2(z) = \frac{m}{2\pi} \log(z+a)$$

$$\text{So } \omega(z) = \omega_1(z) + \omega_2(z)$$

$$= \frac{m}{2\pi} \log(z-a) + \frac{m}{2\pi} \log(z+a)$$





14/11/11

$\underline{u}(x, t)$ , Velocity field,  $\times$  fixed axes.

Incompressibility  $\Rightarrow \nabla \cdot \underline{u} = 0$ .

Local motion at a point

- 1) Translation of C of M.
- 2) Dilatation.
- 3) Rotation.

Irrationality persist:

$$\nabla \cdot \underline{u} = 0 \Rightarrow \exists \phi \text{ st } \underline{u} = \nabla \phi. \quad (\text{True in 3D})$$

$\phi$ : Incompressible and 2D


$\phi$ : Irrational.

Irrational, Incompressible and 2D:  $\phi$  and  $\psi$  then

$$\nabla \phi = -\hat{z} \wedge \nabla \psi.$$

$\exists w(z)$  where  $z = x + iy$ ,  $w(z) = \phi + i\psi$ .



Laurent: Sum of  $z^{th}$ .



In polar:

$\psi, \phi$  drawn from  $\{ r^{th} \cos \theta, r^{\frac{th}{2}} \sin \theta, \log r, \theta \}$ .


System A



System B.

If no flow across C, then system A is the image of system B.

Example 1



• Original System:

Source strength  $m$  at  $x=a$   
Complex potential

$$\omega(z) = \frac{m}{2\pi} \log(z-a)$$

• Image system

Source strength  $m$  at  $x = -a$ .

Complex potential

$$\omega_1(z) = \frac{m}{2\pi} \operatorname{Log}(z+a).$$

Total system = Original + Image.

$$\omega(z) = \frac{m}{2\pi} \operatorname{Log}(z-a) + \frac{m}{2\pi} \operatorname{Log}(z+a).$$

If this is correct then  $u=0$  on  $x=0$ .

$$\omega(z) = \frac{m}{2\pi} \operatorname{Log}(z^2 - a^2)$$

$$\frac{dw}{dz} = \frac{m}{2\pi} \left( \frac{1}{z^2 - a^2} \right) 2z$$

On  $x=0$  or  $z = iy$ .


$$u - iv = \frac{dw}{dz}$$

$$= \frac{m}{2\pi} \left( \frac{1}{y^2 - a^2} \right) 2iy.$$


So  $u=0$  (as expected) and  $v = \frac{my}{\pi(y^2 + a^2)}$

So maximum speed on wall is:


$$V = \pm \frac{m}{2\pi a} \quad \text{when } y = \pm a.$$



### Example 2



Example 3: Wall at  $\pi/n$ .




$$\text{e.g. } n=4.$$

Example 4: Vortex of strength  $K$  at  $z = cb$  above the plane  $y = 0$ .

Complex potential  $w_1(z) = \frac{-icK}{2\pi} \operatorname{Log}(z - cb)$

Image: vortex of strength  $-K$  at  $z = -cb$

Complex potential  $w_2(z) = \frac{+icK}{2\pi} \operatorname{Log}(z + cb)$



total system = original + image

$$= -\frac{iK}{2\pi} \log(z - ib) + \frac{iK}{2\pi} \log(z + ib)$$

Check  $v=0$  on  $y=0$  as expected.

Velocity field:


$$\frac{dw}{dz} = -\frac{iK}{2\pi} \cdot \left( \frac{1}{z - ib} \right) + \frac{iK}{2\pi} \cdot \left( \frac{1}{z + ib} \right)$$



At  $z = ib$ , neglecting first term, which is just the spinning of an isolated vortex about its centre.

$$\frac{dw}{dz} = \frac{iK}{4\pi b}$$

$$\text{i.e. } u = \frac{K}{4\pi b}, \quad v = 0.$$


i.e. a free vortex would be driven along parallel to the plane  $x=0$  by its image in the plane:





### Circle theorem:

The image system in the circle  $|z|=a$  of the complex potential  $w(z) = f(z)$  where  $f(z)$  has no singularities inside the circle (i.e. original system all on one side of line)  $|z| < a$ , is  $f(\frac{a^2}{\bar{z}})$  where for any analytic function  $g(z)$ ,  $\bar{g}(z) = \overline{g(\bar{z})}$



e.g. if

$$g(z) = \dots + \frac{\alpha_2 z}{z^2} + \frac{\alpha_{-1}}{z} + \alpha_0 + \alpha_1 z + \alpha_2 z^2 + \dots$$

$$g(\bar{z}) = \dots + \frac{a_{-2}}{\bar{z}^2} + \frac{a_{-1}}{\bar{z}} + a_0 + a_1 \bar{z} + a_2 \bar{z}^2 + \dots$$

$$\bar{g}(z) = \dots + \frac{\bar{a}_{-2}}{z^2} + \frac{\bar{a}_{-1}}{z} + \bar{a}_0 + \bar{a}_1 z + \bar{a}_2 z^2 + \dots$$

$$\overline{g(\bar{z})} = \dots + \frac{\bar{a}_{-2}}{\bar{z}^2} + \frac{\bar{a}_{-1}}{\bar{z}} + \bar{a}_0 + \bar{a}_1 \bar{z} + \bar{a}_2 \bar{z}^2 + \dots$$



$$\hookrightarrow = \bar{g}(z)$$

Still an analytic function at  $\frac{a^2}{z}$

Now  $f$  has no singularities in  $|z| < a$  so  $f(a^2/z)$  has no singularities in  $|z| > a$ , since

$$|z| > a \Rightarrow \frac{|z|}{a^2} > \frac{1}{a} \quad \text{so} \quad \frac{a^2}{|z|} < a.$$

Similarly for  $\bar{f}(a^2/z)$



Singularities outside  $C$  : Singularities inside  $C$

Check for the complete potential:

$$w(z) = f(z) + \bar{f}\left(\frac{a^2}{z}\right)$$

that there is no flow through  $|z|=a$ .

Why  $a^2/z$  as argument of  $\bar{f}$ ?

On the circle  $|z|=a$ , i.e.  $z\bar{z}=a^2$  i.e.  $a^2/z=\bar{z}$   
i.e.  $a^2/z$  is analytic (except  $z=0$ ) but equal to  $\bar{z}$  on  $C$ .

- this is the Schwarz function for  $C$ .

On  $|z|=a$ ,  $a^2/z=\bar{z}$ .

$$\text{so } \bar{f}\left(\frac{a^2}{z}\right) = \bar{f}(\bar{z})$$

$$= \widehat{f(\bar{z})}$$

$$= \overline{f(z)} \quad \text{on } C.$$

Combine potentials

$$w(z) = f(z) + \overline{f(z)}$$

on  $C$ .

$$\text{Note } w(z) = f(z) + \overline{f(z)}$$

$$= \operatorname{Re}\{w(z)\} \text{ i.e. } \psi=0 \text{ on } |z|=a$$

So

$$\operatorname{Im}\{w(z)\} = 0$$

on  $|z| = a$ .

i.e. circle is a streamline as required i.e.  
no flow across  $|z| = a$ .


i.e.  $\bar{f}\left(\frac{az}{z}\right)$  is image of  $f(z)$  in  $|z| = a$ .

Find Schwarz function  $h(z)$  for  $C$ .

On  $C$   $h(z) = \bar{z}$ . So image of  $f(\bar{z})$  is  
 $\bar{f}(h(z))$ .

Example 1:

Find the image system + the total complex potential for a source of strength  $m$  at  $z = a + ib$  outside the cylinder  $|z| = a$  where  $b > a$ .



Original System:

$$f_1(z) = \frac{m}{2\pi} \log(z - ib)$$

Image system:

$$f_2(z) = \overline{f_1\left(\frac{a^2}{z}\right)}$$

$$= \frac{m}{2\pi} \log\left(\left(\frac{a^2}{z}\right) - ib\right)$$

$$= \frac{m}{2\pi} \log\left(\frac{a^2}{z} + ib\right)$$

Total potential.

$$\omega(z) = f_1(z) + f_2(z)$$

$$= \frac{m}{2\pi} \log(z - ib) + \frac{m}{2\pi} \log\left(\frac{a^2}{z} + ib\right)$$

What is this?

$$\text{Image system} = \frac{m}{2\pi} \log\left(\frac{a^2}{z} + ib\right)$$

$$= -\frac{m}{2\pi} \log(z) + \frac{m}{2\pi} \log(a^2 + ibz)$$

$$= -\frac{m}{2\pi} \log(z) + \frac{m}{2\pi} \log(cb) + \frac{m}{2\pi} \log\left[z - \frac{ca^2}{b}\right]$$

Sink strength  
m of origin


(no surprise)

Arbitrary  
constant  
 $\Rightarrow$  no effect

(no flow  
across C)

Source strength m  
at  $z = \frac{ca^2}{b}$  i.e.  $x = 0$   
 $y = \frac{a^2}{b}, b > a$

Optical image  
point




$$\frac{a^2}{b} < a$$

$$(b > a)$$

Guaranteed.

Example 2: Vortex in coffee cup.



## Equation of Motion

$$\underline{F} = m\underline{a}$$


$$= \frac{d(m\underline{v})}{dt}$$

[

Rate of change of mom. of particle,  
following the particle.

We thus need to define rate of change following  
a particle for a field.

Suppose we have some field, known for all time  
 $t$ , and position  $\underline{r}$ ,  $\phi(t, \underline{r})$ .



Now suppose we follow some particle whose path is  
given by :

$$\frac{d\underline{r}}{dt} = \underline{u}$$

Then the values. of  $\phi$  along the particle path  
are:

$\phi(t, \Sigma(t))$  when  $\frac{dx}{dt} = \underline{u}$

a function of  $t$ , alone.

What is the rate of change of  $\phi$  along this path

$$\frac{D\phi}{Dt} = \left. \frac{\partial \phi}{\partial t} \right|_{x=\Sigma(t)}$$

$$\dots = \frac{\partial \phi}{\partial t} + \frac{\partial \phi}{\partial x} \frac{\partial x}{\partial t} + \frac{\partial \phi}{\partial y} \frac{\partial y}{\partial t} + \frac{\partial \phi}{\partial z} \frac{\partial z}{\partial t}.$$

(Chain rule)

$$\text{i.e } \frac{D\phi}{Dt} = \frac{\partial \phi}{\partial t} + u \frac{\partial \phi}{\partial x} + v \frac{\partial \phi}{\partial y} + w \frac{\partial \phi}{\partial z}$$

$$= \frac{\partial \phi}{\partial t} + (\underline{u} \hat{i} + \underline{v} \hat{j} + \underline{w} \hat{k}) \cdot \left( \frac{\partial \phi}{\partial x} \hat{i} + \frac{\partial \phi}{\partial y} \hat{j} + \frac{\partial \phi}{\partial z} \hat{k} \right)$$

$$= \frac{\partial \phi}{\partial t} + \underline{u} \cdot \nabla \phi$$

Speed at which move through gradient.

$$= \left( \frac{\partial}{\partial t} + \underline{u} \cdot \nabla \right) \phi.$$

Convective or advective derivative.

Example:

Ex. 1.  $\phi = x$

$$\frac{Dx}{DE} = \cancel{\frac{\partial x}{\partial t}} + u \frac{\partial x}{\partial x} + v \cancel{\frac{\partial x}{\partial y}} + w \cancel{\frac{\partial x}{\partial z}}$$

$$= u$$

Ex. 2:  $\phi = r$

$$\frac{Dr}{DE} = \cancel{\frac{\partial r}{\partial t}} (x \hat{i} + y \hat{j} + z \hat{k})$$

$$+ u \cancel{\frac{\partial r}{\partial x}} (x \hat{i} + y \hat{j} + z \hat{k})$$

$$+ v \cancel{\frac{\partial r}{\partial y}} (x \hat{i} + y \hat{j} + z \hat{k})$$

$$+ w \cancel{\frac{\partial r}{\partial z}} (x \hat{i} + y \hat{j} + z \hat{k})$$

$$= 0 + u \hat{i} + v \hat{j} + w \hat{k}$$

$$= u$$

Ex 3:  $\phi = \underline{u};$

$$\frac{D\underline{u}}{Dt} = \frac{\partial \underline{u}}{\partial t} + (\underline{u} \cdot \nabla) \underline{u}.$$

$\Rightarrow$   $-/-$

$$\frac{d}{dt} \int_{a(\epsilon)}^{b(\epsilon)} f(\epsilon, x) dx$$


$$= \int_a^b \frac{df}{dt} dx + f(\epsilon, b) b'(\epsilon) - f(\epsilon, a) a'(\epsilon)$$

17/11/11


## Reynolds Transport theorem (RTT)

Why? Eventually we want to apply Newton's law to a fluid, i.e.

$$\frac{d}{dt}(\text{mom'm}) = \text{force}.$$




Consider a quantity  $\alpha(\Sigma, t)$  associated with a fluid. Let the fluid occupy a domain  $\mathcal{D}$  and have specified velocity field  $\underline{u}(\Sigma, t)$ . Consider a sub-volume  $V$  contained in  $\mathcal{D}$  with surface  $S$ . We take  $V$  to consist always of the same fluid element or particles. Thus  $V$  moves i.e  $V = V(t)$ .



We define

$$I(t) = \int_{V(t)} \alpha(\Sigma, t) d\Sigma.$$

i.e the total amount of  $\alpha$  in  $V$  at any time.



Reynold's : what is  $\frac{dI}{dt}$  ?


$$\frac{dI}{dt} \text{ or } \frac{DI}{DE} = \lim_{\delta t \rightarrow 0} \frac{I(\epsilon + \delta t) + I(\epsilon)}{\delta t}.$$

↑

Emphasises that we are following particles.

Here  $I(\epsilon + \delta t) = \int_{V(\epsilon + \delta t)} \alpha(\Sigma, \epsilon + \delta t) d\Sigma$ .

Here  $V(\epsilon + \delta t)$  is the volume position at an interval  $\delta t$  after  $\epsilon$ .



and by Taylor's Theorem :

$$\alpha(\underline{r}, \epsilon + \delta\epsilon) = \alpha(\underline{r}, \epsilon) + \delta\epsilon \frac{\partial \alpha}{\partial \epsilon}(\underline{r}, \epsilon)$$

$$+ \frac{1}{2} (\delta\epsilon)^2 \frac{\partial^2 \alpha}{\partial \epsilon^2}(\underline{r}, \tau)$$

where  $\tau$  lies in  $(0, \delta\epsilon)$

So:

$$I(\epsilon + \delta\epsilon) = \int_{\underline{r} + \delta\underline{r}} [\alpha(\underline{r}, \epsilon) + \delta\epsilon \frac{\partial \alpha}{\partial \epsilon}(\underline{r}, \epsilon)] d\underline{r}$$

$$+ \frac{1}{2} (\delta\epsilon)^2 \int_{\underline{r} + \delta\underline{r}} \frac{\partial^2 \alpha}{\partial \epsilon^2}(\underline{r}, \tau) d\underline{r}$$

$$= \int_{\underline{r} + \delta\underline{r}} \alpha d\underline{r} + \delta\epsilon \int_{\underline{r} + \delta\underline{r}} \frac{\partial \alpha}{\partial \epsilon} d\underline{r} + O((\delta\epsilon)^2)$$

Argument is  $(\underline{r}, \epsilon)$

Now:

$$\frac{DI}{DE} = \lim_{\delta\epsilon \rightarrow 0} \left\{ \frac{1}{\delta\epsilon} [I(\epsilon + \delta\epsilon) - I(\epsilon)] \right\}$$

$$\dots = \lim_{\delta\epsilon \rightarrow 0} \left\{ \frac{1}{\delta\epsilon} \left[ \underbrace{\int_{\underline{r}} \alpha d\underline{r}}_n + \int_{\underline{r}} \alpha d\underline{r} + \delta\epsilon \int_{\underline{r} + \delta\underline{r}} \frac{d\alpha}{dt} d\underline{r} \right. \right.$$

$$\left. \left. + O((\delta\epsilon)^2) - \int_{\underline{r}} \alpha d\underline{r} \right] \right\}$$

$$\Rightarrow \frac{DI}{DE} = \lim_{\delta t \rightarrow 0} \left\{ \frac{1}{\delta t} \int_{SV} \alpha dV + \int_V \frac{\partial \alpha}{\partial E} dV \right. \\ \left. + \int_{SV} \frac{\partial \alpha}{\partial F} dV + O(\delta t) \right\}.$$

The underlined term is :

$$\underline{\int_{SV} \frac{\partial \alpha}{\partial F} dV} \leq \left| \int_{SV} \frac{\partial \alpha}{\partial F} dV \right| \\ \leq \int_{SV} \left| \frac{\partial \alpha}{\partial F} \right| dV \\ \leq \int_{SV} A dV.$$

$$\text{where } A = \max_V \left( \left| \frac{\delta \alpha}{\delta E} \right| \right) \\ = A \int_{SV} dV \\ = A |SV| \rightarrow 0$$


As  $\delta t \rightarrow 0$ .

$$\text{Thus : } \frac{DI}{DE} = \int_V \frac{\partial \alpha}{\partial F} dV + \lim_{\delta t \rightarrow 0} \frac{1}{\delta t} \int_{SV} \alpha dV.$$

Particles making up  $dS$  have moved a distance  $u \cdot \hat{n}$  in time  $\delta t$ .

They sweep out a volume = area base-times height i.e

$$dV = dS \times h = (\underline{u} \cdot \hat{n}) \delta t .$$



$$\text{i.e } dV \sim (\underline{u} \cdot \hat{n}) \delta t dS .$$

$$\text{Thus is } \int_{\partial V} \alpha dV = \int_S \alpha (\underline{u} \cdot \hat{n}) \delta t dS .$$

$$= \delta t \int_S \alpha (\underline{u} \cdot \hat{n}) dS .$$

Thus:

$$\frac{DI}{DE} = \int_V \frac{\partial \alpha}{\partial t} dV + \int_S \alpha (\underline{u} \cdot \hat{n}) dS .$$

Reynolds Transport Theorem (1)  
or RTT (1)

the first form of RTT I:

$$\frac{D}{DE} \left( \int_V \alpha dV \right) = \int_V \frac{\partial \alpha}{\partial E} dV + \int_S \alpha (\underline{u} \cdot \hat{n}) dS.$$

Local r.o.c.h (rate of change)

flux at  $\alpha$  through boundary of  $V$ .

(The 3D version of Leibnitz rule for differentiating under the integral sign.)

Recall the 1D Leibnitz:

$$\frac{d}{dt} \left( \int_{a(t)}^{b(t)} \alpha(x, t) dx \right) = \int_a^b \frac{\partial x}{\partial t} dt + b'(t) \alpha(b, t) - a'(t) \alpha(a, t).$$

But the divergence theorem says that for any vector  $E$ :

$$\int_S E \cdot \hat{n} dS = \int_V (\nabla \cdot E) dV.$$

Putting  $E = \alpha \underline{u}$ .

Putting  $E = \alpha u$ .

$$\frac{D}{DE} \left( \int_V \alpha dV \right) = \int_V \left[ \frac{\partial \alpha}{\partial E} + \nabla \cdot (\alpha \underline{u}) \right] dV.$$

RRT 2

Now:

$$\nabla \cdot (\alpha \underline{u}) = (\underline{u} \cdot \nabla) \alpha + \alpha \nabla \cdot \underline{u}.$$

So:

$$\begin{aligned} \frac{\partial \alpha}{\partial E} + \nabla \cdot (\alpha \underline{u}) &= \frac{\partial \alpha}{\partial E} + (\underline{u} \cdot \nabla) \alpha + \alpha (\nabla \cdot \underline{u}) \\ &= \frac{D\alpha}{DE} + \alpha (\nabla \cdot \underline{u}). \end{aligned}$$

Thus:

$$\frac{D}{DE} \left( \int_V \alpha dV \right) = \int_V \left( \frac{D\alpha}{DE} + \alpha (\nabla \cdot \underline{u}) \right) dV.$$

RRT 3

Example: Take  $\alpha = \rho$ , density:

$$\text{Then } M = \int_V \rho dV$$

is the mass of particles, making up the volume  $V$ .

Then by RTT2:

$$\begin{aligned}\frac{DM}{DE} &= \frac{D}{DE} \int_V \rho dV \\ &= \int_V \left( \frac{\partial \rho}{\partial E} + \nabla \cdot (\rho \underline{u}) \right) dV.\end{aligned}$$

But mass is conserved so  $\frac{DM}{DE} = 0$ .

i.e. for any  $V$  in  $\mathcal{D}$ :

$$\int_V \left[ \frac{\partial \rho}{\partial E} + \nabla \cdot (\rho \underline{u}) \right] dV = 0.$$


By the lemma, this implies:

$$\frac{\partial \rho}{\partial E} + \nabla \cdot (\rho \underline{u}) = 0$$


everywhere in  $\mathcal{D}$ .

- \* Conservation of mass for a compressible
- \* Contains  $\nabla \cdot \underline{u} = 0$  when  $\rho$  is constant.

21/11/11



streamline  
 $r^2 \cos \theta$ .



Uniform Stream  
 $r \sin \theta$ .

RTT: 3D version of Leibnitz:

$$\text{RTT1: } \frac{D}{DE} \int_V \alpha \, dV = \int_V \frac{\partial \alpha}{\partial t} \, dV + \int_S \alpha \underline{u} \cdot \hat{n} \, dS$$

$$\text{RTT2: } \frac{D}{DE} \int_V \alpha \, dV = \int_V \left[ \frac{\partial \alpha}{\partial t} + \nabla \cdot (\alpha \underline{u}) \right] \, dV.$$



$$\text{RTT3: } \frac{D}{DE} \int_V \alpha \, dV = \int_V \left[ \frac{\partial \alpha}{\partial t} + \alpha (\nabla \cdot \underline{u}) \right] \, dV.$$

Any scalar  $\alpha(x, t)$ .

Example : Conservation of Mass ( $\rho = \rho$  density)

Consider a fluid of variable density  $\rho(x, t)$  that occupies a domain  $D$ . Let  $V$  be any subdomain of  $D$ . [i.e  $V$  must be ARBITRARY]. Consider the total mass of all the particles comprising  $V$  i.e

$$M = \int_V \rho \, dV.$$



The rate of change of mass  $M$ , staying with the same particles must be zero (conservation of mass) i.e

$$\frac{dM}{dt} = 0.$$

But by RTT 2 :

$$\frac{D}{Dt} \int_V \rho \, dV = \int_V \left[ \frac{\partial \rho}{\partial t} + \nabla \cdot (\rho \underline{u}) \right] \, dV.$$

$$\text{So } \int_V \left[ \frac{\partial \rho}{\partial t} + \nabla \cdot (\rho \underline{u}) \right] \, dV = 0.$$

But  $V$  is ARBITRARY, so this is TRUE FOR ALL  $V$ .

Hence by our theorem:

$$\frac{\partial \rho}{\partial t} + \nabla \cdot (\rho \underline{u}) = 0$$

everywhere in  $\mathcal{D}$ .

This can be written:

$$\frac{D\rho}{Dt} + \rho \nabla \cdot \underline{u} = 0.$$

$\nearrow$

TRUE whether COMPRESSIBLE or INCOMPRESSIBLE.

Notice, if the flow is incompressible, fluid elements cannot be squashed i.e. they preserve their volume. But they preserve their mass

$$\rho \nabla \cdot \underline{u} = 0$$

$$\text{i.e. } \nabla \cdot \underline{u} = 0 \quad (\text{As below}).$$

[Notice: This does not require all particle to have the same density].


Eg: WARM: LESS DENSE

WATER

Incompressible not constant density.

COLD: DENSE

Fluid particles retain density c.f. colour.



# BERNARD CONVECTION :

Water

Low density  
 { } } }  
 Heat from  
 below.

RTT4: For a fluid of density  $\rho(x, t)$  considered any quantity  $f(x, t)$

Put  $\alpha = \rho f$  in RTT3:

$$\frac{D}{Dt} \int_V f \rho \, dV = \int_V \left[ \frac{\partial}{\partial t} (f \rho) + \nabla \cdot (f \rho \underline{u}) \right] dV$$

$$[\dots] = \rho \frac{\partial f}{\partial t} + f \frac{\partial \rho}{\partial t} + f \rho \nabla \cdot \underline{u} + \underline{u} \cdot \nabla (f \rho)$$

$$= f \left( \frac{\partial \rho}{\partial t} + \rho \nabla \cdot \underline{u} \right) + \rho \frac{\partial f}{\partial t} + f \nabla \cdot \underline{u} \rho$$

$$+ \rho \underline{u} \cdot \nabla f.$$

$$= f \left( \frac{\partial \rho}{\partial t} + \nabla \cdot (\rho \underline{u}) \right) + \rho \left[ \frac{\partial f}{\partial t} + (\underline{u} \cdot \nabla) f \right]$$

$$= \rho \frac{Df}{Dt}$$

i.e RTT4:

$$\frac{D}{DE} \int_V \rho f \, dV = \int_V \rho \frac{Df}{DE} \, dV$$

or

$$\frac{D}{DE} \int_V f \rho \, dV = \int_V \frac{Df}{DE} \rho \, dV.$$


i.e.:

$$\frac{D}{DE} \int_V f \, dM = \int \frac{Df}{DE} \, dM.$$

i.e integrating w.r.t mass.

Example 2: Force = R.o.c. h of momentum  
i.e  $\alpha = \rho \underline{u}$ .

Consider a fluid of density  $\rho(x, t)$  occupying a domain  $D$ . Let  $V$  be any subdomain, with surface  $S$  of  $D$  (i.e. important that  $V$  is ARBITRARY for our theorem).



Consider

$$\underline{m} = \int_V \rho \underline{u} \, dV.$$


the total momentum of the fluid particle making up  $V$ .

the following these particles, by RTT<sup>4</sup>,

$$\frac{D\bar{m}}{Dt} = \frac{D}{DE} \int_V \rho \bar{u} dV$$


$$= \int_V \rho \frac{Du}{Dt} dV.$$

Acceleration.



By Newton this must equal the total external force acting on the particle comprising  $V$ . (The internal forces sum to zero).

Let each particle be subject to an external force  $E$  per unit mass. (e.g. gravity,  $E = -g\hat{z}$  or magnetic force or or a "fictitious" force e.g. (Coriolis))



Pressure: normal stress

That is ALL for INVISCID inwards  $p(x,t) = p\hat{n}$  fluid as elements cannot exert a shear force (i.e. tangential stress) - there would be an extra term in viscous fluid.

Thus, the total force on all particles comprising

$V_2$  is

$$\int_V \rho E \, dV + \int_S (-p) \hat{n} \, dS.$$

$$= \int_V \rho E \, dV + \int_V (-\nabla p) \, dV$$

by vector form of divergence theorem.

$$= \int_V (-\nabla p + \rho E) \, dV$$

R.o.ch mom'm = force density.

$$\int_V \rho \frac{Du}{Dt} \, dV = \int_V (-\nabla p + \rho E) \, dV.$$

$$\text{i.e. } \int_V \left( \rho \frac{Du}{Dt} + \nabla p - \rho E \right) \, dV = 0.$$

But  $V$  is arbitrary, so this is true for all  $V$ . Hence by our thm:

$$-\rho \frac{Du}{Dt} + \nabla p - \rho E = 0.$$

Everywhere in  $D$ .

This is Euler's Equation for an inviscid fluid:

$$\rho \frac{D\mathbf{u}}{Dt} = -\nabla p + \rho \nabla E.$$

Mass  $\times$  ACCELERATION = FORCE.

Note that:

$\rho$  - rho - density

$p$  - "p" - pressure.

Equations of motion for a (possibly compressible) fluid.

Density  $\rho(x, t)$ , pressure  $p(x, t)$ ,  
velocity  $\mathbf{u}(x, t)$

Mass:  $\frac{\partial \rho}{\partial t} + \nabla \cdot (\rho \mathbf{u}) = 0$ .

Euler:  $\rho \frac{D\mathbf{u}}{Dt} = -\nabla p + \rho \mathbf{E}$ .

Note: 2 unknown scalar fields ( $\rho, p$ )  
fields and one unknown vector fields ( $\mathbf{u}$ ).

We have 1 scalar + 1 vector equation

This is missing a scalar equation.

-/-

Geophysical Fluid Dynamics :- Atmosphere + Ocean

Incompressibility :  $\frac{D\rho}{Dt} = 0$

Mass :  $\nabla \cdot \underline{u} = 0$ .

Euler :  $\rho \frac{D\underline{u}}{Dt} = -\nabla p + \rho F$ .

Gas Dynamics (Cosmology)

$$\rho = f(p.)$$

For an ideal gas

$$p = \rho^\alpha$$

for some  $\alpha$  - second scalar equation.

-/-

We will continue by taking the density to be constant, all particles have same density.

Then

Mass = Incompressibility = "Continuity".

For Euler:


- | scalar unknown:  $\rho$ ,  $\nabla \cdot \underline{u} = 0$ .
- | vector unknown:  $\underline{u}$ ,  $\rho \frac{D\underline{u}}{Dt} = -\nabla p + \rho \underline{F}$ .
- | scalar equation
- | vector equation.

--

Next examples using this:

Open channel flow: hydrodynamics } Need  
Surface water waves } gravity

Example: Find the free surface shape for a cylindrical container partially filled with fluid of constant density  $\rho$  in a solid body rotation with angular speed  $\Omega$  about a vertical axis.




Ans: Let the flow have settled to a steady state, then:

$$\frac{\partial}{\partial t} = 0.$$

Continuity:  $\nabla \cdot \underline{u} = 0$ .

Euler:  $\rho \frac{D\underline{u}}{Dt} = -\nabla p + \rho \underline{F}$ .



$\underline{F}$  force / unit mass  $\leftarrow$  dimension  
Acceleration

So  $\underline{F} = -g \hat{\underline{z}}$ .

$\frac{D\underline{u}}{Dt} = \frac{\partial \underline{u}}{\partial t} + (\underline{u} \cdot \nabla) \underline{u}$ .

So Euler becomes:

$$(\underline{u} \cdot \nabla) \underline{u} = -\nabla p - \rho g \hat{\underline{z}}$$

since  $\underline{F} = -\rho g \hat{\underline{z}}$  <sup>important</sup>

We are told that the fluid is in solid body rotation i.e.:

$$\underline{u} = \underline{\Omega} \wedge \underline{r}$$

$$\Rightarrow \underline{u} = \begin{vmatrix} \hat{i} & \hat{j} & \hat{k} \\ 0 & 0 & \frac{k}{2} \\ x & y & z \end{vmatrix}$$

$$= -\Omega y \hat{i} + \Omega x \hat{j}$$

i.e  $u = -\Omega y \hat{i}$   
 $v = \Omega x \hat{j}$ .

$$\text{Now: } \underline{u} \cdot \nabla = u \frac{\partial}{\partial x} + v \frac{\partial}{\partial y} + w \frac{\partial}{\partial z}$$

So:

$$(\underline{u} \cdot \nabla) u = \left( -\Omega y \frac{\partial}{\partial x} + \Omega x \frac{\partial}{\partial y} \right) (-\Omega y)$$

$$= -\Omega^2 x.$$

$$(\underline{u} \cdot \nabla) v = \left( -\Omega y \frac{\partial}{\partial x} + \Omega x \frac{\partial}{\partial y} \right) (\Omega x)$$

$$= -\Omega^2 y.$$

Eulers: (air components)

$$x\text{-mom'm}: -\rho \Omega^2 x = -\frac{\partial p}{\partial x} \quad (1)$$

$$y\text{-mom'm}: -\rho \Omega^2 y = -\frac{\partial p}{\partial y} \quad (2)$$

$$z\text{-mom'm}: 0 = -\frac{\partial p}{\partial z} - \rho g. \quad (3)$$

Integrate (1)

$$P = \frac{1}{2} \rho \sigma^2 x^2 + f(y, x)$$

Diff. w.r.t  $y$ :

$$P_y = f_y(y, x).$$

Compare with (2):  $f_y = \rho \sigma^2 y$

$$\text{i.e. } f = \frac{1}{2} \rho \sigma^2 y^2 + h(z)$$

$$\text{i.e. } P = \frac{1}{2} \rho \sigma^2 (x^2 + y^2) + h(z)$$

Diff. w.r.t  $z$ :

$$P_z = h'(z)$$

Compare with (3)

$$h'(z) = -\rho g$$

$$\text{i.e. } h(z) = -\rho g z + C$$

where  $C$  is a constant

$$\text{i.e. } P = \frac{1}{2} \rho \sigma^2 (x^2 + y^2) + \rho g z + C.$$

— / —  
iso bars = lines of constant pressure.

isobars surface = surface of constant pressure  
— / —

$P = \text{constant}$ ,  $p = A$ , constant  $A$ .

Take :


$$\rho g z = \frac{1}{2} \rho \Omega^2 (x^2 + y^2) + C - A.$$

$$\text{i.e. } z = \frac{1}{2} \frac{\Omega^2}{g} (x^2 + y^2) + \frac{C - A}{\rho g}$$

Let  $\frac{C - A}{\rho g} = z_0 = \text{constant}$


$$z - z_0 = \frac{1}{2} \frac{\Omega^2}{g} (x^2 + y^2).$$

- a paraboloid with  $(0, 0, z_0)$



## Archimedes ?

Example 2 : Consider a submerged body of volume  $V$  with surface  $S$ . Then the force on the body is upwards and equal to the weight of water displaced.





24/11/11

## Hydrostatic Pressure

Cty (Continuity) :  $\nabla \cdot \underline{u} = 0$ .

Euler :  $\rho \frac{D\underline{u}}{Dt} = -\nabla P + \rho E$ .

When gravity is the only external force :

$$E = -g \hat{\underline{z}}$$

If the fluid is at rest :

$$\underline{u} = 0, \quad 0 = -\nabla P - g \hat{\underline{z}}$$

$$\text{i.e } \frac{\partial P}{\partial x} = 0, \quad \frac{\partial P}{\partial y} = 0, \quad \frac{\partial P}{\partial z} = -\rho g$$

$$\text{i.e } P = P(y, z), \quad P = P(z)$$

$$\text{i.e } P = -\rho g z + \text{const.}$$


---

$z = 0$  : surface where pressure is atmospheric i.e  $P = P_a$

Then  $P = P_a$  when  $z = 0$

$$P = P_a - \rho g z.$$


we call this HYDROSTATIC pressure.



Weight of water  
above  $dS$  is  
 $z dS \times \rho \times g$

i.e Hydrostatic pressure supports above.

Example : Consider a submerged body occupying a volume  $V$  with surface  $S$ , immersed in a fluid of density  $\rho$ .



The force on the body is

$$F = \int_{S'} p_n^+ dS'$$

$$= \int_V \nabla P dV$$

by the divergence theorem.

Hence  $P$  is the pressure in the fluid surrounding  $V$ . But fluid at rest, so:

$$P = P_H = P_a - \rho g \hat{z}$$

So

$$\Delta P = \Delta P_H = -\rho g \hat{z}$$

So

$$F = - \int_V (-\rho g \hat{z}) dV$$

$$= \rho g \hat{z} \int_V dV$$

Density of fluid =  $\rho V g \hat{z}$

Not mass of body

$$\rho V = \text{mass of fluid}$$

$$\rho V g = \text{weight}$$

$\rho V g \hat{z}$  = an upward force equal to the weight of the fluid displaced

ARCHEDELES

-/-

For a moving fluid, it is often convenient to split the pressure into hydrostatic and the rest, called dynamic

$$\text{i.e. } P = P_H + P_d$$

Then the Euler equations under gravity become

$$\begin{aligned}\rho \frac{D\bar{u}}{Dt} &= -\nabla P - \rho g \hat{\underline{z}} \\ &= -\nabla p_H - \nabla p_d - \rho g \hat{\underline{z}} \\ &= -(\rho g \hat{\underline{z}}) - \nabla p_d - \rho g \hat{\underline{z}} \\ &= -\nabla p_d.\end{aligned}$$

i.e. we can ignore gravity in the equation of motion, provided we measure pressure as the deviation from hydrostatic.

This is not useful when a free surface is present since the b.c. there

$$P = P_a$$

is on the total pressure  $P = P_H + P_d$ .

Bernoulli's Equations

We have the identity:

$$(\underline{u} \cdot \nabla) \underline{u} = \nabla \left( \frac{1}{2} \underline{u}^2 \right) + \underline{\omega} \wedge \underline{u}.$$

where  $\underline{\omega} = \nabla \wedge \underline{u}$  is the vorticity.

$$\text{Thus } \frac{D\underline{u}}{Dt} = \frac{\partial \underline{u}}{\partial t} + (\underline{u} \cdot \nabla) \underline{u}.$$

$$\dots = \frac{\partial \underline{u}}{\partial t} + \nabla \left( \frac{1}{2} \underline{u}^2 \right) + \underline{\omega} \wedge \underline{u}.$$

Now Euler is:

$$\rho \frac{D \underline{u}}{D t} = - \nabla p + \rho \underline{F}.$$

Now consider only external forces derivable from a potential i.e.:

$$\underline{F} = - \nabla V_e.$$

i.e for gravity.

$$V_e = gz$$

i.e  $\underline{F}$  is conservative.

Then:

$$\begin{aligned} \rho \left[ \frac{\partial \underline{u}}{\partial t} + \underline{\omega} \wedge \underline{u} \right] &\approx - \nabla p_a - \rho \nabla \left( \frac{1}{2} \underline{u}^2 \right) - \rho \nabla V_e \\ &= - \nabla H. \end{aligned}$$

where

$$H = p + \frac{1}{2} \rho \underline{u}^2 + \rho V_e$$

In steady flow;

$$\frac{\partial \underline{u}}{\partial t} = 0$$

$$\text{So } \rho(\underline{\omega} \wedge \underline{u}) = -\nabla H.$$


Dot with  $\underline{u}$ :

$$0 = (\underline{u} \cdot \nabla) H.$$

i.e  $\frac{D\underline{u}}{Dt} = 0$


i.e Particle paths are streamlines.

Thus  $H$  is constant on STREAMLINES, -  
BERNOLLI's THEOREM.



H CAN have different values on different streamlines. It sometimes, incorrectly called Bernoulli's constant.

Example:



Important : The surface is connected to the exit by STREAMLINES

Assume the hole is sufficiently small that the flow is steady.

Hence Bernoulli's applies on any streamlines :

$H = \text{Constant}$  (Not necessarily same constant)

Hence :

$$H = p + \frac{1}{2} \rho v^2 + \rho V_e$$


The external potential is  $V_e = gz$  (with level of hole).



28/11/11

## Bernoulli Examples

### Example 1: Draining cylinder



S'line connecting surface to exit.

∴ Can apply Bernoulli on this S'line.

i.e  $P + \frac{1}{2} \rho u^2 + \rho V_e$  is constant on streamline

Hence same at top and bottom.

Now:  $V_e = gz$  ( $z=0$  at level of exit)

Pressure is atmospheric at top and bottom

At top:  $P + \frac{1}{2} \rho u^2 + \rho V_e = P_a + \frac{1}{2} \rho U^2 + \rho g h$ .  
where  $u = U$  at surface.

At bottom:  $P + \frac{1}{2} \rho u^2 + \rho V_e = P_a + \frac{1}{2} \rho v^2 + 0$ .  
where  $u = v$  at exit

Thus  $P_a + \frac{1}{2} \rho U^2 + \rho g h = P_a + \frac{1}{2} \rho v^2$

$$\text{i.e } V^2 = U^2 + 2gh.$$

The mass flux at top is  $\rho U A$ .  
 The mass flux at bottom is  $\rho V a$ .


These are the same so :

$$UA = Va.$$

Thus

$$V^2 = \left(\frac{Va}{A}\right)^2 + 2gh.$$

$$\Rightarrow V^2 \left[1 - \left(\frac{a}{A}\right)^2\right] = 2gh$$



If hole is small  $\frac{a}{A} \ll 1$


$$\text{so } \left(\frac{a}{A}\right)^2 \ll \ll 1$$

Then  $V^2 \approx 2gh$

$$\text{i.e } V = \sqrt{2gh}$$




i.e exactly as for a free-falling particle under gravity :  $\frac{1}{2}\sqrt{2gh} \leq V \leq \sqrt{2gh}$

Torricelli:



### Example 2 : Spinning Cylinder

Consider a cylinder of radius  $a$  in a stream, uniform at infinity with speed  $U$  in the  $x$ -direction. Let the cylinder be spinning so that the circulation about the cylinder is  $K$ :




$$-p\hat{n} = -p\hat{E}$$

We will find the force per unit length on the cylinder. Our unit of area is  $dS = dl \cdot 1$ . Thus total force (per unit length) :

$$= \int -p\hat{n} dS$$

$$= - \int p\hat{E} dl \text{ per unit length.}$$



$$\text{And } dl = a d\theta$$

$$F = - \int_{\theta=-\pi}^{\pi} p\hat{E} a d\theta$$

$$\begin{aligned} \hat{E} &= \cos\theta \hat{i} + \sin\theta \hat{j} \\ \hat{i} &= \cos\theta \hat{i} + \sin\theta \hat{j} \end{aligned}$$

$$= -a \int_{-\pi}^{\pi} p(\cos\theta \hat{i} + \sin\theta \hat{j}) d\theta$$


$$= \Phi \hat{i} + \Psi \hat{j}$$

Where the drag,  $D$  is

$$D = -a \int_{-\pi}^{\pi} p \cos \theta d\theta$$

and the lift  $L$  is

$$L = -a \int_{-\pi}^{\pi} p \sin \theta d\theta.$$



Now all streamline originate upstream + we are taking flow to be steady so we use Bernoulli:

$$\text{Note: } \frac{\partial u}{\partial t} = 0 \iff \text{steady}$$

$p + \frac{1}{2} \rho u^2 = \text{constant on streamline in the absence of external force.}$

At infinity,  $p = p_\infty$ , constant

$$u = U_C.$$

$$\text{So } p + \frac{1}{2} \rho u^2 = p_\infty + \frac{1}{2} \rho U^2$$

$$\text{Anywhere in the flow, } p = p_\infty + \frac{1}{2} \rho U^2 - \frac{1}{2} \rho U_C^2$$

The complex potential for the flow is:

$$\omega(z) = U \left( z + \frac{a^2}{z} \right) - \frac{iK}{2\pi} \operatorname{Log} z.$$

$$\text{So } \frac{dw}{dz} = u + iv$$

$$= U \left( 1 - \frac{a^2}{z^2} \right) - \frac{iK}{2\pi z}$$

$$\text{So } u_r - iu_\theta = e^{i\phi} \frac{dw}{dz}$$

$$= 2iU \sin \phi - \frac{iK}{2\pi a} \quad \text{on } z = ae^{i\phi}.$$

i.e.  $u_r = 0$  as expected  
 $u_\theta = \frac{K}{2\pi a} - 2U \sin \phi \quad \left. \right\} \text{On cylinder}$

Thus:

$$|u| = \sqrt{\frac{K^2}{4\pi} - \frac{4U^2}{\pi a} \sin^2 \phi + U^2 \sin^2 \phi}.$$

$$\text{Now: } \Phi = -a \int_{\theta=-\pi}^{\theta=\pi} \cos \phi \rho d\phi$$

Note that:

- $\times \int_{-\pi}^{\pi} \cos \phi d\phi = 0$
- $\times \int_{-\pi}^{\pi} \cos \phi \sin \phi d\phi = 0$
- $\times \int_{-\pi}^{\pi} \cos \phi \sin^2 \phi d\phi = 0$ .

Thus  $D = 0$  i.e. no drag.

Or: Velocity symmetric before + after  
so pressure same before + after.  $\therefore$  no drag.

Anywhere in the flow:

$$P = P_0 + \frac{1}{2} \rho U^2 - \frac{1}{2} \rho u^2$$

$$\text{Now: } L = -a \int_{-\pi}^{\pi} \sin \theta \, p \, d\theta$$

$$\text{Note: } \int_{-\pi}^{\pi} \sin \theta \, C \, d\theta = 0$$

$$\int_{-\pi}^{\pi} \sin^3 \theta \, d\theta = 0$$

$$\int_{-\pi}^{\pi} \sin^2 \theta \, d\theta = \pi$$

$$L = -a \int_{-\pi}^{\pi} \left( -\frac{1}{2} P \right) \left( -\frac{2 UK}{\pi a} \right) \sin^2 \theta \, d\theta$$

$$= -\rho UK$$

$$\xrightarrow{\quad} \quad \xrightarrow{\quad} \quad \textcircled{UK}$$


i.e. downward force

$$\rho UK \quad (\text{indep of } a)$$


(per unit length).

$$\text{Aside } \underline{u}^2 = \underline{u} \cdot \underline{u} = \underline{u} \cdot \underline{u}$$


Example 3: Open channel flow - flow (down along) a channel that open to the air. e.g. river, aqueduct.



- 1) Rises
- 2) Stays same
- 3) Falls.




Plan view



- 1) Gets deeper, join smoothly
- 2) Gets shallower

Initially, let us consider a channel of constant width  $b$ , and horizontal floor.

Let any changes in the flow be slow in the flow direction.



Let the local depth be  $h$  and local speed  $u$  direction.

By conservation of mass, in steady flow, mass flux across station A must equal mass flux across station B.

$$\text{i.e. } \rho h_1 b_{u1} = \rho h_2 b_{u2}$$

$$\text{i.e. } h_1 u_1 = h_2 u_2.$$

OR; throughout the flow

$$uh = Q, \text{ constant.}$$

i.e.  $Q = uh$ , is constant of the motion.

[Volume flux per unit width i.e dimension:  $L^2 T^{-1}$ ]

Provided the flow is smooth, a particle on the surface stays there i.e. surface is a streamline

Hence we apply Bernoulli there:

Bernoulli (on a surface, a streamline):

$$p + \frac{1}{2} \rho u^2 + \rho V_e \text{ is a constant.}$$

Here:  $p = p_a$ ,  $u = u \hat{i}$ ,  $V_e = g z$ .

Thus:

$$p_a + \frac{1}{2} \rho u^2 + \rho gh = \text{const.}$$

$$\text{i.e. } \frac{1}{2} u^2 + gh = \text{constant.} = gH.$$

where  $H$  is a second constant of the motion.

Dimensions of  $H$  are length.

$H$  is the depth the fluid would occupy were it to come to rest i.e.  $h \rightarrow H$ , if  $u \rightarrow 0$ .

$H$ : "head of the flow".


Thus we have

$$uh = Q$$
$$\frac{1}{2}u^2 + gh = gH.$$

Eliminate  $u$ ,  $u = Q/h$

so  $\frac{Q}{2gh^2} + h = H$ .

Let  $f(h) = \frac{Q^2}{2gh^2} + h$ .



This graph has a single minimum for  $h > 0$  where  $f(h) = 0$

$$\text{i.e. } -\frac{2Q^2}{2gh^3} + 1 = 0.$$

$$\text{i.e. } h = h_m = \left(\frac{Q^2}{g}\right)^{1/3}$$

$$f(h_m) = h_m + \frac{h_m^3}{2h_m} = \frac{3}{2}h_m.$$

-/-

At  $h = h_m$

$$\begin{aligned} h_m^3 &= Q^2/g \\ &= \frac{h_m^2 u_m^2}{g} \end{aligned}$$

$$\text{i.e. } \frac{u_m^2}{gh_m} = 1.$$

-/-

We define the Froude number :


$$F = \frac{u}{\sqrt{gh}}$$

at any point in the flow, then  $F = 1$  when  $h = h_m$ ,  
then  $u < u_m$  so  $F < 1$ . If  $h < h_m$  then  $u > u_m$  so  $F > 1$

Fact : The speed of long waves on shallow water is


$\sqrt{gh}$  (shown in water waves).

So if  $F < 1$ , flow is slower than waves, waves can travel upstream: (Subcritical)




If  $F > 1$ , flow is faster than waves, information cannot travel upstream. (Supercritical)

Supercritical: shallow and fast:



Subcritical: Deep and slow:




These are two flows with same  $Q$  or some  $H$  but different  $h$ .

Example. Now suppose the channel remains constant width but the floor of the channel rises smoothly by an amount  $K$ .

$$r > 0$$

$$r = 0$$

$$r < 0$$



Upstream surface height -  $h_1$ ,


Downstream surface height -  $h_2 + K$

Rise in surface  $r = (h_2 + K) - h_1$ .

1/12/11

-/-

From homework:




$u \rightarrow m$ , as  $x \rightarrow \infty$ .

$$\left(\frac{\pi}{2}m - \pi m\right) + \left(-m\pi + \frac{\pi}{2}m\right)$$

$$= -\pi m.$$

Note also  $u \rightarrow -m$  as  $x \rightarrow -\infty$

-/-



$$\begin{aligned}\text{rise } \Gamma &= \text{new} - \text{old} \\ &= h_2 + k - h_1\end{aligned}$$

Mass flux constant

$$u_1 h_1 = u_2 h_2 \quad (\text{speed} \times \text{fluid depth})$$

Now provided the change is smooth the surface is a streamline - this we can apply Bernoulli

$$p + \frac{1}{2} \rho u^2 + \rho g z = \text{const on surface}$$

Upstream :

$$p + \frac{1}{2} \rho u^2 + \rho g z = p_a + \frac{1}{2} \rho u_i^2 + \rho g h_i$$

Downstream :

$$p + \frac{1}{2} \rho u^2 + \rho g z = p_a + \frac{1}{2} \rho u_i^2 + \rho g (h_2 + k)$$

Not the depth height of surface


$$\text{thus: } \frac{1}{2} \rho u_i^2 + \rho g h_i = \frac{1}{2} \rho u_i^2 + \rho g (h_2 + k).$$

$$\text{i.e. } \frac{u_i^2}{2g} + h_i = \frac{u_i^2}{2g} + h_2 + k.$$

$$\text{i.e. } \frac{Q^2}{2gh_i^2} + h_i = \frac{Q^2}{2gh_2^2} + h_2 + k.$$

$$u_1 h_1 = u_2 h_2 = Q \quad (\text{volume flux / unit width})$$


$$\text{i.e. } f(h_1) = f(h_2) + k, \text{ where } f(h) = \frac{Q^2}{2gh^2} + h.$$



$$f(h_1) - k < f(h_m) ?$$

Subcritical flow  $F < 1$ .

More PE than KE gives up PE to get over barrier i.e surface, drops + flows speed up.



Supercritical flow:  $F > 1$  (\*)

$$f(h_2) + k = f(h_1)$$

↓      ↑      ↗  
 decreases    increases    fixed

Find the sign of the rise  $r$ , algebraically

$$r = h_2 + k - h_1$$

$$\frac{Q^2}{2gh_1^2} + h_1 = \frac{Q^2}{2gh_2^2} + h_2 + k$$

$$r = \frac{Q^2}{2g} \left[ \frac{1}{h_1^2} - \frac{1}{h_2^2} \right]$$

$$= \frac{Q^2}{2gh_1^2 h_2^2} (h_2^2 - h_1^2)$$

Thus  $r > 0$  when  $h_2 > h_1$  and  $r < 0$  when  $h_2 < h_1$



- - -

$$F = \frac{u}{\sqrt{gh}}$$

$$\Rightarrow F^2 = \frac{u^2}{gh}$$

$$= \frac{\frac{1}{2} \rho u^2}{\frac{1}{2} \rho gh}$$


(\*) More KE than PE. To get over barrier gives up some KE to get PE.




Sup.  $F < 1$

Super  $F > 1$ .

If  $k = f(h_i) - f(h_m)$  there are four possibilities.



Symmetric



Symmetric




transition  
(Satisfies  
causality)



Causality shows that smooth transitions are always from sub-critical to supercritical.

5/12/11


Summary of last lecture.



Super  
 $F > 1$   
 $h < h_m$

Sub  
 $F < 1$   
 $h > h_m$

$F > 1$   
Super  
Shallow, fast .



$F < 1$   
Sub  
Deep, slow .



Super  
 $F=1$  at maximum height  
Transition .

-/-

Sub,  $F < 1$

Critical  $F = 1$

Super  $F > 1$

$h_k$


$\uparrow$

$$k > f(h_i) - f(h_m)$$

Transition!

If the obstacle height  $k$  is increased further so  $k > f(h_i) - f(h_m)$  then the upstream flow breaks up, deepens, flux decreases and makes the minimum adjustment to allow water to pass over obstacle i.e. flow at the top of bump is critical i.e.  $F = 1$  when  $k$  is a maximum.

Eg: a weir:




Notice if you know the depth at a weir you know the flux without having to measure speed:

$$\frac{Q^2}{g} = h_m^3$$

$$\Rightarrow Q = (gh_m^3)^{1/2} \quad \text{so } u_m = \sqrt{gh_m} \quad \text{since } F = 1.$$

— —




Remember  
one solution  
may be  
 $h_2 = h$ .


Example : Converging channel

Consider flow through a flat-bottom, horizontal channel of varying width,  $b$ .

Side on : (Elevation)



Top view : (Plan view).



(1) Deepens  
 (2) Stay the same } It depends on  $F$ .  
 (3) Shallow

If  $F > 1$  super  
 $F < 1$  sub.

$$\frac{u}{\sqrt{gh}} = \frac{\frac{1}{2} \rho u^2}{\frac{1}{2} \rho g h} = \frac{KE}{PE}$$

① Conservation of mass:

$$\rho h b u = \rho Q$$

so  $Q = h b u$  is the cinitial volume flux.

② Provided the surface remains smooth, the surface is streamline so we can apply Bernoulli there:

$$P + \frac{1}{2} \rho u^2 + \rho z g = \text{const.}$$

$z$  - height of surface.


$$\text{i.e. } P_a + \frac{1}{2} \rho u^2 + \rho g h = \text{const.}, \quad p = P_a \begin{matrix} \checkmark \text{constant} \\ \text{atmosphere} \\ \text{pressure on} \\ \text{surface} \end{matrix}$$

$$\text{i.e. } \frac{u^2}{2g} + h = H \text{ (constant).}$$

$$\text{Eliminating } u, \quad \frac{Q^2}{2gh^2b^2} + h = H.$$

$$\text{i.e. } (H-h)h^2 = \frac{Q^2}{2gb^2}$$

Write  $(H-h)h^2 = f(h)$ .



Information to draw the curve:

$$f(h) = h^2H - h^3$$

$$f'(h) = 2hH - 3h^2$$

$$\text{so } f'(h) = 0 \text{ if } h=0 \text{ or } h = \frac{3}{2}H$$

At  $h = \frac{3}{2}H$

$$f\left(\frac{3}{2}H\right) = \left(\frac{4}{9} - \frac{8}{27}\right)H^3$$


So at  $h = \frac{2}{3}H$ .

$$\frac{w^2}{2g} = H-h = \frac{1}{3}H.$$


$$\text{So: } \frac{u^2}{gh} = \frac{u^2}{g\left(\frac{2}{3}H\right)} = \frac{\frac{2}{3}H}{\frac{2}{3}H} = 1$$

i.e  $F=1$  when  $h = \frac{2}{3}H$ .

Plan view:




$b$  decreasing  $\Rightarrow \frac{Q^2}{2gb^2}$  increasing.



Flows moves towards critical at a constriction.


Aside:



Example 5 : Expanding channel,

①  $SUB \quad F < 1, h > \frac{3}{2} H.$

Plan :



Elevation :

$F < 1$

$F < 1$




River flowing into reservoir:

Then  $h \uparrow H$  as  $b \rightarrow \infty$

i.e.  $\frac{Q^2}{2g^2} = 0.$ ,  $u = 0$  (stagnant)

River smoothly enters stagnant reservoir.

② : SUPER  $F > 1$ ,  $h < \frac{3}{2} h$  fast shallow.



Unsteady Non-smooth jump.

Here  $h \downarrow 0$  as  $b \rightarrow 0$ . River cannot smoothly join reservoir.

$$F = \frac{u}{\sqrt{gh}} = \frac{\text{Flow speed}}{\text{Wave speed}}, F > 1 \text{ supercritical}$$

$$M = \frac{u}{a} = \frac{\text{Flow speed}}{\text{Speed of sound}} \quad M > 1 \text{ Supersonic} \\ M < 1 \text{ Subsonic}$$

Sonic boom: Spontaneous jump from  $M > 1$  to  $M < 1$   
(as this gives out energy - sound)

Only have hydraulic jump from  $F > 1$  to  $F < 1$   
as this gives out energy.

-/-


## Water waves

-Free surface gravity waves.

-Water will take the flow to be 2D, irrotational, inviscid, incompressible.

Thus we have a streamfunction and a velocity potential and complex potential.

i.e  $\exists \Phi$  st  $\underline{u} = \nabla \Phi$



Irrotational so  $\nabla^2 \Phi = 0$ .



Impermeable  $\underline{u} \cdot \hat{n} = 0$ .

i.e  $\frac{\partial \Phi}{\partial n} = 0$  i.e  $\frac{\partial \Phi}{\partial y} = 0$

1) We have  $\exists \Phi$  st  $\underline{u} = \nabla \Phi$ .

let the unknown, free surface by  $y = \eta(x, t)$ .

then in the fluid,  $-h < y < \eta$ , governing equation is  $\nabla^2 \Phi = 0$ .

On lower boundary  $v = 0$  on  $y = -h$ .

We need the b.c's on the surface (because  $\eta$  is

unknown). The two b.c's are the KINEMATIC and DYNAMIC conditions.

DYNAMICS (forces) :  $P = P_a$  on  $y = \eta$

KINEMATICS : Particles on the surface remains on the surface.

Kinematics: i.e: on the surface ( $y = \eta$ )

$$y = \eta(x, t) \quad \forall x, t.$$

$$\text{i.e } y - \eta(x, t) = 0.$$

Following a particle on surface:

$$\frac{D}{Dt} (y - \eta(x, t)) = 0 \quad \text{on } y = \eta \quad \forall x, t.$$

$$\text{i.e } v - \frac{D\eta}{Dt} = 0 \quad \text{on } y = \eta$$

$$\text{i.e } v = \frac{\partial \eta}{\partial t} + u \frac{\partial \eta}{\partial x} \quad \text{on } y = \eta(x, t).$$

$$\text{i.e } \frac{\partial \Phi}{\partial y} = \frac{\partial \eta}{\partial t} + \frac{\partial \Phi}{\partial x} \frac{\partial \eta}{\partial x} \quad \text{on } y = \eta(x, t)$$

-kinematics-b.c.

To deal with the dynamic conditions on pressure we would like to use Bernoulli. But the flow must be STEDY i.e.  $\frac{\partial \mathbf{u}}{\partial t} \equiv 0$  for the form of Bernoulli up to now. We need a new Bernoulli for unsteady flow.

Remember :

$$\frac{D\mathbf{u}}{Dt} = -\frac{1}{\rho} \nabla p + \mathbf{F}$$

$$\text{i.e. } \frac{\partial \mathbf{u}}{\partial t} + (\mathbf{u} \cdot \nabla) \mathbf{u} = -\frac{1}{\rho} \nabla p - \nabla V_e.$$

Note:  $\mathbf{F} = -\nabla V_e$  (a conservative force)

$$\text{i.e. } \frac{\partial \mathbf{u}}{\partial t} + \nabla \left( \frac{1}{2} \mathbf{u}^2 \right) + (\boldsymbol{\omega} \wedge \mathbf{u}) = -\frac{1}{\rho} \nabla p - \nabla V_e$$

[last time : steady, dotted with  $\mathbf{u}$  to get rid of  $\boldsymbol{\omega} \wedge \mathbf{u}$ ].

this time : Use the fact that irrotational,  $\mathbf{u} = \nabla \phi$  and  $\boldsymbol{\omega} = 0$ .

Thus :

$$\frac{D\phi}{Dt} + \nabla \left( \frac{1}{2} \mathbf{u}^2 \right) = -\frac{1}{\rho} \nabla p - \nabla V_e.$$

$$\text{i.e. } \nabla \left[ \frac{\partial \phi}{\partial t} + \frac{1}{2} |\nabla \phi|^2 + \frac{1}{\rho} p + V_e \right] = 0.$$

$$\text{i.e. } \rho \left( \frac{\partial \phi}{\partial t} + \frac{1}{2} |\nabla \phi|^2 \right) + p + \rho V_e = G(t).$$

)

New Benoulli!

8/12/11

Water waves:



Equation:  $\nabla^2 \phi = 0$  [ $u = \nabla \phi$ ,  $\nabla \cdot u = 0$ ].

Lower B.C.:  $\frac{\partial \phi}{\partial y} = 0$ ,  $y = -h$ .

Upper B.C.: Kinematics -  $v = \frac{D\eta}{Dt}$  on  $y = \eta$

i.e.  $\frac{\partial \phi}{\partial y} = \frac{\partial \eta}{\partial t} + \frac{\partial \phi}{\partial x} \frac{\partial \eta}{\partial x}$  on  $y = \eta$ .

Dynamic:  $p = p_a$  on  $y = \eta$ .

Bernoulli (time-dep, irrotational).

$$\rho \frac{\partial \phi}{\partial t} + \frac{1}{2} \rho |\nabla \phi|^2 + p + \rho V_e = F(t).$$

The restoring force is gravity so  $V_e = gy$

$$\text{Thus: } \rho \frac{\partial \phi}{\partial t} + \frac{1}{2} \rho |\nabla \phi|^2 + p + \rho gy = F(t).$$

$F(t)$  can be absorbed into  $\Phi$ .

Redefine  $\hat{\Phi} = \Phi - \rho \int^t F(\tau) d\tau$ .

then  $\nabla \hat{\Phi} = \nabla \Phi = \underline{u}$ .

and  $\rho \frac{\partial \hat{\Phi}}{\partial t} = \rho \frac{\partial \Phi}{\partial t} - F(t)$ .

Thus w.l.o.g we can take  $F \equiv 0$ , [Since if  $F \neq 0$  we can redefine  $\Phi$  as above].

Hence everywhere in the flow:

$$\rho \frac{\partial \Phi}{\partial t} + \frac{1}{2} \rho |\nabla \Phi|^2 + \rho gy + p = 0.$$

### UNSTEADY BERONOUlli

On surface,  $y = \eta$  and  $p = p_a$  (constant)

$$\text{Thus: } \rho \frac{\partial \Phi}{\partial t} + \frac{1}{2} \rho |\nabla \Phi|^2 + \rho g \eta = p_a \text{ (constant)}$$

By the above argument, can absorb  $p_a$  (constant) into  $\Phi$  so we have the dynamic conditions:

$$\frac{\partial \Phi}{\partial t} + \frac{1}{2} |\nabla \Phi|^2 + gy = 0 \text{ on } y = \eta.$$

Dynamic B.C.

Equation Laplace:  $\nabla^2 \phi = 0$ .

Lower B.C:  $\frac{\partial \phi}{\partial y} = 0$  on  $y = -h$ .

Upper BC


• Kinematic:  $\frac{\partial \phi}{\partial y} = \frac{\partial y}{\partial t} + \frac{\partial \phi}{\partial x} \frac{\partial y}{\partial x}$  on  $y = \eta$

• Dynamic:  $\frac{\partial \phi}{\partial t} + \frac{1}{2} |\nabla \phi|^2 + gy = 0$  on  $y = \eta$

$\eta(x, t)$  is unknown, Full, Non-linear, Surface water pattern.

To make progress we "linearise", i.e. we consider waves of infinitesimal amplitude,  $0 < \epsilon \ll 1$ .

i.e. we take  $y(x, t)$  to be of order  $\epsilon$ .



We expect velocities and so  $\phi$  to be  $\epsilon$  also.

Kinematics B.C:  $\frac{\partial \phi}{\partial y} = \frac{\partial y}{\partial t} + \frac{\partial \phi}{\partial x} \frac{\partial y}{\partial x}$

$\epsilon$        $\epsilon \cdot \epsilon$   
i.e.  $\epsilon$ ,       $\epsilon : \epsilon^2$   
or 1,      1 :  $\epsilon$

Thus, in limit  $\epsilon \rightarrow 0$  the final term disappear.

We have  $\frac{\partial \Phi}{\partial y} = \frac{\partial \eta}{\partial \epsilon}$  on  $y = \eta$  (linear).  
(with error of order  $\epsilon$ )

Notice for any function  $f(y)$ .

$$f(\epsilon) = f(0) + \epsilon f'(0) + \frac{1}{2} \epsilon^2 f''(0) + \dots = f(0) \\ (\text{with error of order } \epsilon).$$

This can move BC from  $y = \eta$  (of order  $\epsilon$ )  
to  $y = 0$  with error of order  $\epsilon$ . Thus we have:

$$\frac{\partial \Phi}{\partial y} = \frac{\partial \eta}{\partial t} \quad \text{on } y = 0. \quad (\text{Now linear on known surface})$$

Dynamic BC:

$$\frac{\partial \Phi}{\partial \epsilon} + \frac{1}{2} \epsilon \nabla \Phi^2 + g\eta = 0 \quad \text{on } \begin{array}{c} y = \eta \\ \downarrow \\ y = 0 \end{array}$$

Linearised BC:

$$\frac{\partial \Phi}{\partial \epsilon} + g\eta = 0 \quad \text{on } y = 0.$$

(Linear, on known surface)

— / —


Summary: Linear water waves.

Equation:  $\nabla^2 \phi = 0$  (already linear).

Lower BC:  $\frac{\partial \phi}{\partial y} = 0$  on  $y = -h$  (already linear, already on known surface).

Upper BC:  $\frac{\partial \phi}{\partial y} = \frac{\partial y}{\partial t}$  } on  $y = 0$ .

$$\frac{\partial \phi}{\partial t} + gy = 0.$$



- Wavelength  $\lambda$ ; distance between two successive crests.
- Period  $T$ ; time between arrival at a given point of successive crests.
- Speed  $c$ ; at which the coast advance.

$$[c = \lambda/T]$$



Any (within reason) periodic function can be expressed a sum of sines and cosines. Thus it is sufficient to consider:

$$\eta = A \sin \left[ \frac{2\pi}{\lambda} [x - ct] \right]$$

- waves with amplitude  $A$ , wavelength  $\lambda$ , speed  $c$ , to the right (as period  $T = \lambda/c$ )

12/12/11

## Water Waves

Summary:

- 1) Irrotational, Inviscid, Incompressible  $\Rightarrow$  New Bernoulli  
 $\Rightarrow$  Fully non-linear equation set.
- 2) Infinitesimal waves, linearised  $\Rightarrow$  linear wave equations

$$\text{Gov. Eqn: } \nabla^2 \phi = 0.$$

$$\text{Lower BC: } \frac{\partial \phi}{\partial y} = 0 \text{ on } y = -h.$$

Upper BC:


- Kinematics:  $\frac{\partial \phi}{\partial y} = \frac{\partial \eta}{\partial t}$  on  $y = 0$ .

- Dynamic:  $\frac{\partial \phi}{\partial t} + g\eta = 0$  on  $y = 0$

} linear fixed domain  
 $0 \geq y \geq -h$ .

Linear, constant coefficient: all solutions are sums or integrals of sinusoids.

Look for solutions of the form:



$$\eta(x, t) = \epsilon \sin \left[ \frac{2\pi}{\lambda} (x - ct) \right] = \epsilon \sin [k(x - ct)]$$

$$\dots = E \sin [kx - \omega t]$$

where:

$E$  - Amplitude.

$\lambda$  - Wavelength

$c$  - Speed (phase speed).

$$\text{Period : } T = \lambda/c$$

$$\text{Wavenumber : } K = 2\pi/\lambda, \text{ no of waves in distance } 2\pi.$$

$$\text{Frequency : } \omega = Kc = 2\pi/T, c = \omega/K.$$

We wish to find  $\phi$ .

$$\begin{aligned} \text{On the surface } \frac{\partial \phi}{\partial t} &= -gy \\ &= -Eg \sin [kx - \omega t] \end{aligned}$$

$$\text{Thus } \phi \text{ behaves like } \frac{-Eg}{\omega} \cos [kx - \omega t] \text{ on } y=0.$$

$$\nabla^2 \phi = 0 \quad ①$$

$$\frac{\partial \phi}{\partial y} = 0, y = -h. \quad ②$$

$$\frac{\partial \phi}{\partial y} = \frac{\partial \phi}{\partial t} \text{ on } y = 0. \quad ③$$

$$\frac{\partial \phi}{\partial t} + gy = 0 \text{ on } y = 0 \quad ④$$

$$\text{Equivalently: } \frac{\partial \phi}{\partial y} = \frac{\partial \psi}{\partial t}$$

$$= -\varepsilon \omega \cos[kx - \omega t] \text{ on } y=0.$$

Both of these say that  $(x, t)$  behaviour of  $\phi(x, y, t)$  is like  $\cos(kx - \omega t)$ .

Look for a solution

$$\phi(x, y, t) = -\varepsilon \omega Y(y) \cos(kx - \omega t)$$

$$\text{Then } \frac{\partial \phi}{\partial y} = -\varepsilon \omega Y'(y) \cos(kx - \omega t).$$

$$\text{But on } y=0, \frac{\partial \phi}{\partial y} = \frac{\partial \psi}{\partial t} = -\varepsilon \omega \cos(kx - \omega t).$$

Thus require :  $Y'(0) = 1$  satisfies ②

Similarly for  $\frac{\partial \phi}{\partial y} = 0$  on  $y=-h$ , for all  $x, t$ .

$$Y'(-h) = 0 \text{ satisfies ③}$$

The governing eqn is

$$\frac{\partial^2 \phi}{\partial x^2} + \frac{\partial^2 \phi}{\partial y^2} = 0.$$

$$\frac{\partial^2 \phi}{\partial x^2} = +\varepsilon \omega k^2 Y(y) \cos(kx - \omega t).$$

$$\frac{\partial^2 \phi}{\partial y^2} = -\varepsilon \omega k^2 Y''(y) \cos(kx - \omega t).$$

Addition:

$$0 = Y'' - k^2 Y.$$

Thus we have:

$$(\alpha) Y'' - k^2 Y = 0.$$

$$(\beta) Y(0) = 1$$

$$(\gamma) Y(-h) = 0$$

(Notice no x's, t's, ω's cos's, sin's)  
 (justifies form of  $\phi$  assumed)

One form of Complementary Function is:

$$Y(y) = C e^{ky} + D e^{-ky}$$

or  $Y'(y) = E \cosh ky + F \sinh ky.$

But best is:

$$Y(y) = A \cosh [k(y+h)] + B \sinh [k(y+h)].$$

(satisfies  $(\alpha)$ )

This gives:

$$Y'(y) = A k \sinh [k(y+h)] + B k \cosh [k(y+h)].$$

We require:

$$Y'(-h) = 0, \text{ so } B = 0.$$

It remains to require

$$Y'(0) = 1 \text{ so } Ak \sinh kh = 0.$$

Thus  $Y(y) = \frac{\cosh [k(y+h)]}{\sinh kh}.$

(Solves (α), (β), (γ))

Thus gives:

$$\phi(x, y, t) = -\frac{Ew \cosh [k(y+h)]}{\sinh kh} \cos [kx - ct]$$

$$= -\frac{Ec \cosh [k(y+h)]}{\sinh kh} \cos [k(x - ct)]$$

We still have a condition to satisfy:-

$$\frac{\partial \phi}{\partial t} + gy = 0 \text{ on } y=0.$$

Here:

$$-Ec \coth(kh) [ws \sin(kx - wt)] + Eg \sin[kx - wt] = 0 \text{ for } x;$$

Since time  $t$  is  $\epsilon$ , divide by  $\sin(kx - \omega t)$ .

$$-\omega c \coth(kh) + g = 0.$$

i.e.  $-\omega^2 \coth(kh) + gk = 0$ .  $c = \omega/k$ .


i.e.  $\omega^2 = gk \tanh(kh)$

i.e.  $k$  and  $\omega$  are NOT independent.

Thus  $c^2 = \frac{g}{k} \tanh(kh)$

$$= \frac{g\lambda}{2\pi} \tanh\left[\frac{2\pi h}{\lambda}\right]$$

So waves of different wavelength travel at different speed i.e. wave disperse.



$$u_{ff} = c^2 u_{xx}$$

"the speed" of the waves NOT DISPERSIVE.

Nothing to do with λ  $c^2 = \frac{\tau}{\rho}$

Sound waves ALL travel at "speed of sound"  
DISPERSIVE.

Electromagnetic radiation : - speed "c" - unique  
 (for given medium) NON - DISPERATIVE.

$$\frac{c^2}{gh} = \frac{\tanh(kh)}{kh} = \frac{\tanh\left(\frac{2\pi h}{\lambda}\right)}{(2\pi h/\lambda)}$$



Information about the curve in order to draw it.

$$\Theta = \lambda/2\pi h$$

$$\frac{c^2}{gh} = \Theta \tan\left(\frac{1}{\Theta}\right)$$

$$\text{for } \Theta \gg 1, \frac{c^2}{2g} \sim \Theta \cdot \frac{1}{\Theta} = 1.$$

$$\text{for } \Theta \ll 1, \frac{c^2}{gh} \sim \Theta.$$

-/-


Long waves travel faster with speed  $c = \sqrt{gh}$

Long waves on shallow water are non-dispersive : all have speed  $\sqrt{gh}$ .

Short waves on deep water are dispersive on deep water


$$\frac{\lambda}{2\pi h} \ll 1, \frac{c^2}{gh} \rightarrow \frac{\lambda}{2\pi h} \text{ i.e } c \rightarrow \left(\frac{gh}{2\pi}\right)^{\frac{1}{2}} = (2\pi)^{-\frac{1}{2}} \sqrt{gh}.$$

—/—



Ship speed water proportional to square root of length.

Notice in flow with  $u > c$  i.e.  $u > \sqrt{gh}$  all waves swept downstream i.e. supercritical. ( $F = u/\sqrt{gh} = M$ )  
(c.f. Mach no.  $M = u/c$  where  $c$  speed sound)



—/—

## Particle Paths in a water wave

$$\frac{dx}{dt} = u(x, y, t).$$

But the amplitude of the motion is of order  $\epsilon$  i.e particles only move an amount  $\epsilon$ .

So write :

$$x = x_0 + \epsilon X$$

$$y = y_0 + \epsilon Y.$$

$$\text{Then } \frac{dx}{dt} = \epsilon \frac{dX}{dt}$$

$$= u(x, y, t)$$

$$= \frac{\partial \phi}{\partial x}(x_0 + \epsilon X, y_0 + \epsilon Y, t).$$

$$= \frac{\partial \phi}{\partial x}(x_0, y_0, t) + \cancel{\epsilon \times \frac{\partial^2 \phi}{\partial x^2}} + \cancel{\epsilon \times \frac{\partial^2 \phi}{\partial x \partial y}} \epsilon$$

Thus to order  $\epsilon^2$

$$\epsilon \frac{dX}{dt} = \frac{\partial \phi}{\partial x}(x_0, y_0, t)$$

$$\epsilon \frac{dY}{dt} = \frac{\partial \phi}{\partial y}(x_0, y_0, t).$$

$$\phi = -\epsilon C \frac{\cosh[k(y+h)]}{\sinh kh} \cos[kx - wt]$$

So :

$$\left. \frac{\partial \phi}{\partial x} \right|_{x_0, y_0} = +\epsilon k C \frac{\cosh[k(y_0+h)]}{\sinh kh} \sin(kx_0 - wt)$$

$$\left. \frac{\partial \phi}{\partial y} \right|_{x_0, y_0} = -\epsilon k C \frac{\sinh[k(y_0+h)]}{\sinh kh} \cos(kx_0 + wt)$$

↑  
indep of  $x, y$  i.e  $X, Y$ .

$$\text{Thus } \frac{dX}{dt} = \omega \frac{\cosh[k(y_0+h)]}{\sinh kh} \sin[kx_0 - wt]$$

$$\text{So : } X = \frac{\cosh[k(y_0+h)]}{\sinh kh} \cos[kx_0 - wt]$$

(Absorbs constant  
into  $x_0$ )

$$\text{and } Y = \frac{\sinh[k(y_0+h)]}{\sinh kh} \sin(kx_0 - wt)$$

$$\alpha = \frac{\cosh[k(y_0+h)]}{\sinh kh}, \beta = \frac{\sinh[k(y_0+h)]}{\sinh kh}$$

$$\text{Hence : } \frac{X}{\alpha} = \cos(kx_0 - wt), \frac{Y}{\beta} = \sin(kx_0 - wt)$$


$$\text{So } \left(\frac{X}{\alpha}\right)^2 + \left(\frac{Y}{\beta}\right)^2 = 1, \alpha > \beta \text{ so major axis is horizontal.}$$

Ellipses with vertical semi-axes.

$$\beta = \frac{\sinh[k(y_0 + h)]}{\sinh(kh)}$$

Also horizontal - axes.


$$\alpha = \frac{\cosh[k(y_0 + h)]}{\sinh(kh)}$$



Particle goes around clockwise

When  $\gamma$  is largest,  $\frac{\partial \phi}{\partial x}$  is the largest i.e.  $u$  is largest.

At top,  $y_0 = 0$ ,  $\alpha = \coth kh$ ,  $\beta = 1$  so  $-1 \leq \gamma \leq 1$ .



- exactly the amplitude of the wave  $y = X$  here
- particle move toward at the crest + backward at the trough.

At bottom  $y_0 = -h$ ,  $\alpha = -\operatorname{cosech} kh$ ,  $\beta = 0$ ,  $Y \equiv 0$ .

$$\frac{2e \operatorname{cosech} kh}{k} \quad y = -h$$

base

$h \rightarrow \infty$ , Use  $\phi = Ae^{-ky}$

Much easier

$$\frac{\lambda}{2\pi h}$$



15/12/11

$$y = \eta(x, t)$$



$$y = -h$$

$$c = \frac{1}{\sqrt{2\pi}} \sqrt{gT}$$

short waves.  
deep water

$$\frac{\lambda}{2\pi h} \ll 1$$


$$c = \sqrt{gh}$$

long waves  
shallow waves

$$\frac{\lambda}{2\pi h} \gg 1$$



$$\delta g$$



infinitely deep water  $h \rightarrow \infty$   
 $\Rightarrow$  all waves short.

$$\text{Take } \eta = \epsilon \sin(kx - \omega t)$$

$$\phi = -\epsilon \omega \cos(kx - \omega t) Y(y).$$

Kinematic :  $Y'(0) = 1$  as before.

Lower bc :  $Y \rightarrow 0$  as  $y \rightarrow -\infty$

Equation  $Y'' - kY = 0$   
 CF  $Y = C e^{ky} + D e^{-ky}$ .

Bdd as  $y \rightarrow -\infty \Rightarrow D = 0$ .

But  $Y'(0) = 1$

so  $C = 1/k$

and  $\boxed{\phi = \frac{-\epsilon \omega \cos(kx - \omega t)}{k} e^{ky}}$

$$= -\epsilon c \cos(kx - \omega t) e^{ky}$$

Infinite depth  
velocity potential  
( $h \rightarrow \infty$ )

Substitute in Dynamic condition and find

$$c^2 = g/h$$

$$c^2 = \frac{gl}{2\pi}$$

$$\boxed{c = \frac{1}{\sqrt{2\pi}} \sqrt{gl} \quad \text{as expected.}}$$

$$\frac{l}{2\pi h} \rightarrow 0.$$

~~Kinematics~~

$$\frac{\partial \phi}{\partial y} = \frac{\partial \eta}{\partial t}$$

~~Dynamic~~

$$\frac{\partial \phi}{\partial t} + g\eta = 0$$

~~Particle path are Circles~~

~~Radius  $e^{ky_0}$~~


Reflected waves?

$$\eta_1(x, t) = \epsilon \sin(kx - \omega t)$$

$$\phi_1(x, y, t) = -\epsilon c \cos(kx - \omega t) e^{ky}$$

$$\eta_2(x, t) = \epsilon \sin(kx - \omega t)$$

$$\phi_2(x, t) = +\epsilon c \cos(kx - \omega t) e^{ky}$$



Add them:

$$\eta = \eta_1 + \eta_2 = \epsilon [\sin(kx - \omega t) + \sin(kx + \omega t)]$$

and

$$\phi = \phi_1 + \phi_2 = \epsilon c e^{ky} [\cos(kx - \omega t) - \cos(kx + \omega t)]$$

$$= -2\epsilon ce^{ky} \sin kx \sin wt$$

Particle path

$$\frac{dx}{dt} = u = \frac{\partial \phi}{\partial x}$$

$$= -2\epsilon ck \cos kx e^{ky} \sin wt$$

$$\frac{dy}{dt} = v = \frac{\partial \phi}{\partial y}$$

$$= -2\epsilon ck e^{ky} \sin kx \sin wt$$

Now:

$$\frac{dy}{dx} = \frac{\frac{dy}{dt}}{\frac{dx}{dt}}$$

$$= \frac{\sin kx}{\cos kx}$$

$$= \tan kx$$


$$[\text{so } y = \frac{1}{k} \ln(\sec kx)]$$

To lowest order


$$\begin{aligned} x &= x_0 + \epsilon x' \\ y &= y_0 + \epsilon y' \end{aligned}$$

$$\frac{dy}{dx} = \tan kx_0 + O(\epsilon)$$

Lies og slope  $\tan kx_0$ .



$$kx_0 = \frac{\pi}{2}$$



$$x_0 = \frac{\pi}{2k}$$

- - -

$$\frac{2\pi}{\lambda} x_0 = \frac{\pi}{2}$$

$$\Rightarrow x_0 = \frac{1}{4} \lambda$$

- / -



## 2.5 Hydraulic jump

(q ≈ u here)

Consider the jump as shown in a channel of width  $d$  and horizontal bed. The suffixes 1 and 2 refer to conditions before and after the jump, and we consider the fluid bounded by  $A_1B_1$  and  $A_2B_2$ . In time  $\delta t$ , the fluid has moved to the region bounded by  $A'_1B'_1$  and  $A'_2B'_2$ . Then at the two locations we have the following quantities.

Height	$h_1$	$h_2$
Mean velocity	$q_1$	$q_2$
Pressure	$\rho g(h_1 - z)$	$\rho g(h_2 - z)$
Thickness	$q_1 \delta t$	$q_2 \delta t$
Mass	$m_1 = \rho d h_1 q_1 \delta t$	$m_2 = \rho d h_2 q_2 \delta t$
Conservation of mass shows that	$m_1 = m_2$	$Q$ is the same at 1 and 2
Flow rate	$dh_1 q_1 = Q$	$dh_2 q_2 = Q$
Momentum	$m_1 q_1$	$m_2 q_2$
Force in flow direction	$F_1 = \int_0^{h_1} \rho g d(h_1 - z) dz$ $= \frac{1}{2} \rho g d h_1^2$	$F_2 = - \int_0^{h_2} \rho g d(h_2 - z) dz$ $= - \frac{1}{2} \rho g d h_2^2$

Force equals rate of change of momentum gives  $F_1 - F_2 = (m_2 q_2 - m_1 q_1)/\delta t$  or  $\frac{1}{2} \rho g d(h_1^2 - h_2^2) = \rho Q(q_2 - q_1) = \frac{\rho Q^2}{d} \left( \frac{1}{h_2} - \frac{1}{h_1} \right)$ . Hence either  $h_2 - h_1 = 0$ , in which case the flow is continuous and there is no jump, or

$$h_1 h_2 (h_1 + h_2) = \frac{2Q^2}{gd^2}$$

For given upstream conditions this equation determines  $h_2$  and hence  $q_2 = Q/dh_2$ .

Kinetic energy	$\frac{1}{2} m_1 q_1^2$	$\frac{1}{2} m_2 q_2^2$
----------------	-------------------------	-------------------------

Work done by force	$F_1 q_1 \delta t$	$F_2 q_2 \delta t$
--------------------	--------------------	--------------------

If  $D\delta t$  is the amount of kinetic energy lost in time  $\delta t$ , conservation of energy gives

$$(F_1 q_1 - F_2 q_2) \delta t = \frac{1}{2} m_2 q_2^2 - \frac{1}{2} m_1 q_1^2 + D\delta t,$$

from which it follows that

$$D = \frac{1}{2} \rho g d(h_1^2 q_1 - h_2^2 q_2) + \frac{1}{2} \rho Q(q_1^2 - q_2^2) = \frac{1}{2} \rho g Q(h_1 - h_2) + \frac{\rho Q^3}{2d^2} \left( \frac{1}{h_1^2} - \frac{1}{h_2^2} \right)$$


or

$$D = \frac{1}{2} \rho g Q \frac{(h_2 - h_1)^3}{2h_1 h_2}$$

Since  $D \geq 0$ ,  $h_2 \geq h_1$ . In a hydraulic jump, the level of the water rises and the speed falls. For the flow upstream,

$$\frac{q_1^2}{gh_1} - 1 = \frac{Q^2}{gd^2 h_1^3} - 1 = \frac{h_1 h_2 (h_1 + h_2)}{2h_1^2} - 1 = \frac{(h_2 - h_1)(h_2 + 2h_1)}{2h_1^2},$$

## Energy



From mass & momentum conservation  
we have shown that

$$h_1 h_2 (h_1 + h_2) = \frac{2Q^2}{gd^2} \quad (1)$$

Work done at A = force  $\times$  distance, and distance =  $u_1 s t$  at all heights

Force = pressure, integrated over area =  $\rho g(h_1 - s)$  integrated over area (okay  $P_a = 0$ ).

$$\text{Hence force} = \frac{1}{2} \rho g h_1^2 d$$

$$\text{Thus work done at A} = \frac{1}{2} \rho g h_1^2 u_1 s t = \frac{1}{2} \rho g Q s t \cdot h_1$$

$$\text{Similarly, work done at B} = -\frac{1}{2} \rho g Q s t \cdot h_2 \quad (\text{since displacement in opposite dirn. to force})$$

$$\text{Thus net work done on fluid} = \frac{1}{2} \rho g Q s t (h_1 - h_2).$$

Thus net work done on fluid =  $\frac{1}{2} \rho u_1^2 / \text{unit volume}$ .

$$\text{KE in at A} = \frac{1}{2} \rho u_1^2 / \text{unit volume}$$

$$\therefore \text{Total KE in at A} = \frac{1}{2} \rho u_1^2 Q s t.$$

$$\text{PE} = \rho g s / \text{unit volume}$$

$$\therefore \text{PE in at A} = \frac{1}{2} \rho g h_1^2 d u_1 s t = \frac{1}{2} \rho g h_1 Q s t \quad (\text{integrates from } 0 \text{ to } h_1)$$

$$\therefore \text{Total energy in at A} = \frac{1}{2} \rho Q s t (u_1^2 + g h_1)$$

$$\therefore \text{Total energy out at B} = \frac{1}{2} \rho Q s t (u_2^2 + g h_2)$$

Similarly, total energy out at B = Energy In - Energy Out

$$\text{Energy lost} = \text{Work done} + \text{Energy In} - \text{Energy Out}$$

$$= (\rho Q s t) \left[ g(h_1 - h_2) + \frac{1}{2}(u_1^2 - u_2^2) \right]$$

$$\text{But } u_1^2 = Q^2/h_1^2 d^2 = \frac{g h_2}{2 h_1} (h_1 + h_2) \text{ by (1)}$$

$$\text{and } u_2^2 = \frac{g h_1}{2 h_2} (h_1 + h_2)$$

$$\text{Thus lost energy} = \frac{\rho g Q s t}{4 h_1 h_2} \left[ (h_1 + h_2) h_2^2 - (h_1 + h_2) h_1^2 + 4 h_1 h_2 (h_1 - h_2) \right]$$

$$= \frac{\rho g Q s t}{4 h_1 h_2} (h_2 - h_1)^3$$

For energy to be lost,  $h_2 > h_1$  i.e. an upward jump.