Network Working Group K. Kompella Request for Comments: 3970 Juniper Networks Category: Standards Track January 2005

A Traffic Engineering (TE) MIB

Status of This Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

Copyright Notice

Copyright (C) The Internet Society (2005).

Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in the Internet community. In particular, it describes managed objects for Traffic Engineered (TE) Tunnels; for example, Multi-Protocol Label Switched Paths.

Table of Contents

| 1. | Introduction | 2 |
|------|---|----|
| | 1.1. Specification of Requirements | 2 |
| 2. | The Internet-Standard Management Framework | 2 |
| 3. | Overview of the MIB Module | 2 |
| | 3.1. Traffic Engineering Information | 3 |
| | 3.2. Traffic Tunnel Information | 3 |
| | 3.3. Path Information | 3 |
| | 3.4. Hop Information | 4 |
| | 3.5. Relationship with Other MIB Modules | 4 |
| 4. | Creating, Modifying, and Deleting a TE Tunnel | |
| 5. | MIB Specification | 5 |
| 6. | References | 40 |
| | 6.1. Normative References | 40 |
| | 6.2. Informative References | 40 |
| 7. | Security Considerations | 41 |
| Ackı | nowledgments | 42 |
| Autl | chor's Address | 43 |
| Ful | .l Copyright Statement | 44 |

Kompella Standards Track [Page 1]

1. Introduction

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in the Internet community. In particular, it describes managed objects for Traffic Engineered (TE) Tunnels; for example, Multi-Protocol Label Switched Paths ([7], [8]). The MIB module defined by this memo allows one to configure TE Tunnels, to assign one or more paths to a Tunnel, and to monitor operational aspects of the Tunnel, such as the number of octets and packets that have passed through the Tunnel.

As it stands, this MIB module can only be used to configure or monitor a TE Tunnel at its ingress. The ingress is then expected to use some protocol (such as RSVP-TE) to signal the other routers in the path the information they need to set up the tunnel. The extension of this module for use at other points of a Tunnel is for further study.

1.1. Specification of Requirements

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in RFC 2119 [1].

2. The Internet-Standard Management Framework

For a detailed overview of the documents that describe the current Internet-Standard Management Framework, please refer to Section 7 of RFC 3410 [8].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. MIB objects are generally accessed through the Simple Network Management Protocol (SNMP). Objects in the MIB are defined using the mechanisms defined in the Structure of Management Information (SMI). This memo specifies a MIB module that is compliant to the SMIv2, which is described in STD 58, RFC 2578 [2], STD 58, RFC 2579 [3] and STD 58, RFC 2580 [4].

3. Overview of the MIB Module

The Traffic Engineering MIB module consists of four parts:

- 1) Traffic Engineering information,
- 2) a table of Traffic Engineering Tunnels,
- 3) a table of Paths that tunnels take, and
- 4) a table of Hops that make up a tunnel path.

The MIB module also has statements for minimal and full compliance.

The following subsections give an overview of each part. All objects are mandatory. For minimal compliance, all objects MAY be implemented read-only; for full compliance, all objects must be implemented to their stated MAX-ACCESS capabilities. Notifications are optional.

3.1. Traffic Engineering Information

This part contains information about the Link State Protocols used to carry TE information, the signaling protocols used to set up Traffic Tunnels, the number of Traffic Tunnels that have been configured and that are operational, and a mapping of Administrative Group (called Resource Classes in [7]) numbers to names.

3.2. Traffic Tunnel Information

This part contains a table of Traffic Tunnels and information about each one. This information includes the Tunnel name, its configuration information, its operational information, and the active path(s) that the Tunnel takes.

Configuration information includes the end points of the Traffic Tunnel, and the number of configured paths for the Traffic Tunnel.

Operational information includes the current state (up/down), the count of octets and packets sent on the Traffic Tunnel, how long it has been up, and how many state transitions the Traffic Tunnel has had.

Operational path information includes the number of operational paths, the number of path changes, and when the last path change was.

3.3. Path Information

A Tunnel is a logical entity. An instantiation of a Tunnel is one or more Paths; each Path has a route (also called Explicit Route) or sequence of hops. A Path is indexed by a dual index: The primary index is that of the Tunnel to which the Path belongs; the secondary index is that of the Path itself.

The configured information for a Path consists of the constraints for the Path and a configured route.

The operational information consists of the Path status, the computed route (i.e., the route that was computed to satisfy the constraints), and the actual path as recorded by the signaling protocol.

3.4. Hop Information

A path consists of a sequence of hops. A hop can be loose (meaning that the path eventually traverses the specified node) or strict (meaning that the specified node and possibly the link must be the next node in the path). A hop can be specified as an IPv4 address, an IPv6 address, an Autonomous System number or an unnumbered interface index [5].

The Hop Table contains all hops for all paths on a given router. It is organized as follows. There is a primary index that identifies a list of hops and a secondary index that identifies individual hops. Thus, to get the sequence of recorded hops for a path, one looks up the path's tePathRecordedRoute, which is a primary index into the Hop Table. Then to get the list of actual hops in order for the recorded path, one uses a secondary index of 1, 2,

3.5. Relationship with Other MIB Modules

A TE Tunnel can extend objects from two other MIB modules; one is the Interfaces MIB [10], and the other is the IP Tunnel MIB [11]. The mechanism for doing so is to assign the TE Tunnel index (teTunnelIndex) with a valid ifIndex value in ifTable.

If a TE Tunnel is deemed an interface, a new interface object is created and assigned an ifIndex value in ifTable. Then a TE Tunnel object is created, setting teTunnelIndex to the same value as the interface index.

If (and only if) a TE Tunnel is considered an interface, it may also be considered an IP tunnel (if the encapsulation of the TE Tunnel is IP). In that case, the interface associated with the TE Tunnel should have its ifType set to tunnel(131).

If a TE Tunnel is not considered an interface, then the TE Tunnel index (teTunnelIndex) SHOULD be set to a value at least 2^24, so that it is distinct from normal interfaces.

4. Creating, Modifying, and Deleting a TE Tunnel

To create a TE Tunnel, one first obtains a free Tunnel index by using the object teNextTunnelIndex. One then creates the Tunnel, including all parameters, either as createAndGo or createAndWait. Then, TE Paths for this Tunnel can be created by using the teTunnelNextPathIndex object, again as createAndGo or createAndWait. A particular Path is computed and signaled when both the Path and the enclosing Tunnel have RowStatus 'active'.

To build a Path's configured route, one first gets a free PathHop index by using teNextPathHopIndex, and then builds the route hop-byhop using the secondary index, setting the AddrType, Address, and HopType for each Hop. Finally, one sets the tePathConfiguredRoute in the Path to the PathHop index obtained.

Modifying certain properties of a TE Tunnel or a TE Path may require setting the RowStatus of the Tunnel (or Path) to 'notInService' before making the changes and then setting the RowStatus of the Tunnel (or Path) back to 'active' to re-signal all Paths of the Tunnel (or the modified Path).

A TE Tunnel and all its Paths can be deleted by setting the Tunnel's RowStatus to 'destroy'. A specific Path within a Tunnel can be destroyed by setting that Path's RowStatus to 'destroy'.

5. MIB Specification

This MIB module IMPORTs objects from RFCs 2578 [2], 2579 [3], 2580 [3], 3411 [6], and 3811 [5] and it also has REFERENCE clauses to RFCs 3209 [8] and 3212 [12].

TE-MIB DEFINITIONS ::= BEGIN

IMPORTS

MODULE-IDENTITY, OBJECT-TYPE, NOTIFICATION-TYPE, mib-2, Integer32, Gauge32, Counter32, Counter64, Unsigned32, TimeTicks

FROM SNMPv2-SMI

RowStatus, StorageType, TimeStamp,

TruthValue FROM SNMPv2-TC

SnmpAdminString FROM SNMP-FRAMEWORK-MIB

MODULE-COMPLIANCE, OBJECT-GROUP,

NOTIFICATION-GROUP FROM SNMPv2-CONF

TeHopAddress, TeHopAddressType,

FROM MPLS-TC-STD-MIB; MplsBitRate

teMIB MODULE-IDENTITY

LAST-UPDATED "200501040000Z" -- 01 January 2005 ORGANIZATION "IETF Traffic Engineering Working Group" CONTACT-INFO "

> Kireeti Kompella Editor:

Postal: Juniper Networks, Inc. 1194 Mathilda Ave

```
Sunnyvale, CA 94089
                       Tel: +1 408 745 2000
                       E-mail: kireeti@juniper.net
                The IETF Traffic Engineering Working Group is
                chaired by Jim Boyle and Ed Kern.
                WG Mailing List information:
                  General Discussion: te-wg@ops.ietf.org
                   To Subscribe: te-wg-request@ops.ietf.org
                      In Body:
                                  subscribe
                   Archive:
                                  ftp://ops.ietf.org/pub/lists
                Comments on the MIB module should be sent to the
                mailing list. The archives for this mailing list
                should be consulted for previous discussion on
                this MIB.
   DESCRIPTION "The Traffic Engineering MIB module.
                Copyright (C) The Internet Society (2005). This
                version of this MIB module is part of RFC 3970;
                see the RFC itself for full legal notices.
   -- revision history
              "200501040000Z" -- 01 January 2005
   REVISION
   DESCRIPTION "Initial version, published as RFC 3970."
   ::= { mib-2 122 }
-- Top level objects
teMIBNotifications OBJECT IDENTIFIER ::= { teMIB 0 }
__ *********************************
-- TE MIB Objects
-- TE Info
teInfo OBJECT IDENTIFIER ::= { teMIBObjects 1 }
teDistProtocol OBJECT-TYPE
```

```
SYNTAX
                BITS {
                   other(0),
                    isis(1),
                    ospf(2)
                }
   MAX-ACCESS
              read-only
   STATUS
                current
   DESCRIPTION "IGP used to distribute Traffic Engineering
                information and topology to each device for the
                purpose of automatic path computation. More than
                one IGP may be used to distribute TE information.
    ::= { teInfo 1 }
teSignalingProto OBJECT-TYPE
   SYNTAX
               BITS {
                    other(0),
                    rsvpte(1),
                    crldp(2),
                    static(3) -- static configuration
                }
   MAX-ACCESS
              read-only
   STATUS
                current
   DESCRIPTION "Traffic Engineering signaling protocols supported
                by this device. More than one protocol may be
               supported.
               "For a description of RSVP-TE, see RFC 3209;
   REFERENCE
               for CR-LDP, see RFC 3212.
   ::= { teInfo 2 }
teNotificationEnable OBJECT-TYPE
   SYNTAX
               TruthValue
   MAX-ACCESS read-write
   STATUS
               current
   DESCRIPTION "If this object is true, then it enables the
                generation of notifications from this MIB module.
                Otherwise notifications are not generated.
   DEFVAL { false }
   ::= { teInfo 3 }
teNextTunnelIndex OBJECT-TYPE
   SYNTAX Unsigned32
   MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION "An integer that may be used as a new Index in the
```

teTunnelTable.

The special value of 0 indicates that no more new entries can be created in that table.

When this MIB module is used for configuration, this object always contains a legal value (if non-zero) for an index that is not currently used in that table. The Command Generator (Network Management Application) reads this variable and uses the (non-zero) value read when creating a new row with an SNMP SET. When the SET is performed, the Command Responder (agent) must determine whether the value is indeed still unused; Two Network Management Applications may attempt to create a row (configuration entry) simultaneously and use the same value. If it is currently unused, the SET succeeds, and the Command Responder (agent) changes the value of this object according to an implementation-specific algorithm. If the value is in use, however, the SET fails. The Network Management Application must then re-read this variable to obtain a new usable value.

::= { teInfo 4 }

teNextPathHopIndex OBJECT-TYPE

SYNTAX Unsigned32 MAX-ACCESS read-only STATUS current

DESCRIPTION "An integer that may be used as a new Index in the tePathHopTable.

The special value of 0 indicates that no more new entries can be created in that table.

When this MIB module is used for configuration, this object always contains a legal value (if non-zero) for an index that is not currently used in that table. The Command Generator (Network Management Application) reads this variable and uses the (non-zero) value read when creating a new row with an SNMP SET. When the SET is performed, the Command Responder (agent) must determine whether the value is indeed still unused; Two Network Management Applications may attempt to create a row (configuration entry) simultaneously and use the same value. If it is currently unused, the SET

```
succeeds, and the Command Responder (agent) changes
                the value of this object according to an
                implementation-specific algorithm. If the value is
                in use, however, the SET fails. The Network
                Management Application must then re-read this
                variable to obtain a new usable value.
    ::= { teInfo 5 }
teConfiguredTunnels OBJECT-TYPE
   SYNTAX
           Gauge32
   MAX-ACCESS read-only
               current
   STATUS
   DESCRIPTION "Number of currently configured Tunnels."
   ::= { teInfo 6 }
teActiveTunnels OBJECT-TYPE
   SYNTAX Gauge32
   MAX-ACCESS read-only
               current
   DESCRIPTION "Number of currently active Tunnels."
   ::= { teInfo 7 }
tePrimaryTunnels OBJECT-TYPE
   SYNTAX Gauge32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION "Number of currently active Tunnels running on
               their primary paths.
    ::= { teInfo 8 }
teAdminGroupTable OBJECT-TYPE
   SYNTAX
               SEQUENCE OF TeAdminGroupEntry
   MAX-ACCESS not-accessible
   STATUS
               current
   DESCRIPTION "A mapping of configured administrative groups. Each
                entry represents an Administrative Group and
                provides a name and index for the group.
                Administrative groups are used to label links in the
                Traffic Engineering topology in order to place
                constraints (include and exclude) on Tunnel paths.
                A groupName can only be linked to one group number.
                The groupNumber is the number assigned to the
                administrative group used in constraints,
                such as tePathIncludeAny or tePathIncludeAll.
```

```
::= { teInfo 9 }
teAdminGroupEntry OBJECT-TYPE
               TeAdminGroupEntry
   MAX-ACCESS not-accessible
   STATUS
               current
   DESCRIPTION "A mapping between a configured group number and
                its human-readable name. The group number should
                be between 1 and 32, inclusive. Group number n
                represents bit number (n-1) in the bit vector for
                Include/Exclude constraints.
                All entries in this table MUST be kept in stable
                storage so that they will re-appear in case of a
                restart/reboot.
               { teAdminGroupNumber }
   INDEX
    ::= { teAdminGroupTable 1 }
TeAdminGroupEntry ::=
   SEQUENCE {
       teAdminGroupNumber Integer32,
       teAdminGroupName SnmpAdminString,
       teAdminGroupRowStatus RowStatus
teAdminGroupNumber OBJECT-TYPE
   SYNTAX Integer32 (1..32)
   MAX-ACCESS not-accessible
   STATUS
               current
   DESCRIPTION "Index of the administrative group."
   ::= { teAdminGroupEntry 1 }
teAdminGroupName OBJECT-TYPE
   SYNTAX SnmpAdminString (SIZE (1..32))
   MAX-ACCESS read-create
   STATUS
               current
   DESCRIPTION "Name of the administrative group."
   ::= { teAdminGroupEntry 2 }
teAdminGroupRowStatus OBJECT-TYPE
   SYNTAX RowStatus
              read-create
   MAX-ACCESS
   STATUS
               current
   DESCRIPTION "The status of this conceptual row.
                The value of this object has no effect on whether
```

other objects in this conceptual row can be

```
modified.
    ::= { teAdminGroupEntry 3 }
-- Tunnel Table
teTunnelTable OBJECT-TYPE
   SYNTAX
                SEQUENCE OF TeTunnelEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION "Table of Configured Traffic Tunnels."
   ::= { teMIBObjects 2 }
teTunnelEntry OBJECT-TYPE
   SYNTAX
               TeTunnelEntry
   MAX-ACCESS not-accessible
   STATUS
                current
   DESCRIPTION "Entry containing information about a particular
               Traffic Tunnel.
               { teTunnelIndex }
    ::= { teTunnelTable 1 }
TeTunnelEntry ::=
   SEQUENCE {
       teTunnelIndex
                                      Unsigned32,
       teTunnelName
                                      SnmpAdminString,
       teTunnelNextPathIndex
                                      Unsigned32,
     -- Conceptual row information:
       teTunnelRowStatus
                                     RowStatus,
       teTunnelStorageType
                                      StorageType,
     -- Address information:
       teTunnelSourceAddressType
                                      TeHopAddressType,
       teTunnelSourceAddress
                                      TeHopAddress,
       \verb|teTunnelDestinationAddressType| TeHopAddressType|,
       teTunnelDestinationAddress
                                     TeHopAddress,
     -- State/performance information:
                                     INTEGER,
       teTunnelState
       teTunnelDiscontinuityTimer TimeStamp,
       teTunnelOctets
                                      Counter64,
       teTunnelPackets
                                      Counter64,
       teTunnelLPOctets
                                      Counter32,
       teTunnelLPPackets
                                      Counter32,
                                      TimeTicks,
       teTunnelAge
       teTunnelTimeUp
                                     TimeTicks,
       teTunnelPrimaryTimeUp
                                     TimeTicks,
       teTunnelTransitions
                                     Counter32,
       teTunnelLastTransition
                                     TimeTicks,
```

```
Counter32,
       teTunnelPathChanges
       teTunnelLastPathChange
                                      TimeTicks,
       teTunnelConfiguredPaths
                                     Gauge32,
       teTunnelStandbyPaths
                                     Gauge32,
       teTunnelOperationalPaths
                                     Gauge32
   }
teTunnelIndex
               OBJECT-TYPE
   SYNTAX
               Unsigned32 (1..4294967295)
   MAX-ACCESS not-accessible
   STATUS
               current
   DESCRIPTION "A unique index that identifies a Tunnel. If the TE
                Tunnel is considered an interface, then this index
                must match the interface index of the corresponding
                interface. Otherwise, this index must be at least
                2^24, so that it does not overlap with any existing
                interface index.
    ::= { teTunnelEntry 1 }
teTunnelName
              OBJECT-TYPE
   SYNTAX
               SnmpAdminString (SIZE (1..32))
   MAX-ACCESS read-create
   STATUS
               current
   DESCRIPTION "Name of the Traffic Tunnel.
                Note that the name of a Tunnel MUST be unique.
                When a SET request contains a name that is already
                in use for another entry, then the implementation
                must return an inconsistentValue error.
                The value of this object cannot be changed if the
                if the value of the corresponding teTunnelRowStatus
                object is 'active'.
    ::= { teTunnelEntry 2 }
teTunnelNextPathIndex OBJECT-TYPE
   SYNTAX Unsigned32
   MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION "An integer that may be used as a new Index for the
                next Path in this Tunnel.
                The special value of 0 indicates that no more Paths
                can be created for this Tunnel, or that no more new
                entries can be created in tePathTable.
```

When this MIB module is used for configuration, this object always contains a legal value (if non-zero) for an index that is not currently used in that table. The Command Generator (Network Management Application) reads this variable and uses the (non-zero) value read when creating a new row with an SNMP SET. When the SET is performed, the Command Responder (agent) must determine whether the value is indeed still unused; Two Network Management Applications may attempt to create a row (configuration entry) simultaneously and use the same value. If it is currently unused, the SET succeeds, and the Command Responder (agent) changes the value of this object according to an implementation-specific algorithm. If the value is in use, however, the SET fails. The Network Management Application must then re-read this variable to obtain a new usable value.

::= { teTunnelEntry 3 } teTunnelRowStatus OBJECT-TYPE SYNTAX RowStatus read-create MAX-ACCESS STATUS current DESCRIPTION "The status of this conceptual row. When the value of this object is 'active', then the values for the corresponding objects teTunnelName, teTunnelSourceAddressType, teTunnelSourceAddress, teTunnelDestinationAddressType, and teTunnelDestinationAddress cannot be changed. ::= { teTunnelEntry 4 } teTunnelStorageType OBJECT-TYPE SYNTAX StorageType MAX-ACCESS read-create STATUS current DESCRIPTION "The storage type for this conceptual row. Conceptual rows having the value 'permanent' need not allow write-access to any columnar objects

in the row.

::= { teTunnelEntry 5 }

```
teTunnelSourceAddressType OBJECT-TYPE
   SYNTAX TeHopAddressType
   MAX-ACCESS read-create
   STATUS
               current
   DESCRIPTION "The type of Traffic Engineered Tunnel hop address
                for the source of this Tunnel. Typically, this
                address type is IPv4 or IPv6, with a prefix length
                of 32 or 128, respectively. If the TE Tunnel path
                is being computed by a path computation server,
                however, it is possible to use more flexible source
                address types, such as AS numbers or prefix lengths
                less than host address lengths.
                The value of this object cannot be changed
                if the value of the corresponding teTunnelRowStatus
                object is 'active'.
    ::= { teTunnelEntry 6 }
teTunnelSourceAddress OBJECT-TYPE
               TeHopAddress
   MAX-ACCESS read-create
   STATUS
                current
   DESCRIPTION "The Source Traffic Engineered Tunnel hop address of
                this Tunnel.
                The type of this address is determined by the value
                of the corresponding teTunnelSourceAddressType.
                Note that the source and destination addresses of a
                Tunnel can be different address types.
                The value of this object cannot be changed
                if the value of the corresponding teTunnelRowStatus
                object is 'active'.
    ::= { teTunnelEntry 7 }
teTunnelDestinationAddressType OBJECT-TYPE
   SYNTAX
                TeHopAddressType
   MAX-ACCESS
               read-create
                current
   DESCRIPTION "The type of Traffic Engineered Tunnel hop address
                for the destination of this Tunnel.
                The value of this object cannot be changed
                if the value of the corresponding teTunnelRowStatus
                object is 'active'.
```

```
::= { teTunnelEntry 8 }
teTunnelDestinationAddress OBJECT-TYPE
   SYNTAX TeHopAddress
   MAX-ACCESS read-create
   STATUS
                current
   DESCRIPTION "The Destination Traffic Engineered Tunnel hop
                address of this Tunnel.
                The type of this address is determined by the value
                of the corresponding teTunnelDestinationAddressType.
                Note that source and destination addresses of a
                Tunnel can be different address types.
                The value of this object cannot be changed
                if the value of the corresponding teTunnelRowStatus
                object is 'active'.
    ::= { teTunnelEntry 9 }
teTunnelState
                OBJECT-TYPE
   SYNTAX
                INTEGER {
                    unknown(1),
                    up(2),
                    down(3),
                    testing(4)
                }
   MAX-ACCESS
              read-only
   STATUS
                current
   DESCRIPTION "The operational state of the Tunnel."
    ::= { teTunnelEntry 10 }
teTunnelDiscontinuityTimer OBJECT-TYPE
   SYNTAX TimeStamp
   MAX-ACCESS read-only
                current
   DESCRIPTION "The value of sysUpTime on the most recent occasion
                at which any one or more of this tunnel's counters
                suffered a discontinuity. The relevant counters
                are teTunnelOctets, teTunnelPackets,
                teTunnelLPOctets, and teTunnelLPPackets. If no such
                discontinuities have occurred since the last
                re-initialization of the local management subsystem
                then this object contains a zero value.
    ::= { teTunnelEntry 11 }
```

```
teTunnelOctets OBJECT-TYPE
   SYNTAX Counter64
   MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION "The number of octets that have been forwarded over
                the Tunnel.
                Discontinuities in the value of this counter can
                occur at re-initialization of the management system,
                and at other times, as indicated by the value of
                teTunnelDiscontinuityTimer.
    ::= { teTunnelEntry 12 }
teTunnelPackets OBJECT-TYPE
   SYNTAX
               Counter64
   MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION "The number of packets that have been forwarded over
                the Tunnel.
                Discontinuities in the value of this counter can
                occur at re-initialization of the management system
                and at other times, as indicated by the value of
                teTunnelDiscontinuityTimer.
    ::= { teTunnelEntry 13 }
teTunnelLPOctets OBJECT-TYPE
   SYNTAX
              Counter32
   MAX-ACCESS read-only
   STATUS
                current
   DESCRIPTION "The number of octets that have been forwarded over
                the Tunnel.
                Discontinuities in the value of this counter can
                occur at re-initialization of the management system
                and at other times, as indicated by the value of
                teTunnelDiscontinuityTimer.
    ::= { teTunnelEntry 14 }
teTunnelLPPackets OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION "The number of packets that have been forwarded over
               the Tunnel.
```

STATUS

current

Discontinuities in the value of this counter can occur at re-initialization of the management system and at other times, as indicated by the value of teTunnelDiscontinuityTimer. ::= { teTunnelEntry 15 } teTunnelAge OBJECT-TYPE TimeTicks SYNTAX MAX-ACCESS read-only STATUS current DESCRIPTION "The age (i.e., time from creation of this conceptual row till now) of this Tunnel in hundredths of a second. Note that because TimeTicks wrap in about 16 months, this value is best used in interval measurements. ::= { teTunnelEntry 16 } teTunnelTimeUp OBJECT-TYPE TimeTicks SYNTAX MAX-ACCESS read-only STATUS current DESCRIPTION "The total time in hundredths of a second that this Tunnel has been operational. Note that because TimeTicks wrap in about 16 months, this value is best used in interval measurements. An example of usage of this object would be to compute the percentage up time over a period of time by obtaining values of teTunnelAge and teTunnelTimeUp at two points in time and computing the following ratio: ((teTunnelTimeUp2 - teTunnelTimeUp1)/ (teTunnelAge2 - teTunnelAge1)) * 100 %. In doing so, the management station must account for wrapping of the values of teTunnelAge and teTunnelTimeUp between the two measurements. ::= { teTunnelEntry 17 } teTunnelPrimaryTimeUp OBJECT-TYPE SYNTAX TimeTicks MAX-ACCESS read-only

Kompella Standards Track [Page 17]

DESCRIPTION "The total time in hundredths of a second that this

Tunnel's primary path has been operational. Note that because TimeTicks wrap in about 16 months, this

value is best used in interval measurements. An example of usage of this field would be to compute what percentage of time that a TE Tunnel was on the primary path over a period of time by computing ((teTunnelPrimaryTimeUp2 - teTunnelPrimaryTimeUp1)/ (teTunnelTimeUp2 - teTunnelTimeUp1))*100 %. In doing so, the management station must account for wrapping of the values of teTunnelPrimaryTimeUp and teTunnelTimeUp between the two measurements. ::= { teTunnelEntry 18 } teTunnelTransitions OBJECT-TYPE SYNTAX Counter32 MAX-ACCESS read-only STATUS current DESCRIPTION "The number of operational state transitions (up -> down and down -> up) this Tunnel has undergone. ::= { teTunnelEntry 19 } teTunnelLastTransition OBJECT-TYPE SYNTAX TimeTicks MAX-ACCESS read-only STATUS current DESCRIPTION "The time in hundredths of a second since the last operational state transition occurred on this Tunnel. Note that if the last transition was over 16 months ago, this value will be inaccurate. ::= { teTunnelEntry 20 } teTunnelPathChanges OBJECT-TYPE SYNTAX Counter32 MAX-ACCESS read-only current DESCRIPTION "The number of path changes this Tunnel has had." ::= { teTunnelEntry 21 } teTunnelLastPathChange OBJECT-TYPE SYNTAX TimeTicks

MAX-ACCESS read-only

current

STATUS

```
DESCRIPTION "The time in hundredths of a second since the last
                path change occurred on this Tunnel.
                Note that if the last transition was over 16
                months ago, this value will be inaccurate.
                Path changes may be caused by network events or by
                reconfiguration that affects the path.
    ::= { teTunnelEntry 22 }
teTunnelConfiguredPaths OBJECT-TYPE
   SYNTAX
            Gauge32
   MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION "The number of paths configured for this Tunnel."
   ::= { teTunnelEntry 23 }
teTunnelStandbyPaths OBJECT-TYPE
   SYNTAX Gauge32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION "The number of standby paths configured for this
               Tunnel.
    ::= { teTunnelEntry 24 }
teTunnelOperationalPaths OBJECT-TYPE
   SYNTAX Gauge32
   MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION "The number of operational paths for this Tunnel.
                This includes the path currently active, as
                well as operational standby paths.
    ::= { teTunnelEntry 25 }
__ *********************************
-- Tunnel Path Table
tePathTable OBJECT-TYPE SYNTAX SEQUENCE OF
               SEQUENCE OF TePathEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION "Table of Configured Traffic Tunnels."
   ::= { teMIBObjects 3 }
```

```
OBJECT-TYPE
tePathEntry
   SYNTAX
               TePathEntry
   MAX-ACCESS not-accessible
   STATUS
               current
   DESCRIPTION "Entry containing information about a particular
                Traffic Tunnel. Each Traffic Tunnel can have zero
                or more Traffic Paths.
                As a Traffic Path can only exist over an existing
                Traffic Tunnel, all tePathEntries with
                a value of n for teTunnelIndex MUST be removed by
                the implementation when the corresponding
                teTunnelEntry with a value of n for teTunnelIndex
                is removed.
               { teTunnelIndex, tePathIndex }
    ::= { tePathTable 1 }
TePathEntry ::=
   SEQUENCE {
                                 Unsigned32,
       tePathIndex
       tePathName
                                 SnmpAdminString,
    -- Conceptual row information
       tePathRowStatus RowStatus,
       tePathStorageType
                               StorageType,
    -- Path properties
                                INTEGER,
       tePathType
                              Unsigned32,
       tePathConfiguredRoute
       tePathBandwidth
                               MplsBitRate,
       tePathIncludeAny
                               Unsigned32,
       tePathIncludeAll
                               Unsigned32,
       tePathExclude
                                Unsigned32,
       tePathSetupPriority
                                Integer32,
       tePathHoldPriority
                                Integer32,
       tePathProperties
                                BITS,
    -- Path status
       tePathOperStatus
                               INTEGER,
       tePathAdminStatus
                                INTEGER,
       tePathComputedRoute
                               Unsigned32,
       tePathRecordedRoute
                               Unsigned32
   }
tePathIndex
               OBJECT-TYPE
               Unsigned32 (1..4294967295)
   SYNTAX
   MAX-ACCESS not-accessible
               current
   DESCRIPTION "An index that uniquely identifies a path within
               a Tunnel.
```

```
The combination of <teTunnelIndex, tePathIndex> thus
                uniquely identifies a path among all paths on this
                router.
    ::= { tePathEntry 1 }
tePathName
                OBJECT-TYPE
    SYNTAX
                SnmpAdminString (SIZE(0..32))
              read-create
   MAX-ACCESS
   STATUS
                current
   DESCRIPTION "The name of this path.
                A pathName must be unique within the set of paths
                over a single tunnel. If a SET request is received
                with a duplicate name, then the implementation MUST
                return an inconsistentValue error.
                The value of this object cannot be changed
                if the value of the corresponding teTunnelRowStatus
                object is 'active'.
    ::= { tePathEntry 2 }
tePathRowStatus OBJECT-TYPE
   SYNTAX
                RowStatus
              read-create
   MAX-ACCESS
                current
   STATUS
   DESCRIPTION "The status of this conceptual row.
                When the value of this object is 'active', then
                the value of tePathName cannot be changed. All
                other writable objects may be changed; however,
                these changes may affect traffic going over the TE
                tunnel or require the path to be computed and/or
                re-signaled.
    ::= { tePathEntry 3 }
tePathStorageType OBJECT-TYPE
   SYNTAX
               StorageType
   MAX-ACCESS
               read-create
                current
   DESCRIPTION "The storage type for this conceptual row.
                Conceptual rows having the value 'permanent' need
                not allow write-access to any columnar objects
                in the row.
```

```
::= { tePathEntry 4 }
tePathType OBJECT-TYPE
   SYNTAX
                INTEGER {
                    other(1),
                    primary(2),
                     standby(3),
                     secondary(4)
   MAX-ACCESS
                read-create
   STATUS
                current
   DESCRIPTION "The type for this PathEntry; i.e., whether this path
                is a primary path, a standby path, or a secondary
                path.
    ::= { tePathEntry 5 }
tePathConfiguredRoute OBJECT-TYPE
   SYNTAX
            Unsigned32
   MAX-ACCESS read-create
   STATUS
                current
   DESCRIPTION "The route that this TE path is configured to follow;
                i.e., an ordered list of hops. The value of this
                object gives the primary index into the Hop Table.
                The secondary index is the hop count in the path, so
                to get the route, one could get the first hop with
                index <tePathConfiguredRoute, 1> in the Hop Table
                and do a getnext to get subsequent hops.
    ::= { tePathEntry 6 }
tePathBandwidth OBJECT-TYPE
   SYNTAX
                MplsBitRate
   UNITS
               "Kilobits per second"
   {\tt MAX-ACCESS} \qquad {\tt read-create}
   STATUS
                current
   DESCRIPTION "The configured bandwidth for this Tunnel,
                in units of thousands of bits per second (Kbps).
                { 0 }
   DEFVAL
    ::= { tePathEntry 7 }
tePathIncludeAny OBJECT-TYPE
   SYNTAX Unsigned32
   MAX-ACCESS read-create
                current
   DESCRIPTION "This is a configured set of administrative groups
                specified as a bit vector (i.e., bit n is 1 if group
```

```
n is in the set, where n = 0 is the LSB). For each
                link that this path goes through, the link must have
                at least one of the groups specified in IncludeAny
                to be acceptable. If IncludeAny is zero, all links
                are acceptable.
               { 0 }
   DEFVAL
    ::= { tePathEntry 8 }
tePathIncludeAll OBJECT-TYPE
   SYNTAX
               Unsigned32
   MAX-ACCESS read-create
   STATUS
                current
   DESCRIPTION "This is a configured set of administrative groups
                specified as a bit vector (i.e., bit n is 1 if group
                n is in the set, where n = 0 is the LSB). For each
                link that this path goes through, the link must have
                all of the groups specified in IncludeAll to be
                acceptable. If IncludeAll is zero, all links are
                acceptable.
   DEFVAL
               { 0 }
    ::= { tePathEntry 9 }
tePathExclude OBJECT-TYPE
   SYNTAX
                Unsigned32
   MAX-ACCESS read-create
                current
   DESCRIPTION "This is a configured set of administrative groups
                specified as a bit vector (i.e., bit n is 1 if group
                n is in the set, where n = 0 is the LSB). For each
                link that this path goes through, the link MUST have
                groups associated with it, and the intersection of
                the link's groups and the 'exclude' set MUST be
                null.
   DEFVAL
               { 0 }
    ::= { tePathEntry 10 }
tePathSetupPriority OBJECT-TYPE
   SYNTAX
                Integer32 (0..7)
   MAX-ACCESS
                read-create
               current
   STATUS
   DESCRIPTION "The setup priority configured for this path, with 0
                as the highest priority and 7 as the lowest.
   DEFVAL
              { 7 }
```

```
::= { tePathEntry 11 }
tePathHoldPriority OBJECT-TYPE
                 Integer32 (0..7)
    MAX-ACCESS read-create
                  current
    STATUS
    DESCRIPTION "The hold priority configured for this path, with 0
                 as the highest priority and 7 as the lowest.
                 { 0 }
    DEFVAL
    ::= { tePathEntry 12 }
tePathProperties OBJECT-TYPE
                  BITS {
    SYNTAX
                      recordRoute(0),
                      cspf(1),
                      makeBeforeBreak(2),
                      mergeable(3),
                      fastReroute(4),
                      protected(5)
                  }
    MAX-ACCESS
                read-create
    STATUS
                  current
    DESCRIPTION "The set of configured properties for this path,
                  expressed as a bit map. For example, if the path
                  supports 'make before break', then bit 2 is set.
    ::= { tePathEntry 13 }
tePathOperStatus OBJECT-TYPE
    SYNTAX
                  INTEGER {
                      unknown(0),
                      down(1),
                      testing(2),
                      dormant(3),
                      ready(4),
                      operational(5)
                  }
    MAX-ACCESS
                 read-only
                  current
    STATUS
    DESCRIPTION "The operational status of the path:
                  unknown:
                                Signaling failed.
                  down:
                  testing: Administratively set aside for testing. dormant: Not signaled (for a backup tunnel). ready: Signaled but not yet carrying traffic.
                  operational: Signaled and carrying traffic.
```

```
::= { tePathEntry 14 }
tePathAdminStatus OBJECT-TYPE
                INTEGER {
                    normal(1),
                    testing(2)
                 }
   MAX-ACCESS
                read-create
   STATUS
                current
   DESCRIPTION "The operational status of the path:
                normal: Used normally for forwarding. testing: Administratively set aside for testing.
    ::= { tePathEntry 15 }
tePathComputedRoute OBJECT-TYPE
   SYNTAX
               Unsigned32
   MAX-ACCESS read-only
   STATUS
                current
   DESCRIPTION "The route computed for this path, perhaps using
                 some form of Constraint-based Routing.
                 algorithm is implementation dependent.
                 This object returns the computed route as an ordered
                 list of hops. The value of this object gives the
                 primary index into the Hop Table. The secondary
                 index is the hop count in the path, so to get the
                 route, one could get the first hop with index
                 <tePathComputedRoute, 1> in the Hop Table and do a
                 getnext to get subsequent hops.
                A value of zero (0) means there is no computedRoute.
    ::= { tePathEntry 16 }
tePathRecordedRoute OBJECT-TYPE
   SYNTAX Unsigned32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION "The route actually used for this path, as recorded
                 by the signaling protocol. This is again an ordered
                 list of hops; each hop is expected to be strict.
                 The value of this object gives the primary index
                 into the Hop Table. The secondary index is the hop
                 count in the path, so to get the route, one can get
                 the first hop with index <tePathRecordedRoute, 1>
                 in the Hop Table and do a getnext to get subsequent
```

```
hops.
                A value of zero (0) means there is no recordedRoute.
   ::= { tePathEntry 17 }
__ *********************************
-- Tunnel Path Hop Table
tePathHopTable OBJECT-TYPE
   SYNTAX
               SEQUENCE OF TePathHopEntry
   MAX-ACCESS not-accessible
   STATUS
                current
   DESCRIPTION "Table of Tunnel Path Hops."
   ::= { teMIBObjects 4 }
tePathHopEntry OBJECT-TYPE
   SYNTAX
               TePathHopEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION "Entry containing information about a particular
                hop.
               { teHopListIndex, tePathHopIndex }
   INDEX
   ::= { tePathHopTable 1 }
TePathHopEntry ::=
   SEQUENCE {
                                   Unsigned32,
       teHopListIndex
                                   Unsigned32,
       tePathHopIndex
    -- Conceptual row information
       tePathHopRowStatus RowStatus,
tePathHopStorageType StorageType,
tePathHopAddrType TeHopAddressType,
       tePathHopAddress
                                  TeHopAddress,
                                  INTEGER
       tePathHopType
   }
teHopListIndex OBJECT-TYPE
   SYNTAX
               Unsigned32 (1..4294967295)
   MAX-ACCESS not-accessible
   STATUS
               current
   DESCRIPTION "An index that identifies a list of hops. This is
               the primary index to access hops.
   ::= { tePathHopEntry 1 }
```

```
tePathHopIndex OBJECT-TYPE
   SYNTAX Unsigned32 (1..4294967295)
   MAX-ACCESS not-accessible
   STATUS
               current
   DESCRIPTION "An index that identifies a particular hop among the
                list of hops for a path. An index of i identifies
                the ith hop. This is the secondary index for a hop
                entry.
    ::= { tePathHopEntry 2 }
tePathHopRowStatus OBJECT-TYPE
   SYNTAX
               RowStatus
   MAX-ACCESS read-create
   STATUS
                current
   DESCRIPTION "The status of this conceptual row.
                Any field in this table can be changed, even if the
                value of this object is 'active'. However, such a
                change may cause traffic to be rerouted or even
                disrupted.
    ::= { tePathHopEntry 3 }
tePathHopStorageType OBJECT-TYPE
           StorageType
   SYNTAX
   MAX-ACCESS read-create
   STATUS
               current
   DESCRIPTION "The storage type for this conceptual row.
                Conceptual rows having the value 'permanent' need
                not allow write-access to any columnar objects
                in the row.
    ::= { tePathHopEntry 4 }
tePathHopAddrType OBJECT-TYPE
           TeHopAddressType
   SYNTAX
   MAX-ACCESS
              read-create
   STATUS
                current
   DESCRIPTION "The type of Traffic Engineered Tunnel hop Address
                of this hop.
                The value of this object cannot be changed
                if the value of the corresponding tePathRowStatus
                object is 'active'.
    ::= { tePathHopEntry 5 }
```

```
tePathHopAddress OBJECT-TYPE
   SYNTAX TeHopAddress
   MAX-ACCESS read-create
   STATUS
               current
   DESCRIPTION "The Traffic Engineered Tunnel hop Address of this
                hop.
                The type of this address is determined by the value
                of the corresponding tePathHopAddressType.
                The value of this object cannot be changed
                if the value of the corresponding teTunnelRowStatus
                object is 'active'.
   ::= { tePathHopEntry 6 }
tePathHopType
               OBJECT-TYPE
   SYNTAX
                INTEGER {
                   unknown(0),
                   loose(1),
                   strict(2)
                }
   MAX-ACCESS
              read-only
   STATUS
               current
   DESCRIPTION "The type of hop:
               unknown:
                        This hop is a LOOSE hop.
                loose:
               strict: This hop is a STRICT hop.
   ::= { tePathHopEntry 7 }
__ *********************************
-- TE Notifications
              NOTIFICATION-TYPE
teTunnelUp
   OBJECTS
               { teTunnelName,
                 tePathName } -- TunnelPath
   STATUS
               current
   DESCRIPTION "A teTunnelUp notification is generated when the
                Tunnel indexed by teTunnelName transitions to the
                'up' state.
                A tunnel is up when at least one of its paths is up.
                The tePathName is the name of the path whose
                transition to up made the tunnel go up.
```

```
This notification MUST be limited to at most one
                every minute, in case the tunnel flaps up and down.
    ::= { teMIBNotifications 1 }
                NOTIFICATION-TYPE
teTunnelDown
   OBJECTS
                { teTunnelName,
                  tePathName } -- TunnelPath
   STATUS
                current
   DESCRIPTION "A teTunnelDown notification is generated when the
                Tunnel indexed by teTunnelName transitions to the
                'down' state.
                A tunnel is up when at least one of its paths is up.
                The tePathName is the name of the path whose
                transition to down made the tunnel go down.
                This notification MUST be limited to at most one
                every minute, in case the tunnel flaps up and down.
    ::= { teMIBNotifications 2 }
teTunnelChanged NOTIFICATION-TYPE
   OBJECTS
                { teTunnelName,
                  tePathName } -- toTunnelPath
                current
   STATUS
   DESCRIPTION "A teTunnelChanged notification is generated when an
                active path on the Tunnel indexed by teTunnelName
                changes or a new path becomes active. The value
                of tePathName is the new active path.
                This notification MUST be limited to at most one
                every minute, in case the tunnel changes quickly.
    ::= { teMIBNotifications 3 }
teTunnelRerouted NOTIFICATION-TYPE
   OBJECTS
                { teTunnelName,
                  tePathName } -- toTunnelPath
   STATUS
                current
   DESCRIPTION "A teTunnelRerouted notification is generated when
                an active path for the Tunnel indexed by
                teTunnelName stays the same, but its route changes.
                This notification MUST be limited to at most one
                every minute, in case the tunnel reroutes quickly.
    ::= { teMIBNotifications 4 }
```

```
-- End of TE-MIB objects
__ **********************************
-- TE Compliance Statements
teGroups
   OBJECT IDENTIFIER ::= { teMIBConformance 1 }
teModuleCompliance
   OBJECT IDENTIFIER ::= { teMIBConformance 2 }
-- TE object groups
teTrafficEngineeringGroup OBJECT-GROUP
   OBJECTS {
       teTunnelName,
       teTunnelNextPathIndex,
       teTunnelRowStatus,
       teTunnelStorageType,
       teTunnelSourceAddressType,
       teTunnelSourceAddress,
       teTunnelDestinationAddressType,
       teTunnelDestinationAddress,
       teTunnelState,
       teTunnelDiscontinuityTimer,
       teTunnelOctets,
       teTunnelPackets,
       teTunnelLPOctets,
       teTunnelLPPackets,
       teTunnelAge,
       teTunnelTimeUp,
       teTunnelPrimaryTimeUp,
       teTunnelTransitions,
       teTunnelLastTransition,
       teTunnelPathChanges,
       teTunnelLastPathChange,
       teTunnelConfiguredPaths,
       teTunnelStandbyPaths,
       teTunnelOperationalPaths,
       tePathBandwidth,
       tePathIncludeAny,
       tePathIncludeAll,
       tePathExclude,
```

```
tePathSetupPriority,
       tePathHoldPriority,
       tePathProperties,
       tePathOperStatus,
       tePathAdminStatus,
       tePathComputedRoute,
       tePathRecordedRoute,
       teDistProtocol,
       teSignalingProto,
       teNotificationEnable,
       teNextTunnelIndex,
       teNextPathHopIndex,
       teAdminGroupName,
       teAdminGroupRowStatus,
       teConfiguredTunnels,
       teActiveTunnels,
       tePrimaryTunnels,
       tePathName,
       tePathType,
       tePathRowStatus,
       tePathStorageType,
       tePathConfiguredRoute,
       tePathHopRowStatus,
       tePathHopStorageType,
       tePathHopAddrType,
       tePathHopAddress,
       tePathHopType
   }
               current
   DESCRIPTION "Objects for Traffic Engineering in this MIB module."
   ::= { teGroups 1 }
teNotificationGroup NOTIFICATION-GROUP
  NOTIFICATIONS {
      teTunnelUp,
      teTunnelDown,
      teTunnelChanged,
      teTunnelRerouted
  }
  STATUS
               current
  DESCRIPTION "Notifications specified in this MIB module."
  ::= { teGroups 2 }
__ **********************************
--
-- TE compliance statements
    There are four compliance statements: read-only and full
```

```
compliance for regular TE devices, and read-only and full
     compliance for path computation servers.
teModuleReadOnlyCompliance MODULE-COMPLIANCE
   STATUS
                current
   DESCRIPTION "When this MIB module is implemented without support
                for read-create (i.e., in read-only mode), then such
                an implementation can claim read-only compliance.
                Such a device can be monitored but cannot be
                configured with this MIB module.
   MODULE
                -- enclosing module, i.e., TE-MIB
       MANDATORY-GROUPS {
           teTrafficEngineeringGroup
       }
                   teNotificationGroup
       DESCRIPTION "Implementation of this group is optional."
       OBJECT
                   teNotificationEnable
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   teAdminGroupName
       OBJECT
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   teAdminGroupRowStatus
       OBJECT
                   RowStatus { active(1) }
       SYNTAX
       MIN-ACCESS
                    read-only
       DESCRIPTION "Write access is not required."
       OBJECT
                   teTunnelName
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
       OBJECT
                   teTunnelRowStatus
       SYNTAX RowStatus { active(1) }
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
       OBJECT
                   teTunnelStorageType
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
```

```
OBJECT
           teTunnelSourceAddressType
SYNTAX
          TeHopAddressType { ipv4(1), ipv6(2) }
MIN-ACCESS read-only
DESCRIPTION "Write access is not required. An
            implementation is only required to support
            IPv4 and IPv6 host addresses."
OBJECT
           teTunnelSourceAddress
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
OBJECT
           teTunnelDestinationAddressType
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
OBJECT
           teTunnelDestinationAddress
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
OBJECT
           tePathName
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
OBJECT
           tePathRowStatus
           RowStatus { active(1) }
SYNTAX
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
OBJECT
           tePathStorageType
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
OBJECT
           tePathType
MIN-ACCESS
            read-only
DESCRIPTION "Write access is not required."
OBJECT
           tePathConfiguredRoute
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
OBJECT
           tePathBandwidth
MIN-ACCESS read-only
DESCRIPTION "Write access is not required."
OBJECT
```

tePathIncludeAny

DESCRIPTION "Write access is not required."

MIN-ACCESS read-only

```
tePathIncludeAll
       OBJECT
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
       OBJECT
                   tePathExclude
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
       OBJECT
                   tePathSetupPriority
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
       OBJECT
                   tePathHoldPriority
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   tePathProperties
       OBJECT
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
       OBJECT
                   tePathAdminStatus
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   tePathHopRowStatus
       OBJECT tePathHopkowStatus
SYNTAX RowStatus { active(1) }
MIN-ACCESS read-only
       OBJECT
       DESCRIPTION "Write access is not required."
       OBJECT
                   tePathHopStorageType
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   tePathHopAddrType
       OBJECT
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   tePathHopAddress
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
    ::= { teModuleCompliance 1 }
teModuleFullCompliance MODULE-COMPLIANCE
   STATUS
                current
   DESCRIPTION "When this MIB module is implemented with support for
                read-create, then the implementation can claim
                full compliance. Such devices can be both
```

```
monitored and configured with this MIB module.
            -- enclosing module, i.e., TE-MIB
MODULE
    MANDATORY-GROUPS {
       teTrafficEngineeringGroup
    GROUP
                teNotificationGroup
    DESCRIPTION "Implementation of this group is optional."
    OBJECT
                teAdminGroupRowStatus
    SYNTAX
                RowStatus { active(1) }
    WRITE-SYNTAX RowStatus { createAndGo(4), destroy(6) }
    DESCRIPTION "Support for notInService, createAndWait and
                notReady is not required.
    OBJECT
                teTunnelRowStatus
    SYNTAX RowStatus { active(1), notInService(2) }
    \label{eq:write-syntax} \mbox{WRITE-SYNTAX RowStatus } \left\{ \mbox{ active(1), notInService(2),} \right.
                             createAndGo(4), destroy(6)
    DESCRIPTION "Support for createAndWait and notReady is not
                required.
                teTunnelSourceAddressType
    OBJECT
                TeHopAddressType { ipv4(1), ipv6(2) }
    SYNTAX
    DESCRIPTION "Write access is required. An implementation is
                only required to support IPv4 and IPv6 host
                addresses.
    OBJECT
                tePathRowStatus
               RowStatus { active(1), notInService(2) }
    WRITE-SYNTAX RowStatus { active(1), notInService(2),
                             createAndGo(4), destroy(6)
    DESCRIPTION "Support for createAndWait and notReady is not
                required.
    OBJECT tePathHopRowStatus
                RowStatus { active(1), notInService(2) }
    SYNTAX
    WRITE-SYNTAX RowStatus { active(1), notInService(2),
```

```
createAndGo(4), destroy(6)
                              }
       DESCRIPTION "Support for createAndWait and notReady is not
                   required.
    ::= { teModuleCompliance 2 }
teModuleServerReadOnlyCompliance MODULE-COMPLIANCE
                current
   STATUS
   DESCRIPTION "When this MIB module is implemented by a path
                computation server without support for read-create
                (i.e., in read-only mode), then the implementation
                can claim read-only compliance. Such
                a device can be monitored but cannot be
                configured with this MIB module.
   MODULE
               -- enclosing module, i.e., TE-MIB
       MANDATORY-GROUPS {
           teTrafficEngineeringGroup
                   teNotificationGroup
       DESCRIPTION "Implementation of this group is optional."
       OBJECT
                   teNotificationEnable
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   teAdminGroupName
       OBJECT
       MIN-ACCESS
                    read-only
       DESCRIPTION "Write access is not required."
       OBJECT
                   teAdminGroupRowStatus
       SYNTAX
                   RowStatus { active(1) }
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
       OBJECT
                   teTunnelName
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   teTunnelRowStatus
       OBJECT
       SYNTAX
                   RowStatus { active(1) }
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
```

OBJECT teTunnelStorageType

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT teTunnelSourceAddressType

MIN-ACCESS read-only

DESCRIPTION "Write access is not required. A path

computation server SHOULD implement all types

of tunnel source address types.

OBJECT teTunnelSourceAddress

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT teTunnelDestinationAddressType

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT teTunnelDestinationAddress

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT tePathName MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT SYNTAX tePathRowStatus

RowStatus { active(1) }

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT tePathStorageType

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT tePathType MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT tePathConfiguredRoute

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT tePathBandwidth

MIN-ACCESS read-only

DESCRIPTION "Write access is not required."

OBJECT

```
tePathIncludeAny
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
       OBJECT
                   tePathIncludeAll
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
       OBJECT tePathExclude
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
       OBJECT
                   tePathSetupPriority
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   tePathHoldPriority
       OBJECT
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   tePathProperties
       OBJECT
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   tePathAdminStatus
       OBJECT
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
       OBJECT tePathHopRowStatus SYNTAX RowStatus { active(1) }
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   tePathHopStorageType
       OBJECT
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   tePathHopAddrType
       OBJECT
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
                   tePathHopAddress
       OBJECT
       MIN-ACCESS read-only
       DESCRIPTION "Write access is not required."
    ::= { teModuleCompliance 3 }
teModuleServerFullCompliance MODULE-COMPLIANCE
```

```
STATUS
            current
DESCRIPTION "When this MIB module is implemented by a path
            computation server with support for read-create,
            then the implementation can claim full
            compliance.
MODULE
            -- enclosing module, i.e., TE-MIB
   MANDATORY-GROUPS {
       teTrafficEngineeringGroup
    }
   GROUP
               teNotificationGroup
   DESCRIPTION "Implementation of this group is optional."
   OBJECT
                teAdminGroupRowStatus
                RowStatus { active(1) }
   SYNTAX
   WRITE-SYNTAX RowStatus { createAndGo(4), destroy(6) }
   DESCRIPTION "Support for notInService, createAndWait, and
                notReady is not required.
   OBJECT
                teTunnelRowStatus
                RowStatus { active(1), notInService(2) }
   WRITE-SYNTAX RowStatus { active(1), notInService(2),
                            createAndGo(4), destroy(6)
   DESCRIPTION "Support for createAndWait and notReady is not
                required.
                teTunnelSourceAddressType
   DESCRIPTION "Write access is required. An implementation
                of a path computation server SHOULD support all
                types of tunnel source address types.
               tePathRowStatus
   OBJECT
            RowStatus { active(1), notInService(2) }
   SYNTAX
   WRITE-SYNTAX RowStatus { active(1), notInService(2),
                            createAndGo(4), destroy(6)
   DESCRIPTION "Support for createAndWait and notReady is not
                required.
   OBJECT
               tePathHopRowStatus
```

```
SYNTAX
                RowStatus { active(1), notInService(2) }
   WRITE-SYNTAX RowStatus { active(1), notInService(2),
                             createAndGo(4), destroy(6)
                           }
   DESCRIPTION "Support for createAndWait and notReady is not
                required.
::= { teModuleCompliance 4 }
```

END

6. References

6.1. Normative References

- [1] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997.
- [2] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Structure of Management Information Version 2 (SMIv2)", STD 58, RFC 2578, April 1999.
- [3] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Textual Conventions for SMIv2", STD 58, RFC 2579, April 1999.
- [4] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Conformance Statements for SMIv2", STD 58, RFC 2580, April 1999.
- [5] Nadeau, T. and J. Cucchiara, "Definitions of Textual Conventions (TCs) for Multiprotocol Label Switching (MPLS) Management", RFC 3811, June 2004.
- [6] Harrington, D., Presuhn, R., and B. Wijnen, "An Architecture for Describing Simple Network Management Protocol (SNMP) Management Frameworks", STD 62, RFC 3411, December 2002.
- [7] Awduche, D., Malcolm, J., Agogbua, J., O'Dell, M., and J. McManus, "Requirements for Traffic Engineering Over MPLS", RFC 2702, September 1999.

6.2. Informative References

[8] Awduche, D., Berger, L., Gan, D., Li, T., Srinivasan, V., and G. Swallow, "RSVP-TE: Extensions to RSVP for LSP Tunnels", RFC 3209, December 2001.

- [9] Case, J., Mundy, R., Partain, D., and B. Stewart, "Introduction and Applicability Statements for Internet-Standard Management Framework", RFC 3410, December 2002.
- [10] McCloghrie, K. and F. Kastenholz, "The Interfaces Group MIB", RFC 2863, June 2000.
- [11] Thaler, D., "IP Tunnel MIB", RFC 2667, August 1999.
- [12] Jamoussi, B., Andersson, L., Callon, R., Dantu, R., Wu, L., Doolan, P., Worster, T., Feldman, N., Fredette, A., Girish, M., Gray, E., Heinanen, J., Kilty, T., and A. Malis, "Constraint-Based LSP Setup using LDP", RFC 3212, January 2002.

7. Security Considerations

This MIB module relates to the configuration and management of Traffic Engineering tunnels. The unauthorized manipulation of fields in the tables teAdminGroupTable, teTunnelTable, tePathTable, and tePathHopTable may lead to tunnel flapping, tunnel paths being changed, or traffic being disrupted. In addition, if these tables are read by unauthorized parties, the information can be used to trace traffic patterns, traffic volumes, and tunnel paths. This may be considered proprietary and confidential information by some providers.

There are a number of management objects defined in this MIB module with a MAX-ACCESS clause of read-write and/or read-create. Such objects may be considered sensitive or vulnerable in some network environments. The support for SET operations in a non-secure environment without proper protection can have a negative effect on network operations. These are the tables and objects and their sensitivity/vulnerability:

teAdminGroupTable: Changing this will affect the semantics of include and exclude constraints, and thus traffic takes unintended routes.

teTunnelTable: Changing this affects many properties of traffic tunnels.

tePathTable: Changing this affects the constraints (including bandwidth) of tunnel paths, as well as the status of the path.

tePathHopTable: Changing this affects the route followed by a traffic tunnel path.

Some of the readable objects in this MIB module (i.e., objects with a MAX-ACCESS other than not-accessible) may be considered sensitive or vulnerable in some network environments. It is thus important to control even GET and/or NOTIFY access to these objects and possibly to even encrypt the values of these objects when sending them over the network via SNMP. These are the tables and objects and their sensitivity/vulnerability:

teTunnelTable: Describes tunnel endpoints and traffic volumes.

tePathTable: Describes path properties. tePathHopTable: Describes path routes.

SNMP versions prior to SNMPv3 did not include adequate security. Even if the network itself is secure (for example by using IPSec), even then, there is no control as to who on the secure network is allowed to access and GET/SET (read/change/create/delete) the objects in this MIB module.

It is RECOMMENDED that implementers consider the security features as provided by the SNMPv3 framework (see [9], section 8), including full support for the SNMPv3 cryptographic mechanisms (for authentication and privacy).

Further, deployment of SNMP versions prior to SNMPv3 is NOT RECOMMENDED. Instead, it is RECOMMENDED to deploy SNMPv3 and to enable cryptographic security. It is then a customer/operator responsibility to ensure that the SNMP entity giving access to an instance of this MIB module is properly configured to give access to the objects only to those principals (users) that have legitimate rights to indeed GET or SET (change/create/delete) them.

Acknowledgments

It was Tony Li's suggestion that the author embark on this MIB. Many thanks to him and to Der-Hwa Gan for their input and help.

Many thanks, too, to Bert Wijnen for his incredible help, both with improving the correctness, structure, and readability of the MIB module, and with the text of the RFC. Thanks also to Adrian Farrel for his detailed review.

Author's Address

Kireeti Kompella Juniper Networks, Inc. 1194 N. Mathilda Ave Sunnyvale, CA 94089

EMail: kireeti@juniper.net

Full Copyright Statement

Copyright (C) The Internet Society (2005).

This document is subject to the rights, licenses and restrictions contained in BCP 78, and except as set forth therein, the authors retain all their rights.

This document and the information contained herein are provided on an "AS IS" basis and THE CONTRIBUTOR, THE ORGANIZATION HE/SHE REPRESENTS OR IS SPONSORED BY (IF ANY), THE INTERNET SOCIETY AND THE INTERNET ENGINEERING TASK FORCE DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Intellectual Property

The IETF takes no position regarding the validity or scope of any Intellectual Property Rights or other rights that might be claimed to pertain to the implementation or use of the technology described in this document or the extent to which any license under such rights might or might not be available; nor does it represent that it has made any independent effort to identify any such rights. Information on the IETF's procedures with respect to rights in IETF Documents can be found in BCP 78 and BCP 79.

Copies of IPR disclosures made to the IETF Secretariat and any assurances of licenses to be made available, or the result of an attempt made to obtain a general license or permission for the use of such proprietary rights by implementers or users of this specification can be obtained from the IETF on-line IPR repository at http://www.ietf.org/ipr.

The IETF invites any interested party to bring to its attention any copyrights, patents or patent applications, or other proprietary rights that may cover technology that may be required to implement this standard. Please address the information to the IETF at ietf-ipr@ietf.org.

Acknowledgement

Funding for the RFC Editor function is currently provided by the Internet Society.