Network Working Group Request for Comments: 2940 Category: Standards Track A. Smith
Consultant
D. Partain
Ericsson
J. Seligson
Nortel Networks
October 2000

Definitions of Managed Objects for Common Open Policy Service (COPS)

Protocol Clients

Status of this Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

Copyright Notice

Copyright (C) The Internet Society (2000). All Rights Reserved.

Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in TCP/IP based internets. In particular it defines objects for managing a client of the Common Open Policy Service (COPS) protocol.

This memo includes a MIB module in a manner that is compliant to the SMIv2 [V2SMI].

Smith Standards Track [Page 1]

1. The SNMP Management Framework

The SNMP Management Framework presently consists of five major components:

- o An overall architecture, described in an Architecture for Describing SNMP Management Frameworks [ARCH].
- o Mechanisms for describing and naming objects and events for the purpose of management. The first version of this Structure of Management Information (SMI) is called SMIv1 and described in STD 16, RFC 1155 [V1SMI], STD 16, RFC 1212 [V1CONCISE] and RFC 1215 [V1TRAPS]. The second version, called SMIv2, is described in STD 58, RFC 2578 [V2SMI], STD 58, RFC 2579 [V2TC] and STD 58, RFC 2580 [V2CONFORM].
- o Message protocols for transferring management information. The first version of the SNMP message protocol is called SNMPv1 and described in STD 15, RFC 1157 [V1PROTO]. A second version of the SNMP message protocol, which is not an Internet standards track protocol, is called SNMPv2c and described in RFC 1901 [V2COMMUNITY] and RFC 1906 [V2TRANS]. The third version of the message protocol is called SNMPv3 and described in RFC1906 [V2TRANS], Message Processing and Dispatching [V3MPC] and User-based Security Model [V3USM].
- o Protocol operations for accessing management information. The first set of protocol operations and associated PDU formats is described in STD 15, RFC 1157 [V1PROTO]. A second set of protocol operations and associated PDU formats is described in RFC 1905 [V2PROTO].
- o A set of fundamental applications described in SNMPv3 Applications [V3APPS] and the view-based access control mechanism described in View-based Access Control Model [V3VACM].

A more detailed introduction to the current SNMP Management Framework can be found in RFC 2570 [V3INTRO].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. Objects in the MIB are defined using the mechanisms defined in the SMI.

This memo specifies a MIB module that is compliant to the SMIv2. A MIB conforming to the SMIv1 can be produced through the appropriate translations. The resulting translated MIB must be semantically equivalent, except where objects or events are omitted because no

translation is possible (use of Counter64). Some machine readable information in SMIv2 will be converted into textual descriptions in SMIv1 during the translation process. However, this loss of machine readable information is not considered to change the semantics of the MIB.

2. Overview

The COPS protocol [COPS] is a client-server protocol intended for the communication of policy requests and decisions between a Policy Enforcement Point (PEP) and a Policy Decision Point (PDP). The PEP acts as a COPS client in this scenario. The model for policy outsourcing, of which the COPS protocol provides one part, is described in [FRAMEWORK].

2.1. Scope

This MIB is intended to provide management of the important features of a COPS protocol client module. It does not provide management for a COPS server - this is outside the scope of the current memo. It provides for monitoring of status and protocol statistics, as well as for configuration of the client, in particular for telling it where to locate its servers. Other mechanisms for achieving this function without SNMP configuration might include use of the Service Location Protocol [SRVLOC] although this is outside the scope of this memo and are not specified by the COPS protocol itself.

This MIB also does not provide management of specific COPS client-types e.g., for use with the RSVP protocol [RSVP][COPSRSVP].

3. Structure of COPS Client MIB

Objects in this MIB are arranged into groups. Each group is organized as a set of related objects. The overall structure is described below.

3.1. copsClientCapabilitiesGroup

This group contains objects that represent COPS protocol capabilities implemented by this COPS client.

3.2. copsClientStatusGroup

This group contains objects that indicate the current status of connection(s) to COPS servers, including per-server protocol statistics. It maintains last-known statistics for all of the servers with which the client has ever been connected since agent restart.

Smith Standards Track [Page 3]

3.3. copsConfigGroup

This group contains objects that allow for configuration of COPS server addresses and the order to which connections should be attempted. It contains a table of per-server objects as well as scalars for configuration of the retry algorithm to be used by a client to obtain a connection to an appropriate server.

3.4. Textual Conventions

The datatypes CopsClientState, CopsServerEntryType, CopsErrorCode, CopsTcpPort and CopsAuthType are used as textual conventions in this document. These textual conventions have NO effect on either the syntax nor the semantics of any managed object. Objects defined using these conventions are always encoded by means of the rules that define their primitive type. Hence, no changes to the SMI or the SNMP are necessary to accommodate these textual conventions which are adopted merely for the convenience of readers.

3.5. Relationship to Other MIBs

3.5.1. Relationship to the 'system' group

This MIB contains definitions for a single COPS protocol client represented by a single SNMP agent and instance of the MIB-2 system group [MIB2]. It does not address the case of multiple co-located COPS protocol clients.

4. Definitions for COPS Client MIB

COPS-CLIENT-MIB DEFINITIONS ::= BEGIN

|
 | - |
 | _ |
 |
 | _ | _ |
|------|------|------|------|------|------|------|------|---|------|------|------|------|------|------|------|------|------|---|-------|------|---|---|
|
 | |
 | _ |
_ |
 | _ | _ |

IMPORTS

MODULE-IDENTITY, OBJECT-TYPE, Counter32, Integer32,
Unsigned32, mib-2
 FROM SNMPv2-SMI
TimeStamp, TimeInterval, RowStatus, TEXTUAL-CONVENTION
 FROM SNMPv2-TC
MODULE-COMPLIANCE, OBJECT-GROUP
 FROM SNMPv2-CONF
InetAddressType, InetAddress
 FROM INET-ADDRESS-MIB;

-- REFERENCE

Smith Standards Track [Page 4]

```
"The COPS (Common Open Policy Service) Protocol RFC 2748
copsClientMIB MODULE-IDENTITY
   LAST-UPDATED "200009280000Z"
   ORGANIZATION "IETF RSVP Admission Policy Working Group"
   CONTACT-INFO
              Andrew Smith (WG co-chair)
        Phone: +1 408 579 2821
        Email: ah_smith@pacbell.net
               Mark Stevens (WG co-chair)
        Phone: +1 978 287 9102
        Email: markstevens@lucent.com
        Editor: Andrew Smith
        Phone: +1 408 579 2821
        Email: ah smith@pacbell.net
        Editor: David Partain
        Phone: +46 13 28 41 44
        Email: David.Partain@ericsson.com
        Editor: John Seligson
        Phone: +1 408 495 2992
        Email: jseligso@nortelnetworks.com"
   DESCRIPTION
       "The COPS Client MIB module"
   REVISION "200009280000Z"
   DESCRIPTION "This version published as RFC 2940"
   ::= \{ mib-2 89 \}
copsClientMIBObjects OBJECT IDENTIFIER ::= { copsClientMIB 1 }
__ _____
-- Textual Conventions
CopsClientState ::= TEXTUAL-CONVENTION
   STATUS
           current
   DESCRIPTION
       "A value indicating the state of a COPS client."
   SYNTAX
              INTEGER {
           copsClientInvalid(1),
                                 -- default state.
           copsClientTcpconnected(2), -- TCP connection up but COPS
                                     -- not yet open.
```

```
copsClientAuthenticating(3), -- TCP connection up but still
                                    -- authenticating.
          copsClientSecAccepted(4), -- connection authenticated.
          -- client is in process of
                                   -- tearing down connection.
   }
CopsServerEntryType ::= TEXTUAL-CONVENTION
   STATUS current
   DESCRIPTION
      "A value indicating how a COPS server entry came into existence."
   SYNTAX INTEGER {
         copsServerStatic(1),
                                   -- configured by manager
          }
CopsErrorCode ::= TEXTUAL-CONVENTION
   STATUS current
   DESCRIPTION
       "A value describing a COPS protocol error. Codes are identical
       to those used by the COPS protocol itself."
   SYNTAX INTEGER {
          errorOther(0),
                                  -- none of the below
          errorBadHandle(1),
          errorInvalidHandleReference(2),
          errorBadMessageFormat(3),
          errorUnableToProcess(4),
          errorMandatoryClientSiMissing(5),
          errorUnsupportedClientType(6),
          errorMandatoryCopsObjectMissing(7),
          errorClientFailure(8),
          errorCommunicationFailure(9),
          errorUnspecified(10), -- client-type specific subcode
          errorShuttingDown(11),
          errorRedirectToPreferredServer(12),
          errorUnknownCopsObject(13),
          errorAuthenticationFailure(14),
          errorAuthenticationMissing(15)
-- REFERENCE
-- "RFC 2748 section 2.2.8"
CopsTcpPort ::= TEXTUAL-CONVENTION
   STATUS current
   DESCRIPTION
       "A value indicating a TCP protocol port number."
```

Smith Standards Track [Page 6]

```
SYNTAX
          INTEGER (0..65535)
CopsAuthType ::= TEXTUAL-CONVENTION
  STATUS
           current
  DESCRIPTION
     "A value indicating a type of security authentication mechanism."
        INTEGER {
     authNone(0),
     authOther(1),
     authIpSecAh(2),
     authIpSecEsp(3),
     authTls(4),
     authCopsIntegrity(5)
   }
__ ______
copsClientCapabilitiesGroup OBJECT IDENTIFIER
                    ::= { copsClientMIBObjects 1 }
-- Capabilities of the COPS client to connect to a COPS server:
copsClientCapabilities OBJECT-TYPE
  SYNTAX BITS {
     copsClientAuthIpSecAh(1) , -- supports IP-SEC Authentication
     copsClientAuthIpSecEsp(2), -- supports IP-SEC Encryption
     MAX-ACCESS read-only
  STATUS
        current
  DESCRIPTION
     "A list of the optional capabilities that this COPS client
     supports."
   ::= { copsClientCapabilitiesGroup 1 }
__ ______
copsClientStatusGroup OBJECT IDENTIFIER ::= { copsClientMIBObjects 2 }
__ _____
-- Current status of COPS server connections, all read-only.
```

Smith Standards Track [Page 7]

```
copsClientServerCurrentTable OBJECT-TYPE
    SYNTAX SEQUENCE OF CopsClientServerCurrentEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
        "A table of information regarding COPS servers as seen from the
       point of view of a COPS client. This table contains entries
       for both statically-configured and dynamically-learned servers
       (from a PDP Redirect operation). One entry exists in this table
       for each COPS Client-Type served by the COPS server. In addition,
       an entry will exist with copsClientServerClientType 0 (zero)
       representing information about the underlying connection itself:
       this is consistent with the COPS specification which reserves
       this value for this purpose."
    ::= { copsClientStatusGroup 1 }
copsClientServerCurrentEntry OBJECT-TYPE
    SYNTAX CopsClientServerCurrentEntry
   MAX-ACCESS not-accessible
   STATUS
           current
   DESCRIPTION
        "A set of information regarding a single COPS server serving
       a single COPS Client-Type from the point of view of a COPS
    INDEX { copsClientServerAddressType, copsClientServerAddress,
           copsClientServerClientType }
    ::= { copsClientServerCurrentTable 1 }
CopsClientServerCurrentEntry ::=
    SEQUENCE {
       copsClientServerAddressType
                                           InetAddressType,
        copsClientServerAddress
                                           InetAddress,
       copsClientServerClientType
                                           INTEGER,
       copsClientServerTcpPort
                                           CopsTcpPort,
       copsClientServerType
                                           CopsServerEntryType,
       copsClientServerAuthType
                                           CopsAuthType,
       copsClientServerLastConnAttempt
                                           TimeStamp,
                                           CopsClientState,
       copsClientState
       copsClientServerKeepaliveTime
                                           TimeInterval,
       copsClientServerAccountingTime
                                           TimeInterval,
       copsClientInPkts
                                           Counter32,
       copsClientOutPkts
                                           Counter32,
                                           Counter32,
       copsClientInErrs
       copsClientLastError
                                           CopsErrorCode,
       copsClientTcpConnectAttempts
                                           Counter32,
       copsClientTcpConnectFailures
                                           Counter32,
       copsClientOpenAttempts
                                           Counter32,
```

```
copsClientOpenFailures
                                           Counter32,
       copsClientErrUnsupportClienttype Counter32,
       copsClientErrUnknownOpcode
copsClientErrUnknownCnum
                                          Counter32,
                                          Counter32,
                                          Counter32,
       copsClientErrBadCtype
       copsClientErrBadSends
                                          Counter32,
       copsClientErrWrongObjects
                                         Counter32,
       copsClientErrWrongOpcode
                                          Counter32,
       copsClientKaTimedoutClients
copsClientErrAuthFailures
                                         Counter32,
                                          Counter32,
       copsClientErrAuthMissing
                                          Counter32
   }
copsClientServerAddressType OBJECT-TYPE
   SYNTAX InetAddressType
   MAX-ACCESS not-accessible
   STATUS
               current
   DESCRIPTION
       "The type of address in copsClientServerAddress."
    ::= { copsClientServerCurrentEntry 1 }
copsClientServerAddress OBJECT-TYPE
   SYNTAX InetAddress
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
       "The IPv4, IPv6 or DNS address of a COPS Server. Note that,
       since this is an index to the table, the DNS name must be
       short enough to fit into the maximum length of indices allowed
       by the management protocol in use."
   REFERENCE
       "RFC 2748 section 2.3"
    ::= { copsClientServerCurrentEntry 2 }
copsClientServerClientType OBJECT-TYPE
   SYNTAX INTEGER (0..65535)
   MAX-ACCESS not-accessible
   STATUS
              current
   DESCRIPTION
       "The COPS protocol Client-Type for which this entry
       applies. Multiple Client-Types can be served by a single
       COPS server. The value 0 (zero) indicates that this
       entry contains information about the underlying connection
       itself."
   REFERENCE
       "RFC 2748 section 6, IANA"
```

```
::= { copsClientServerCurrentEntry 3 }
copsClientServerTcpPort OBJECT-TYPE
   SYNTAX CopsTcpPort
   MAX-ACCESS read-only
   STATUS
              current
   DESCRIPTION
       "The TCP port number on the COPS server to which the
       client should connect/is connected."
    ::= { copsClientServerCurrentEntry 4 }
copsClientServerType OBJECT-TYPE
   SYNTAX CopsServerEntryType
   MAX-ACCESS read-only
   STATUS
              current
   DESCRIPTION
       "Indicator of the source of this COPS server information.
       COPS servers may be configured by network management
       into copsClientServerConfigTable and appear in this entry
       with type copsServerStatic(1). Alternatively, the may be
       notified from another COPS server by means of the COPS
       PDP-Redirect mechanism and appear as copsServerRedirect(2)."
    ::= { copsClientServerCurrentEntry 5 }
copsClientServerAuthType OBJECT-TYPE
   SYNTAX CopsAuthType
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
       "Indicator of the current security mode in use between
       client and this COPS server."
    ::= { copsClientServerCurrentEntry 6 }
copsClientServerLastConnAttempt OBJECT-TYPE
   SYNTAX TimeStamp
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
       "Timestamp of the last time that this client attempted to
       connect to this COPS server."
    ::= { copsClientServerCurrentEntry 7 }
copsClientState OBJECT-TYPE
   SYNTAX CopsClientState
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
       "The state of the connection and COPS protocol with respect
```

```
to this COPS server."
    ::= { copsClientServerCurrentEntry 8 }
copsClientServerKeepaliveTime OBJECT-TYPE
   SYNTAX TimeInterval
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "The value of the COPS protocol Keepalive timeout, in
       centiseconds, currently in use by this client, as
       specified by this COPS server in the Client-Accept operation.
       A value of zero indicates no keepalive activity is expected."
   REFERENCE
       "RFC 2748 section 3.7, 4.4"
    ::= { copsClientServerCurrentEntry 9 }
copsClientServerAccountingTime OBJECT-TYPE
   SYNTAX TimeInterval
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
       "The value of the COPS protocol Accounting timeout, in
       centiseconds, currently in use by this client, as specified
       by the COPS server in the Client-Accept operation. A value
       of zero indicates no accounting activity is to be performed."
   REFERENCE
       "RFC 2748 section 3.7"
    ::= { copsClientServerCurrentEntry 10 }
copsClientInPkts OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION
       "A count of the total number of COPS messages that this client
       has received from this COPS server marked for this Client-Type.
       This value is cumulative since agent restart and is not zeroed
       on new connections."
    ::= { copsClientServerCurrentEntry 11 }
copsClientOutPkts OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
       "A count of the total number of COPS messages that this client
       has sent to this COPS server marked for this Client-Type. This
       value is cumulative since agent restart and is not zeroed on new
```

```
connections."
    ::= { copsClientServerCurrentEntry 12 }
copsClientInErrs OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "A count of the total number of COPS messages that this client
       has received from this COPS server marked for this Client-Type
       that contained errors in syntax. This value is cumulative since
       agent restart and is not zeroed on new connections."
    ::= { copsClientServerCurrentEntry 13 }
copsClientLastError OBJECT-TYPE
   SYNTAX CopsErrorCode
   MAX-ACCESS read-only
   STATUS
              current
   DESCRIPTION
       "The code contained in the last COPS protocol Error Object
       received by this client from this COPS server marked for this
       Client-Type. This value is not zeroed on COPS Client-Open
       operations."
   REFERENCE
       "RFC 2748 section 2.2.8"
    ::= { copsClientServerCurrentEntry 14 }
copsClientTcpConnectAttempts OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
       "A count of the number of times that this COPS client has tried
        (successfully or otherwise) to open an TCP connection to a COPS
       server. This value is cumulative since agent restart and is not
       zeroed on new connections. This value is not incremented for
       entries representing a non-zero Client-Type."
    ::= { copsClientServerCurrentEntry 15 }
copsClientTcpConnectFailures OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
       "A count of the number of times that this COPS client has failed
       to open an TCP connection to a COPS server. This value is
       cumulative since agent restart and is not zeroed on new
       connections. This value is not incremented for
```

```
entries representing a non-zero Client-Type."
    ::= { copsClientServerCurrentEntry 16 }
copsClientOpenAttempts OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "A count of the number of times that this COPS client has tried
       to perform a COPS Client-Open to a COPS server for this
       Client-Type. This value is cumulative since agent restart and is
       not zeroed on new connections."
    ::= { copsClientServerCurrentEntry 17 }
copsClientOpenFailures OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
              current
   STATUS
   DESCRIPTION
       "A count of the number of times that this COPS client has failed
       to perform a COPS Client-Open to a COPS server for this
       Client-Type. This value is cumulative since agent restart and is
       not zeroed on new connections."
    ::= { copsClientServerCurrentEntry 18 }
copsClientErrUnsupportClienttype OBJECT-TYPE
    SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "A count of the total number of COPS messages that this client
       has received from COPS servers that referred to Client-Types
       that are unsupported by this client. This value is cumulative
       since agent restart and is not zeroed on new connections. This
       value is not incremented for entries representing a non-zero
       Client-Type."
    ::= { copsClientServerCurrentEntry 19 }
copsClientErrUnsupportedVersion OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "A count of the total number of COPS messages that this client
       has received from COPS servers marked for this Client-Type that
       had a COPS protocol Version number that is unsupported by this
       client. This value is cumulative since agent restart and is not
       zeroed on new connections."
```

```
::= { copsClientServerCurrentEntry 20 }
copsClientErrLengthMismatch OBJECT-TYPE
   SYNTAX
           Counter32
   MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION
        "A count of the total number of COPS messages that this client
       has received from COPS servers marked for this Client-Type that
       had a COPS protocol Message Length that did not match the actual
       received message. This value is cumulative since agent restart
       and is not zeroed on new connections."
    ::= { copsClientServerCurrentEntry 21 }
copsClientErrUnknownOpcode OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
              current
   STATUS
   DESCRIPTION
       "A count of the total number of COPS messages that this client
       has received from COPS servers marked for this Client-Type that
       had a COPS protocol Op Code that was unrecognised by this
       client. This value is cumulative since agent restart and is not
       zeroed on new connections."
    ::= { copsClientServerCurrentEntry 22 }
copsClientErrUnknownCnum OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS
            current
   DESCRIPTION
       "A count of the total number of COPS messages that this client
       has received from COPS servers marked for this Client-Type that
       contained a COPS protocol object C-Num that was unrecognised by
       this client. This value is cumulative since agent restart and is
       not zeroed on new connections."
    ::= { copsClientServerCurrentEntry 23 }
copsClientErrBadCtype OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "A count of the total number of COPS messages that this client
       has received from COPS servers marked for this Client-Type that
       contained a COPS protocol object C-Type that was not defined for
       the C-Nums known by this client. This value is cumulative since
       agent restart and is not zeroed on new connections."
```

```
::= { copsClientServerCurrentEntry 24 }
copsClientErrBadSends OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS
               current
   DESCRIPTION
        "A count of the total number of COPS messages that this client
       attempted to send to COPS servers marked for this Client-Type
       that resulted in a transmit error. This value is cumulative
       since agent restart and is not zeroed on new connections."
    ::= { copsClientServerCurrentEntry 25 }
copsClientErrWrongObjects OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS
              current
   DESCRIPTION
       "A count of the total number of COPS messages that this client
       has received from COPS servers marked for this Client-Type that
       did not contain a permitted set of COPS protocol objects. This
       value is cumulative since agent restart and is not zeroed on new
       connections."
    ::= { copsClientServerCurrentEntry 26 }
copsClientErrWrongOpcode OBJECT-TYPE
    SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "A count of the total number of COPS messages that this client
       has received from COPS servers marked for this Client-Type that
       had a COPS protocol Op Code that should not have been sent to a
       COPS client e.g. Open-Requests. This value is cumulative since
       agent restart and is not zeroed on new connections."
    ::= { copsClientServerCurrentEntry 27 }
copsClientKaTimedoutClients OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
        "A count of the total number of times that this client has
       been shut down for this Client-Type by COPS servers that had
       detected a COPS protocol Keepalive timeout. This value is
       cumulative since agent restart and is not zeroed on new
       connections."
    ::= { copsClientServerCurrentEntry 28 }
```

```
copsClientErrAuthFailures OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
       "A count of the total number of times that this client has
       received a COPS message marked for this Client-Type which
       could not be authenticated using the authentication mechanism
       used by this client."
   ::= { copsClientServerCurrentEntry 29 }
copsClientErrAuthMissing OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS
             current
   DESCRIPTION
       "A count of the total number of times that this client has
       received a COPS message marked for this Client-Type which did not
       contain authentication information."
   ::= { copsClientServerCurrentEntry 30 }
__ ______
copsClientConfigGroup OBJECT IDENTIFIER ::= { copsClientMIBObjects 3 }
__ ______
copsClientServerConfigTable OBJECT-TYPE
    SYNTAX SEQUENCE OF CopsClientServerConfigEntry
   MAX-ACCESS not-accessible
   STATUS
              current
   DESCRIPTION
       "Table of possible COPS servers to try to connect to in order
       of copsClientServerConfigPriority. There may be multiple
       entries in this table for the same server and client-type which
       specify different security mechanisms: these mechanisms will
       be attempted by the client in the priority order given. Note
       that a server learned by means of PDPRedirect always takes
       priority over any of these configured entries."
   ::= { copsClientConfigGroup 1 }
copsClientServerConfigEntry OBJECT-TYPE
   SYNTAX CopsClientServerConfigEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
       "A set of configuration information regarding a single
```

```
COPS server from the point of view of a COPS client."
   INDEX { copsClientServerConfigAddrType,
          copsClientServerConfigAddress,
          copsClientServerConfigClientType,
          copsClientServerConfigAuthType }
   ::= { copsClientServerConfigTable 1 }
CopsClientServerConfigEntry ::=
   SEQUENCE {
       copsClientServerConfigAddress
                                      InetAddress,
       copsClientServerConfigPriority
                                       Integer32,
       copsClientServerConfigRowStatus RowStatus
   }
copsClientServerConfigAddrType OBJECT-TYPE
   SYNTAX InetAddressType
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
       "The type of address in copsClientServerConfigAddress."
   ::= { copsClientServerConfigEntry 1 }
copsClientServerConfigAddress OBJECT-TYPE
   SYNTAX InetAddress
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
       "The IPv4, IPv6 or DNS address of a COPS Server. Note that,
       since this is an index to the table, the DNS name must be
       short enough to fit into the maximum length of indices allowed
       by the management protocol in use."
   REFERENCE
       "RFC 2748 section 2.3"
   ::= { copsClientServerConfigEntry 2 }
copsClientServerConfigClientType OBJECT-TYPE
   SYNTAX INTEGER (0..65535)
   MAX-ACCESS not-accessible
          current
   STATUS
   DESCRIPTION
       "The COPS protocol Client-Type for which this entry
       applies and for which this COPS server is capable
       of serving. Multiple Client-Types can be served by a
       single COPS server."
```

```
REFERENCE
       "RFC 2748 section 6, IANA"
    ::= { copsClientServerConfigEntry 3 }
copsClientServerConfigAuthType OBJECT-TYPE
   SYNTAX
           CopsAuthType
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
       "The type of authentication mechanism for this COPS client
       to request when negotiating security at the start of a
       connection to a COPS server."
   REFERENCE
       "RFC 2748 section 4."
   ::= { copsClientServerConfigEntry 4 }
copsClientServerConfigTcpPort OBJECT-TYPE
   SYNTAX CopsTcpPort
   MAX-ACCESS read-create
   STATUS
           current
   DESCRIPTION
       "The TCP port number on the COPS server to which the
       client should connect."
    ::= { copsClientServerConfigEntry 5 }
copsClientServerConfigPriority OBJECT-TYPE
   SYNTAX Integer32
   MAX-ACCESS read-create
   STATUS
           current
   DESCRIPTION
       "The priority of this entry relative to other entries.
       COPS client will attempt to contact COPS servers for the
       appropriate Client-Type. Higher numbers are tried first. The
       order to be used amongst server entries with the same priority
       is undefined. COPS servers that are notified to the client using
       the COPS protocol PDP-Redirect mechanism are always used in
       preference to any entries in this table."
    ::= { copsClientServerConfigEntry 6 }
copsClientServerConfigRowStatus OBJECT-TYPE
   SYNTAX RowStatus
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
       "State of this entry in the table."
   ::= { copsClientServerConfigEntry 7 }
```

```
copsClientServerConfigRetryAlgrm OBJECT-TYPE
   SYNTAX
              INTEGER {
                   other(1),
                   sequential(2),
                   roundRobin(3)
   MAX-ACCESS read-write
   STATUS
           current
   DESCRIPTION
        "The algorithm by which the client should retry when it
        fails to connect to a COPS server."
   DEFVAL { sequential }
    ::= { copsClientConfigGroup 2 }
copsClientServerConfigRetryCount OBJECT-TYPE
   SYNTAX Unsigned32
   MAX-ACCESS read-write
   STATUS
               current
   DESCRIPTION
       "A retry count for use by the retry algorithm. Each retry
        algorithm needs to specify how it uses this value.
        For the 'sequential(2)' algorithm, this value is the
        number of times the client should retry to connect
        to one COPS server before moving on to another.
        For the 'roundRobin(3)' algorithm, this value is not used."
   DEFVAL { 1 }
    ::= { copsClientConfigGroup 3 }
copsClientServerConfigRetryIntvl OBJECT-TYPE
   SYNTAX TimeInterval
              "centi-seconds"
   UNITS
   MAX-ACCESS read-write
               current
   DESCRIPTION
       "A retry interval for use by the retry algorithm. Each retry
        algorithm needs to specify how it uses this value.
        For the 'sequential(2)' algorithm, this value is the time to
        wait between retries of a connection to the same COPS server.
        For the 'roundRobin(3)' algorithm, the client always attempts
        to connect to each Server in turn, until one succeeds or they
        all fail; if they all fail, then the client waits for the value
        of this interval before restarting the algorithm."
   DEFVAL { 1000 }
    ::= { copsClientConfigGroup 4 }
```

```
-- Conformance Information
__ ______
copsClientConformance OBJECT IDENTIFIER ::= { copsClientMIB 2 }
copsClientGroups OBJECT IDENTIFIER ::= { copsClientConformance 1 }
copsClientCompliances OBJECT IDENTIFIER ::= { copsClientConformance 2 }
__ ______
-- units of conformance
copsDeviceStatusGroup OBJECT-GROUP
   OBJECTS {
       copsClientCapabilities,
       copsClientServerTcpPort, copsClientServerType,
       copsClientServerAuthType, copsClientServerLastConnAttempt,
       copsClientState, copsClientServerKeepaliveTime,
       copsClientServerAccountingTime, copsClientInPkts,
       copsClientOutPkts, copsClientInErrs, copsClientLastError,
       copsClientTcpConnectAttempts, copsClientTcpConnectFailures,
       copsClientOpenAttempts, copsClientOpenFailures,
       copsClientErrUnsupportClienttype,
       \verb|copsClientErrUnsupportedVersion|, | \verb|copsClientErrLengthMismatch|, | \\
       copsClientErrUnknownOpcode, copsClientErrUnknownCnum,
       copsClientErrBadCtype, copsClientErrBadSends,
       copsClientErrWrongObjects, copsClientErrWrongOpcode,
       copsClientKaTimedoutClients, copsClientErrAuthFailures,
       copsClientErrAuthMissing
   }
   STATUS
              current
   DESCRIPTION
       "A collection of objects for monitoring the status of
       connections to COPS servers and statistics for a COPS client."
    ::= { copsClientGroups 1 }
copsDeviceConfigGroup OBJECT-GROUP
   OBJECTS {
       copsClientServerConfigTcpPort, copsClientServerConfigPriority,
       copsClientServerConfigRowStatus,
       copsClientServerConfigRetryAlgrm,
       copsClientServerConfigRetryCount,
       copsClientServerConfigRetryIntvl
   STATUS
              current
   DESCRIPTION
       "A collection of objects for configuring COPS server
```

```
information."
   ::= { copsClientGroups 2 }
__ _____
-- compliance statements
copsClientCompliance MODULE-COMPLIANCE
   STATUS current
   DESCRIPTION
       "The compliance statement for device support of
       management of the COPS client."
   MODULE
       MANDATORY-GROUPS {
          copsDeviceStatusGroup, copsDeviceConfigGroup
       OBJECT
                 copsClientServerConfigTcpPort
       MIN-ACCESS read-only
       DESCRIPTION
           "Write access is required only if the device supports the
           configuration of COPS server information."
                  copsClientServerConfigPriority
       MIN-ACCESS read-only
       DESCRIPTION
           "Write access is required only if the device supports the
           configuration of COPS server information."
                  copsClientServerConfigRowStatus
       OBJECT
       MIN-ACCESS read-only
       DESCRIPTION
           "Write access is required only if the device supports the
           configuration of COPS server information."
                 copsClientServerConfigRetryAlgrm
       OBJECT
       MIN-ACCESS read-only
       DESCRIPTION
           "Write access is required only if the device supports the
           configuration of COPS server information."
       OBJECT copsClientServerConfigRetryCount
       MIN-ACCESS read-only
       DESCRIPTION
           "Write access is required only if the device supports the
           configuration of COPS server information."
```

OBJECT copsClientServerConfigRetryIntvl
MIN-ACCESS read-only
DESCRIPTION
"Write access is required only if the device supports the

"Write access is required only if the device supports the configuration of COPS server information."

::= { copsClientCompliances 1 }

END

5. Acknowledgments

This document describes instrumentation for the client side of the COPS protocol which was defined by the RSVP Admission Policy (rap) Working Group, now known as the Resource Allocation Protocol (rap) Working Group.

6. Security Considerations

There are a number of management objects defined in this MIB that have a MAX-ACCESS clause of read-create. Such objects may be considered sensitive or vulnerable in some network environments. The support for SET operations in a non-secure environment without proper protection can have a negative effect on network operations.

SNMPv1 by itself is not a secure environment. Even if the network itself is secure (for example by using IPSec), even then, there is no control as to who on the secure network is allowed to access and GET/SET (read/change/create/delete) the objects in this MIB.

It is recommended that the implementers consider the security features as provided by the SNMPv3 framework. Specifically, the use of the User-based Security Model [USM] and the View-based Access Control Model [VACM] is recommended.

It is then a customer/user responsibility to ensure that the SNMP entity giving access to an instance of this MIB, is properly configured to give access to the objects only to those principals (users) that have legitimate rights to indeed GET or SET (change/create/delete) them.

7. References

- [ARCH] Harrington, D., Presuhn, R. and B. Wijnen, "An Architecture for Describing SNMP Management Frameworks", RFC 2571, April 1999.
- [V1PROTO] Case, J., Fedor, M., Schoffstall, M. and J. Davin,
 "Simple Network Management Protocol", STD 15, RFC 1157,
 May 1990.
- [V1SMI] Rose, M. and K. McCloghrie, "Structure and Identification of Management Information for TCP/IP-based Internets", STD 16, RFC 1155, May 1990.
- [V1TRAPS] Rose, M., "A Convention for Defining Traps for use with the SNMP", RFC 1215, March 1991.
- [V2SMI] McCloghrie, K., Perkins, D., Schoenwaelder, J., Case, J., Rose, M. and S. Waldbusser, "Structure of Management Information Version 2 (SMIv2)", STD 58, RFC 2578, April 1999.
- [V2TC] McCloghrie, K., Perkins, D., Schoenwaelder, J., Case, J., Rose, M. and S. Waldbusser, "Textual Conventions for SMIv2", STD 58, RFC 2579, April 1999.
- [V2CONFORM] McCloghrie, K., Perkins, D., Schoenwaelder, J., Case, J., Rose, M. and S. Waldbusser, "Conformance Statements for SMIv2", STD 58, RFC 2580, April 1999.
- [V2COMMUNITY] Case, J., McCloghrie, K., Rose, M. and S. Waldbusser, "Introduction to Community-based SNMPv2", RFC 1901, January 1996.
- [V2TRANS] Case, J., McCloghrie, K., Rose, M. and S. Waldbusser,
 "Transport Mappings for Version 2 of the Simple Network
 Management Protocol (SNMPv2)", RFC 1906, January 1996.
- [V2PROTO] Case, J., McCloghrie, K., Rose, M. and S. Waldbusser, "Protocol Operations for Version 2 of the Simple Network Management Protocol (SNMPv2)", RFC 1905, January 1996.

- [V3INTRO] Case, J., Mundy, R., Partain, D. and B. Stewart,
 "Introduction to Version 3 of the Internet-standard
 Network Management Framework", RFC 2570, April 1999.
- [V3MPC] Case, J., Harrington D., Presuhn R. and B. Wijnen,
 "Message Processing and Dispatching for the Simple
 Network Management Protocol (SNMP)", RFC 2572, April
 1999.
- [V3USM] Blumenthal, U. and B. Wijnen, "The User-Based Security Model (USM) for Version 3 of the Simple Network Management Protocol (SNMPv3)", RFC 2574, April 1999.
- [V3APPS] Levi, D., Meyer, P. and B. Stewart, "SNMP Applications", RFC 2573, April 1999.
- [V3VACM] Wijnen, B., Presuhn, R. and K. McCloghrie, "View-based Access Control Model for the Simple Network Management Protocol (SNMP)", RFC 2575, April 1999.
- [MIB2] McCloghrie K. and M. Rose, "Management Information Base for Network Management of TCP/IP-based internets", STD 17, RFC 1213, March 1991.
- [FRAMEWORK] Yavatkar, R., Pendarakis, D. and Guerin, R., "A Framework for Policy-based Admission Control", RFC 2753, January 2000.
- [COPS] Boyle, J., Cohen, R., Durham, D., Herzog, S., Rajan, R. and A. Sastry, "The COPS (Common Open Policy Service) Protocol", RFC 2748, January 2000.
- [RSVP] Braden, R. ed., Zhang, L., Berson, S., Herzog, S. and S. Jamin, "Resource ReSerVation Protocol (RSVP) Version 1 Functional Specification", RFC 2205, September 1997.
- [COPSRSVP] Boyle, J., Cohen, R., Durham, D., Herzog, S., Rajan, R. and A. Sastry, "COPS Usage for RSVP", RFC 2749, January 2000.
- [SRVLOC] Guttman, E., Perkins, C., Veizades, J. and M. Day, "Service Location Protocol, Version 2", RFC 2608, June 1999.
- [ADDRESSMIB] Daniele, M., Haberman, B., Routhier, S. and J. Schoenwaelder, "Textual Conventions for Internet Network Addresses", RFC 2851, June 2000.

[PROCESS] Bradner, S., "The Internet Standards Process -- Revision 3", BCP 9, RFC 2026, October 1996.

8. Authors' Addresses

Andrew Smith

Fax: +1 415 345 1827 Email: ah_smith@pacbell.net

David Partain
Ericsson Radio Systems
Research and Innovation
P.O. Box 1248
SE-581 12 Linkoping
Sweden

Phone: +46 13 28 41 44

EMail: David.Partain@ericsson.com

John Seligson Nortel Networks, Inc. 4401 Great America Parkway Santa Clara, CA 95054 USA

Phone: +1 408 495 2992

EMail: jseligso@nortelnetworks.com

9. Notices

The IETF takes no position regarding the validity or scope of any intellectual property or other rights that might be claimed to pertain to the implementation or use of the technology described in this document or the extent to which any license under such rights might or might not be available; neither does it represent that it has made any effort to identify any such rights. Information on the IETF's procedures with respect to rights in standards-track and standards-related documentation can be found in BCP-11. Copies of claims of rights made available for publication and any assurances of licenses to be made available, or the result of an attempt made to obtain a general license or permission for the use of such proprietary rights by implementors or users of this specification can be obtained from the IETF Secretariat.

The IETF invites any interested party to bring to its attention any copyrights, patents or patent applications, or other proprietary rights which may cover technology that may be required to practice this standard. Please address the information to the IETF Executive Director.

Smith Standards Track [Page 26]

10. Full Copyright Statement

Copyright (C) The Internet Society (2000). All Rights Reserved.

This document and translations of it may be copied and furnished to others, and derivative works that comment on or otherwise explain it or assist in its implementation may be prepared, copied, published and distributed, in whole or in part, without restriction of any kind, provided that the above copyright notice and this paragraph are included on all such copies and derivative works. However, this document itself may not be modified in any way, such as by removing the copyright notice or references to the Internet Society or other Internet organizations, except as needed for the purpose of developing Internet standards in which case the procedures for copyrights defined in the Internet Standards process must be followed, or as required to translate it into languages other than English.

The limited permissions granted above are perpetual and will not be revoked by the Internet Society or its successors or assigns.

This document and the information contained herein is provided on an "AS IS" basis and THE INTERNET SOCIETY AND THE INTERNET ENGINEERING TASK FORCE DISCLAIMS ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

${\tt Acknowledgement}$

Funding for the RFC Editor function is currently provided by the Internet Society.