Network Working Group Request for Comments: 1451

J. Case
SNMP Research, Inc.
K. McCloghrie
Hughes LAN Systems
M. Rose
Dover Beach Consulting, Inc.
S. Waldbusser
Carnegie Mellon University
April 1993

# Manager-to-Manager Management Information Base

#### Status of this Memo

This RFC specifes an IAB standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "IAB Official Protocol Standards" for the standardization state and status of this protocol. Distribution of this memo is unlimited.

## Table of Contents

1 Introduction	2
1.1 A Note on Terminology	2
2 Overview	3
2.1 A SNMPv2 Entity Acting in a Dual Role	3
2.2 Alarms, Events, and Notifications	3
2.3 Access Control	4
3 Definitions	6
3.1 The Alarm Group	7
3.1.1 Alarm-Related Notifications	20
3.2 The Event Group	21
3.3 Conformance Information	29
3.3.1 Compliance Statements	29
3.3.2 Units of Conformance	29
4 Acknowledgements	31
5 References	35
6 Security Considerations	36
7 Authors' Addresses	36

#### 1. Introduction

A network management system contains: several (potentially many) nodes, each with a processing entity, termed an agent, which has access to management instrumentation; at least one management station; and, a management protocol, used to convey management information between the agents and management stations. Operations of the protocol are carried out under an administrative framework which defines both authentication and authorization policies.

Network management stations execute management applications which monitor and control network elements. Network elements are devices such as hosts, routers, terminal servers, etc., which are monitored and controlled through access to their management information.

Management information is viewed as a collection of managed objects, residing in a virtual information store, termed the Management Information Base (MIB). Collections of related objects are defined in MIB modules. These modules are written using a subset of OSI's Abstract Syntax Notation One (ASN.1) [1], termed the Structure of Management Information (SMI) [2].

The management protocol, version 2 of the Simple Network Management Protocol [3], provides for the exchange of messages which convey management information between the agents and the management stations, including between management stations. It is the purpose of this document to define managed objects which describe the behavior of a SNMPv2 entity acting in both a manager role and an agent role.

# 1.1. A Note on Terminology

For the purpose of exposition, the original Internet-standard Network Management Framework, as described in RFCs 1155, 1157, and 1212, is termed the SNMP version 1 framework (SNMPv1). The current framework is termed the SNMP version 2 framework (SNMPv2).

#### 2. Overview

The purpose of this MIB is to provide the means for coordination between multiple management stations. That is, the means by which the controlling and monitoring functions of network management can be distributed amongst multiple management stations. Such distribution facilitates the scaling of network management solutions based on the SNMPv2 to meet the needs of very large networks, or of networks composed of multiple interconnected administrations. Specifically, this MIB provides the means for one management station to request management services from another management station.

## 2.1. A SNMPv2 Entity Acting in a Dual Role

A management station providing services to other management station(s), is a SNMPv2 entity which acts in the dual role of both manager and agent; the requests for service are received through acting in an agent role (with respect to the managed objects defined in this MIB), and the requested services are performed through acting in a manager role.

## 2.2. Alarms, Events, and Notifications

In this initial version, this MIB defines the concepts of "alarms", "events", and "notifications". Each alarm is a specific condition detected through the periodic (at a configured sampling interval) monitoring of the value of a specific management information variable. An example of an alarm condition is when the monitored variable falls outside a configured range. Each alarm condition triggers an event, and each event can cause (one or more) notifications to be reported to other management stations using the Inform-Request PDU.

Specifically, this MIB defines three MIB tables and a number of scalar objects. The three tables are: the Alarm Table, the Event Table, and the Notification Table.

#### 2.3. Access Control

The Administrative Model for SNMPv2 document [4] includes an access control model, which must not be subverted by allowing access to management information variables via the Alarm table. That is, access to a monitored variable via the Alarm table must be controlled according to the identity of the management station accessing the particular entry in the Alarm table.

An entry in the Alarm table provides the means to configure the sampling of the value of a MIB variable in the MIB view associated with the specified context (which can refer to object resources that are either local or remote). The sampling is done by (conceptually or actually) issuing a SNMPv2 request to retrieve the variable's value. This request is authenticated and/or protected from disclosure according to a source party and a destination party pair which has access to the indicated context.

Thus, to provide the required access control, the initial MIB view assigned, by convention, to parties on SNMPv2 entities that implement the snmpAlarmTable, must include the component:

```
viewSubtree = { snmpAlarm }
viewStatus = { excluded }
viewMask = { ''H }
```

Then, the MIB view associated with the context, requestContext, accessible by a requesting management station, can be configured to include specific Alarm table entries — the ones associated with those contexts to which the requesting management station has access.

In particular, to provide a requestContext with access to the sampling context sampleContext, the following family of view subtrees would be included for the requestContext on the SNMPv2 entity acting in a dual role:

```
{ snmpAlarmEntry WILDCARD sampleContext }
Which would be configured in the party MIB [5] as:
contextIdentity = { requestContext }
contextViewIndex = { ViewIndex }
```

```
RFC 1451 Manager-to-Manager MIB April 1993
```

#### 3. Definitions

```
SNMPv2-M2M-MIB DEFINITIONS ::= BEGIN
IMPORTS
   MODULE-IDENTITY, OBJECT-TYPE, NOTIFICATION-TYPE,
    Integer32, Counter32, snmpModules
        FROM SNMPv2-SMI
   DisplayString, InstancePointer, RowStatus, TimeStamp
       FROM SNMPv2-TC
    MODULE-COMPLIANCE, OBJECT-GROUP
       FROM SNMPv2-CONF
    contextIdentity
       FROM SNMPv2-PARTY-MIB;
snmpM2M MODULE-IDENTITY
   LAST-UPDATED "9304010000Z"
    ORGANIZATION "IETF SNMPv2 Working Group"
    CONTACT-INFO
                     Steven Waldbusser
             Postal: Carnegie Mellon University
                     4910 Forbes Ave
                     Pittsburgh, PA 15213
                Tel: +1 412 268 6628
                Fax: +1 412 268 4987
             E-mail: waldbusser@cmu.edu"
    DESCRIPTION
            "The Manager-to-Manager MIB module."
    ::= { snmpModules 2 }
snmpM2MObjects OBJECT IDENTIFIER ::= { snmpM2M 1 }
```

```
-- the alarm group
-- a collection of objects allowing the description and
-- configuration of threshold alarms from a SNMPv2 entity
-- acting in a dual role.
snmpAlarm
              OBJECT IDENTIFIER ::= { snmpM2MObjects 1 }
-- This Alarm mechanism periodically takes statistical samples
-- from variables available via SNMPv2 and compares them to
-- thresholds that have been configured. The alarm table
-- stores configuration entries that each define a variable,
-- polling period, and threshold parameters. If a sample is
-- found to cross the threshold values, an event is generated.
-- Only variables that resolve to an ASN.1 primitive type of
-- INTEGER (Integer32, Counter32, Gauge32, TimeTicks,
-- Counter64, or UInteger32) may be monitored in this way.
-- This function has a hysteresis mechanism to limit the
-- generation of events. This mechanism generates one event
-- as a threshold is crossed in the appropriate direction. No
-- more events are generated for that threshold until the
-- opposite threshold is crossed.
-- In the case of sampling a deltaValue, an entity may
-- implement this mechanism with more precision if it takes a
-- delta sample twice per period, each time comparing the sum
-- of the latest two samples to the threshold. This allows
-- the detection of threshold crossings that span the sampling
-- boundary. Note that this does not require any special
-- configuration of the threshold value. It is suggested that
-- entities implement this more precise algorithm.
```

```
snmpAlarmNextIndex OBJECT-TYPE
   SYNTAX INTEGER (0..65535)
   MAX-ACCESS read-only
   STATUS
           current
   DESCRIPTION
           "The index number of the next appropriate
           unassigned entry in the snmpAlarmTable. The value
           O indicates that no unassigned entries are
           available.
           A management station should create new entries in
           the snmpAlarmTable using this algorithm: first,
           issue a management protocol retrieval operation to
           determine the value of snmpAlarmNextIndex; and,
           second, issue a management protocol set operation
           to create an instance of the snmpAlarmStatus
           object setting its value to 'createAndGo' or
            'createAndWait' (as specified in the description
           of the RowStatus textual convention)."
    ::= { snmpAlarm 1 }
snmpAlarmTable OBJECT-TYPE
   SYNTAX SEQUENCE OF SnmpAlarmEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
           "A list of snmpAlarm entries."
    ::= { snmpAlarm 2 }
snmpAlarmEntry OBJECT-TYPE
   SYNTAX SnmpAlarmEntry
   MAX-ACCESS not-accessible
   STATUS
           current
   DESCRIPTION
            "A list of parameters that set up a periodic
           sampling query to check for alarm conditions.
           contextIdentity included in the INDEX clause is
           the context to which the sampling queries are
           directed."
              { contextIdentity, snmpAlarmIndex }
    ::= { snmpAlarmTable 1 }
```

```
SnmpAlarmEntry ::= SEQUENCE {
   snmpAlarmIndex
                                     INTEGER,
   snmpAlarmVariable
                                     InstancePointer,
   snmpAlarmInterval
                                    Integer32,
   snmpAlarmSampleType
                                    INTEGER,
                                    Integer32,
   snmpAlarmValue
   snmpAlarmStartupAlarm
                                     INTEGER,
   snmpAlarmRisingThreshold
                                     Integer32,
   snmpAlarmFallingThreshold
                                    Integer32,
   snmpAlarmRisingEventIndex
                                    INTEGER,
   snmpAlarmFallingEventIndex
                                    INTEGER,
   snmpAlarmUnavailableEventIndex
                                    INTEGER,
   snmpAlarmStatus
                                     RowStatus
}
snmpAlarmIndex OBJECT-TYPE
   SYNTAX INTEGER (1..65535)
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
           "An index that uniquely identifies an entry in the
           snmpAlarm table for a particular sampling context.
           Each such entry defines a diagnostic sample at a
           particular interval for a variable in the
           particular context's object resources."
    ::= { snmpAlarmEntry 1 }
```

snmpAlarmVariable OBJECT-TYPE
SYNTAX InstancePointer
MAX-ACCESS read-create
STATUS current
DESCRIPTION

"The object identifier of the particular variable to be sampled. Only variables that resolve to an ASN.1 primitive type of INTEGER (Integer32, Counter32, Gauge32, TimeTicks, Counter64, or UInteger32) may be sampled.

If it is detected by an error response of authorizationError, noSuchObject, or noSuchInstance that the variable name of an established snmpAlarmEntry is no longer available in the sampling context, a single snmpObjectUnavailableAlarm event is generated and the status of this snmpAlarmEntry is set to 'destroy'. Likewise, if the syntax of the variable retrieved by the query is not Integer32, Counter32, Gauge32, TimeTicks, Counter64, or UInteger32, the same actions will be taken.

If the SNMPv2 entity acting in a dual role detects that the sampled value can not be obtained due to lack of response to management queries, it should either:

1) Set the status of this snmpAlarmEntry to 'destroy', if it is determined that further communication is not possible;

or,

2) Delete the associated snmpAlarmValue instance (but not the entire conceptual row), and continue to attempt to sample the variable and recreate the associated snmpAlarmValue instance should communication be reestablished.

An attempt to modify this object will fail with an 'inconsistentValue' error if the associated snmpAlarmStatus object would be equal to 'active' both before and after the modification attempt."

```
::= { snmpAlarmEntry 2 }
snmpAlarmInterval OBJECT-TYPE
   SYNTAX
             Integer32
   UNITS
             "seconds"
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
           "The interval in seconds over which the data is
           sampled and compared with the rising and falling
           thresholds. When setting this object and the
           sampling type is 'deltaValue', care should be
           taken to ensure that the change during this
           interval of the variable being sampled will not
           exceed the (-2^31...2^31-1) range of the
           snmpAlarmValue.
           An attempt to modify this object will fail with an
           'inconsistentValue' error if the associated
           snmpAlarmStatus object would be equal to 'active'
           both before and after the modification attempt."
    ::= { snmpAlarmEntry 3 }
```

```
snmpAlarmSampleType OBJECT-TYPE
   SYNTAX
            INTEGER {
                  absoluteValue(1),
                  deltaValue(2)
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
            "The method of sampling the selected variable and
           calculating the value to be compared against the
           thresholds. If the value of this object is
            'absoluteValue', the value of the selected
           variable at the end of the sampling interval will
           be compared directly with both the
           snmpAlarmRisingThreshold and the
            snmpAlarmFallingThreshold values. If the value of
           this object is 'deltaValue', the value of the
           selected variable at the end of the sampling
           interval will be subtracted from its value at the
           end of the previous sampling interval, and the
           difference compared with both the
           snmpAlarmRisingThreshold and the
           snmpAlarmFallingThreshold values.
           An attempt to modify this object will fail with an
            'inconsistentValue' error if the associated
           snmpAlarmStatus object would be equal to 'active'
           both before and after the modification attempt."
   DEFVAL { deltaValue }
    ::= { snmpAlarmEntry 4 }
```

snmpAlarmValue OBJECT-TYPE
SYNTAX Integer32
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"The value of the statistic during the last sampling period. The value during the current sampling period is not made available until the period is completed. If the value of the statistic does not fit in the signed 32 bit representation of this object, it should be truncated in an implementation specific manner.

Note that if the associated snmpAlarmSampleType is set to 'deltaValue', the value of this object is the difference in the sampled variable since the last sample.

This object will be created by the SNMPv2 entity acting in a dual role when this entry is set to 'active', and the first sampling period has completed. It may be created and deleted at other times by the SNMPv2 entity acting in a dual role when the sampled value can not be obtained, as specified in the snmpAlarmVariable object."

::= { snmpAlarmEntry 5 }

```
\verb"snmpAlarmStartupAlarm" OBJECT-TYPE"
   SYNTAX
             INTEGER {
                  risingAlarm(1),
                  fallingAlarm(2),
                  risingOrFallingAlarm(3)
   MAX-ACCESS read-create
   STATUS
             current
   DESCRIPTION
            "The alarm that may be sent when this entry is
            first set to 'active'. If the first sample after
            this entry becomes active is greater than or equal
            to the risingThreshold and snmpAlarmStartupAlarm
            is equal to 'risingAlarm' or
            'risingOrFallingAlarm', then a single rising alarm
            will be generated. If the first sample after this
            entry becomes active is less than or equal to the
            fallingThreshold and snmpAlarmStartupAlarm is
            equal to 'fallingAlarm' or 'risingOrFallingAlarm',
            then a single falling alarm will be generated.
            Note that a snmpObjectUnavailableAlarm is sent
            upon startup whenever it is applicable,
            independent of the setting of
            snmpAlarmStartupAlarm.
            An attempt to modify this object will fail with an
            'inconsistentValue' error if the associated
            snmpAlarmStatus object would be equal to 'active'
            both before and after the modification attempt."
   DEFVAL { risingOrFallingAlarm }
    ::= { snmpAlarmEntry 6 }
```

snmpAlarmRisingThreshold OBJECT-TYPE

SYNTAX Integer32
MAX-ACCESS read-create
STATUS current
DESCRIPTION

"A threshold for the sampled statistic. When the current sampled value is greater than or equal to this threshold, and the value at the last sampling interval was less than this threshold, a single event will be generated. A single event will also be generated if the first sample after this entry becomes active is greater than or equal to this threshold and the associated snmpAlarmStartupAlarm is equal to 'risingAlarm' or 'risingOrFallingAlarm'.

After a rising event is generated, another such event will not be generated until the sampled value falls below this threshold and reaches the snmpAlarmFallingThreshold.

An attempt to modify this object will fail with an 'inconsistentValue' error if the associated snmpAlarmStatus object would be equal to 'active' both before and after the modification attempt."

::= { snmpAlarmEntry 7 }

 $\verb|snmpAlarmFallingThreshold| OBJECT-TYPE|$ 

SYNTAX Integer32
MAX-ACCESS read-create
STATUS current
DESCRIPTION

"A threshold for the sampled statistic. When the current sampled value is less than or equal to this threshold, and the value at the last sampling interval was greater than this threshold, a single event will be generated. A single event will also be generated if the first sample after this entry becomes active is less than or equal to this threshold and the associated snmpAlarmStartupAlarm is equal to 'fallingAlarm' or 'risingOrFallingAlarm'.

After a falling event is generated, another such event will not be generated until the sampled value rises above this threshold and reaches the snmpAlarmRisingThreshold.

An attempt to modify this object will fail with an 'inconsistentValue' error if the associated snmpAlarmStatus object would be equal to 'active' both before and after the modification attempt."

::= { snmpAlarmEntry 8 }

snmpAlarmRisingEventIndex OBJECT-TYPE
 SYNTAX INTEGER (0..65535)
 MAX-ACCESS read-create
 STATUS current
 DESCRIPTION

"The index of the snmpEventEntry that is used when a rising threshold is crossed. The snmpEventEntry identified by a particular value of this index is the same as identified by the same value of the snmpEventIndex object. If there is no corresponding entry in the snmpEventTable, then no association exists. In particular, if this value is zero, no associated event will be generated, as zero is not a valid snmpEventIndex.

An attempt to modify this object will fail with an 'inconsistentValue' error if the associated snmpAlarmStatus object would be equal to 'active' both before and after the modification attempt."

::= { snmpAlarmEntry 9 }

```
snmpAlarmFallingEventIndex OBJECT-TYPE
    SYNTAX     INTEGER (0..65535)
    MAX-ACCESS read-create
    STATUS     current
    DESCRIPTION
```

"The index of the snmpEventEntry that is used when a falling threshold is crossed. The snmpEventEntry identified by a particular value of this index is the same as identified by the same value of the snmpEventIndex object. If there is no corresponding entry in the snmpEventTable, then no association exists. In particular, if this value is zero, no associated event will be generated, as zero is not a valid snmpEventIndex.

An attempt to modify this object will fail with an 'inconsistentValue' error if the associated snmpAlarmStatus object would be equal to 'active' both before and after the modification attempt."

::= { snmpAlarmEntry 10 }

snmpAlarmUnavailableEventIndex OBJECT-TYPE

SYNTAX INTEGER (0..65535)

MAX-ACCESS read-create STATUS current

DESCRIPTION

"The index of the snmpEventEntry that is used when a variable becomes unavailable. The snmpEventEntry identified by a particular value of this index is the same as identified by the same value of the snmpEventIndex object. If there is no corresponding entry in the snmpEventTable, then no association exists. In particular, if this value is zero, no associated event will be generated, as zero is not a valid snmpEventIndex.

An attempt to modify this object will fail with an 'inconsistentValue' error if the associated snmpAlarmStatus object would be equal to 'active' both before and after the modification attempt."

::= { snmpAlarmEntry 11 }

```
snmpAlarmStatus OBJECT-TYPE
   SYNTAX RowStatus
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
           "The status of this snmpAlarm entry. This object
           may not be set to 'active' unless the following
           columnar objects exist in this row:
           snmpAlarmVariable, snmpAlarmInterval,
           snmpAlarmSampleType, snmpAlarmStartupAlarm,
           snmpAlarmRisingThreshold,
           snmpAlarmFallingThreshold,
           snmpAlarmRisingEventIndex,
           snmpAlarmFallingEventIndex, and
           snmpAlarmUnavailableEventIndex."
    ::= { snmpAlarmEntry 12 }
```

```
-- alarm-related notifications
snmpAlarmNotifications
              OBJECT IDENTIFIER ::= { snmpAlarm 3 }
snmpRisingAlarm NOTIFICATION-TYPE
   OBJECTS { snmpAlarmVariable, snmpAlarmSampleType,
              snmpAlarmValue, snmpAlarmRisingThreshold }
   STATUS current
   DESCRIPTION
            "An event that is generated when an alarm entry
            crosses its rising threshold. The instances of
            those objects contained within the varbind list
            are those of the alarm entry which generated this
            event."
    ::= { snmpAlarmNotifications 1 }
snmpFallingAlarm NOTIFICATION-TYPE
   OBJECTS { snmpAlarmVariable, snmpAlarmSampleType,
              snmpAlarmValue, snmpAlarmFallingThreshold }
   STATUS current
   DESCRIPTION
            "An event that is generated when an alarm entry
            crosses its falling threshold. The instances of
            those objects contained within the varbind list
            are those of the alarm entry which generated this
            event."
    ::= { snmpAlarmNotifications 2 }
snmpObjectUnavailableAlarm NOTIFICATION-TYPE
   OBJECTS { snmpAlarmVariable }
   STATUS current
   DESCRIPTION
            "An event that is generated when a variable
            monitored by an alarm entry becomes unavailable.
            The instance of snmpAlarmVariable contained within
            the varbind list is the one associated with the
            alarm entry which generated this event."
    ::= { snmpAlarmNotifications 3 }
```

```
-- the event group
-- a collection of objects allowing the description and
-- configuration of events from a SNMPv2 entity acting
-- in a dual role.
              OBJECT IDENTIFIER ::= { snmpM2MObjects 2 }
snmpEvent
-- The snmpEvent table defines the set of events generated on
-- a SNMPv2 entity acting in a dual role. Each entry in the
-- snmpEventTable associates an event type with the
-- notification method and associated parameters. Some
-- snmpEvent entries are fired by an associated condition in
-- the snmpAlarmTable. Others are fired on behalf of
-- conditions defined in the NOTIFICATION-TYPE macro.
-- snmpNotificationTable defines notifications that should
-- occur when an associated event is fired.
snmpEventNextIndex OBJECT-TYPE
   SYNTAX INTEGER (0..65535)
   MAX-ACCESS read-only
   STATUS
            current
   DESCRIPTION
            "The index number of the next appropriate
           unassigned entry in the snmpEventTable. The value
            O indicates that no unassigned entries are
           available.
           A management station should create new entries in
           the snmpEventTable using this algorithm: first,
            issue a management protocol retrieval operation to
           determine the value of snmpEventNextIndex; and,
            second, issue a management protocol set operation
            to create an instance of the snmpEventStatus
            object setting its value to 'createAndWait' or
            'createAndGo'."
    ::= { snmpEvent 1 }
```

```
snmpEventTable OBJECT-TYPE
   SYNTAX SEQUENCE OF SnmpEventEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
           "A list of events."
    ::= { snmpEvent 2 }
snmpEventEntry OBJECT-TYPE
   SYNTAX SnmpEventEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
           "A set of parameters that describe an event that
           is generated when certain conditions are met."
           { snmpEventIndex }
    ::= { snmpEventTable 1 }
SnmpEventEntry ::= SEQUENCE {
   snmpEventID
                         OBJECT IDENTIFIER,
   snmpEventDescription DisplayString,
snmpEventEvents Counter32,
   snmpEventLastTimeSent TimeStamp,
   snmpEventStatus
                   RowStatus
}
snmpEventIndex OBJECT-TYPE
   SYNTAX INTEGER (1..65535)
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
           "An index that uniquely identifies an entry in the
           snmpEvent table. Each such entry defines an event
           generated when the appropriate conditions occur."
    ::= { snmpEventEntry 1 }
```

```
snmpEventID OBJECT-TYPE
   SYNTAX OBJECT IDENTIFIER
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
           "The authoritative identification of the event
           type generated by this entry. This variable
           occurs as the second varbind of an InformRequest-
           PDU. If this OBJECT IDENTIFIER maps to a
           NOTIFICATION-TYPE the sender will place the
           objects listed in the NOTIFICATION-TYPE in the
           varbind list."
    ::= { snmpEventEntry 2 }
snmpEventDescription OBJECT-TYPE
   SYNTAX DisplayString (SIZE (0..127))
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
           "A comment describing this snmpEvent entry."
    ::= { snmpEventEntry 3 }
snmpEventEvents OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS
           current
   DESCRIPTION
           "The number of events caused by event generators
           associated with this snmpEvent entry."
    ::= { snmpEventEntry 4 }
```

```
snmpEventLastTimeSent OBJECT-TYPE
   SYNTAX TimeStamp
   MAX-ACCESS read-only
   STATUS
           current
   DESCRIPTION
           "The value of sysUpTime at the time this snmpEvent
           entry last generated an event. If this entry has
           not generated any events, this value will be
           zero."
   DEFVAL { 0 }
    ::= { snmpEventEntry 5 }
snmpEventStatus OBJECT-TYPE
   SYNTAX RowStatus
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
           "The status of this snmpEvent entry. This object
           may not be set to 'active' unless the following
           columnar objects exist in this row: snmpEventID,
           snmpEventDescription, snmpEventEvents, and
           snmpEventLastTimeSent.
           Setting an instance of this object to the value
            'destroy' has the effect of invalidating any/all
           entries in the snmpEventTable, and the
           snmpEventNotifyTable which reference the
           corresponding snmpEventEntry."
    ::= { snmpEventEntry 6 }
```

```
snmpEventNotifyMinInterval OBJECT-TYPE
   SYNTAX Integer32
   UNITS
              "seconds"
   MAX-ACCESS read-only
   STATUS
           current
   DESCRIPTION
            "The minimum interval that the SNMPv2 entity
           acting in a dual role will wait before
           retransmitting an InformRequest-PDU. This object
            specifies the minimal value supported by the
           SNMPv2 entity acting in a dual role, based on
           resource or implementation constraints.
           For a particular entry in the
            snmpEventNotifyTable, if the associated
            snmpEventNotifyIntervalRequested variable is
           greater than this object, the
            snmpEventNotifyIntervalRequested value shall be
           used as the minimum interval for retransmissions
            of InformRequest-PDUs sent on behalf of that
           entry."
    ::= { snmpEvent 3 }
snmpEventNotifyMaxRetransmissions OBJECT-TYPE
   SYNTAX
             Integer32
   MAX-ACCESS read-only
   STATUS
             current
   DESCRIPTION
            "The maximum number of time that the SNMPv2 entity
           acting in a dual role will retransmit an
           InformRequest-PDU. This object specifies the
           maximal value supported by the SNMPv2 entity
            acting in a dual role, based on resource or
            implementation constraints.
           For a particular entry in the
            snmpEventNotifyTable, if the associated
            snmpEventNotifyRetransmissionsRequested variable
            is less than this object, the
            snmpEventNotifyRetransmissionsRequested value
            shall be used as the retransmission count for
            InformRequest-PDUs sent on behalf of that entry."
    ::= { snmpEvent 4 }
-- The snmpEventNotifyTable is used to configure the
```

```
-- destination and type of notifications sent by a SNMPv2
-- entity acting in a manager role when a particular event
-- is triggered.
snmpEventNotifyTable OBJECT-TYPE
             SEQUENCE OF SnmpEventNotifyEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
           "A list of protocol configuration entries for
            event notifications from this entity."
    ::= { snmpEvent 5 }
snmpEventNotifyEntry OBJECT-TYPE
   SYNTAX SnmpEventNotifyEntry
   MAX-ACCESS not-accessible
   STATUS
              current
   DESCRIPTION
           "A set of parameters that describe the type and
           destination of InformRequest-PDUs sent for a
           particular event. The snmpEventIndex in this
           entry's INDEX clause identifies the snmpEventEntry
           which, when triggered, will generate a
           notification as configured in this entry. The
           contextIdentity in this entry's INDEX clause
            identifies the context to which a notification
           will be sent."
    INDEX
              { snmpEventIndex, contextIdentity }
    ::= { snmpEventNotifyTable 1 }
SnmpEventNotifyEntry ::= SEQUENCE {
   snmpEventNotifyIntervalRequested
                                            Integer32,
    snmpEventNotifyRetransmissionsRequested Integer32,
    snmpEventNotifyLifetime
                                            Integer32,
   snmpEventNotifyStatus
                                            RowStatus
}
```

```
\verb|snmpEventNotifyIntervalRequested OBJECT-TYPE|\\
   SYNTAX Integer32
   UNITS
              "seconds"
    MAX-ACCESS read-create
    STATUS
             current
    DESCRIPTION
            "The requested interval for retransmission of
            Inform PDUs generated on the behalf of this entry.
            This variable will be the actual interval used
            unless the snmpEventNotifyMinInterval is greater
            than this object, in which case the interval shall
            be equal to snmpEventNotifyMinInterval."
    DEFVAL { 30 }
    ::= { snmpEventNotifyEntry 1 }
snmpEventNotifyRetransmissionsRequested OBJECT-TYPE
    SYNTAX Integer32
    MAX-ACCESS read-create
    STATUS
             current
    DESCRIPTION
            "The requested number of retransmissions of an
            {\tt InformRequest-PDU\ generated\ on\ behalf\ of\ this}
            entry.
            This variable will be the actual number of
            retransmissions used unless the
            snmpEventNotifyMaxRetransmissions is less than
            this object, in which case the retransmission
            count shall be equal to
            snmpEventNotifyMaxRetransmissions."
    DEFVAL { 5 }
    ::= { snmpEventNotifyEntry 2 }
```

```
snmpEventNotifyLifetime OBJECT-TYPE
   SYNTAX Integer32
   UNITS
             "seconds"
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
           "The number of seconds this entry shall live until
           the corresponding instance of
           snmpEventNotifyStatus is set to 'destroy'. This
           value shall count down to zero, at which time the
           corresponding instance of snmpEventNotifyStatus
           will be set to 'destroy'. Any management station
           that is using this entry must periodically refresh
           this value to ensure the continued delivery of
           events."
   DEFVAL { 86400 }
    ::= { snmpEventNotifyEntry 3 }
snmpEventNotifyStatus OBJECT-TYPE
   SYNTAX RowStatus
   MAX-ACCESS read-create
   STATUS
           current.
   DESCRIPTION
            "The state of this snmpEventNotifyEntry. This
           object may not be set to 'active' unless the
           following columnar objects exist in this row:
           snmpEventNotifyIntervalRequested,
           snmpEventNotifyRetransmissionsRequested, and
           snmpEventNotifyLifetime."
    ::= { snmpEventNotifyEntry 4 }
```

```
-- conformance information
snmpM2MConformance
               OBJECT IDENTIFIER ::= { snmpM2M 2 }
snmpM2MCompliances
               OBJECT IDENTIFIER ::= { snmpM2MConformance 1 }
snmpM2MGroups OBJECT IDENTIFIER ::= { snmpM2MConformance 2 }
-- compliance statements
snmpM2MCompliance MODULE-COMPLIANCE
   STATUS current
   DESCRIPTION
            "The compliance statement for SNMPv2 entities
           which implement the Manager-to-Manager MIB."
   MODULE -- this module
       MANDATORY-GROUPS { snmpAlarmGroup, snmpEventGroup }
    ::= { snmpM2MCompliances 1 }
-- units of conformance
snmpAlarmGroup OBJECT-GROUP
   OBJECTS { snmpAlarmNextIndex,
              snmpAlarmVariable, snmpAlarmInterval,
              snmpAlarmSampleType, snmpAlarmValue,
              snmpAlarmStartupAlarm, snmpAlarmRisingThreshold,
              snmpAlarmFallingThreshold,
              snmpAlarmRisingEventIndex,
              snmpAlarmFallingEventIndex,
              snmpAlarmUnavailableEventIndex,
             snmpAlarmStatus }
   STATUS current
   DESCRIPTION
            "A collection of objects allowing the description
            and configuration of threshold alarms from a
            SNMPv2 entity acting in a dual role."
    ::= { snmpM2MGroups 1 }
```

END

## 4. Acknowledgements

The comments of the SNMP version 2 working group are gratefully acknowledged:

Beth Adams, Network Management Forum Steve Alexander, INTERACTIVE Systems Corporation David Arneson, Cabletron Systems Toshiya Asaba Fred Baker, ACC Jim Barnes, Xylogics, Inc. Brian Bataille Andy Bierman, SynOptics Communications, Inc. Uri Blumenthal, IBM Corporation Fred Bohle, Interlink Jack Brown Theodore Brunner, Bellcore Stephen F. Bush, GE Information Services Jeffrey D. Case, University of Tennessee, Knoxville John Chang, IBM Corporation Szusin Chen, Sun Microsystems Robert Ching Chris Chiotasso, Ungermann-Bass Bobby A. Clay, NASA/Boeing John Cooke, Chipcom Tracy Cox, Bellcore Juan Cruz, Datability, Inc. David Cullerot, Cabletron Systems Cathy Cunningham, Microcom James R. (Chuck) Davin, Bellcore Michael Davis, Clearpoint Mike Davison, FiberCom Cynthia DellaTorre, MITRE Taso N. Devetzis, Bellcore Manual Diaz, DAVID Systems, Inc. Jon Dreyer, Sun Microsystems David Engel, Optical Data Systems Mike Erlinger, Lexcel Roger Fajman, NIH Daniel Fauvarque, Sun Microsystems Karen Frisa, CMU Shari Galitzer, MITRE Shawn Gallagher, Digital Equipment Corporation Richard Graveman, Bellcore Maria Greene, Xyplex, Inc.

```
Michel Guittet, Apple
Robert Gutierrez, NASA
Bill Hagerty, Cabletron Systems
Gary W. Haney, Martin Marietta Energy Systems
Patrick Hanil, Nokia Telecommunications
Matt Hecht, SNMP Research, Inc.
Edward A. Heiner, Jr., Synernetics Inc.
Susan E. Hicks, Martin Marietta Energy Systems
Geral Holzhauer, Apple
John Hopprich, DAVID Systems, Inc.
Jeff Hughes, Hewlett-Packard
Robin Iddon, Axon Networks, Inc.
David Itusak
Kevin M. Jackson, Concord Communications, Inc.
Ole J. Jacobsen, Interop Company
Ronald Jacoby, Silicon Graphics, Inc.
Satish Joshi, SynOptics Communications, Inc.
Frank Kastenholz, FTP Software
Mark Kepke, Hewlett-Packard
Ken Key, SNMP Research, Inc.
Zbiginew Kielczewski, Eicon
Jongyeoi Kim
Andrew Knutsen, The Santa Cruz Operation
Michael L. Kornegay, VisiSoft
Deirdre C. Kostik, Bellcore
Cheryl Krupczak, Georgia Tech
Mark S. Lewis, Telebit
David Lin
David Lindemulder, AT&T/NCR
Ben Lisowski, Sprint
David Liu, Bell-Northern Research
John Lunny, The Wollongong Group
Robert C. Lushbaugh Martin, Marietta Energy Systems
Michael Luufer, BBN
Carl Madison, Star-Tek, Inc.
Keith McCloghrie, Hughes LAN Systems
Evan McGinnis, 3Com Corporation
Bill McKenzie, IBM Corporation
Donna McMaster, SynOptics Communications, Inc.
```

Dave Minnich, FiberCom

Doug Miller, Telebit

Mohammad Mirhakkak, MITRE

John Medicke, IBM Corporation

Rohit Mital, Protools

George Mouradian, AT&T Bell Labs

Patrick Mullaney, Cabletron Systems Dan Myers, 3Com Corporation Rina Nathaniel, Rad Network Devices Ltd. Hien V. Nguyen, Sprint Mo Nikain Tom Nisbet William B. Norton, MERIT Steve Onishi, Wellfleet Communications, Inc. David T. Perkins, SynOptics Communications, Inc. Carl Powell, BBN Ilan Raab, SynOptics Communications, Inc. Richard Ramons, AT&T Venkat D. Rangan, Metric Network Systems, Inc. Louise Reingold, Sprint Sam Roberts, Farallon Computing, Inc. Kary Robertson, Concord Communications, Inc. Dan Romascanu, Lannet Data Communications Ltd. Marshall T. Rose, Dover Beach Consulting, Inc. Shawn A. Routhier, Epilogue Technology Corporation Chris Rozman Asaf Rubissa, Fibronics Jon Saperia, Digital Equipment Corporation Michael Sapich Mike Scanlon, Interlan Sam Schaen, MITRE John Seligson, Ultra Network Technologies Paul A. Serice, Corporation for Open Systems Chris Shaw, Banyan Systems Timon Sloane Robert Snyder, Cisco Systems Joo Young Song Roy Spitier, Sprint Einar Stefferud, Network Management Associates John Stephens, Cayman Systems, Inc. Robert L. Stewart, Xyplex, Inc. (chair) Kaj Tesink, Bellcore Dean Throop, Data General Ahmet Tuncay, France Telecom-CNET Maurice Turcotte, Racal Datacom Warren Vik, INTERACTIVE Systems Corporation Yannis Viniotis Steven L. Waldbusser, Carnegie Mellon Universitty Timothy M. Walden, ACC Alice Wang, Sun Microsystems

James Watt, Newbridge

Luanne Waul, Timeplex
Donald E. Westlake III, Digital Equipment Corporation
Gerry White
Bert Wijnen, IBM Corporation
Peter Wilson, 3Com Corporation
Steven Wong, Digital Equipment Corporation
Randy Worzella, IBM Corporation
Daniel Woycke, MITRE
Honda Wu
Jeff Yarnell, Protools
Chris Young, Cabletron
Kiho Yum, 3Com Corporation

#### 5. References

- [1] Information processing systems Open Systems
  Interconnection Specification of Abstract Syntax
  Notation One (ASN.1), International Organization for
  Standardization. International Standard 8824, (December, 1987).
- [2] Case, J., McCloghrie, K., Rose, M., and Waldbusser, S., "Structure of Management Information for version 2 of the Simple Network Management Protocol (SNMPv2)", RFC 1442, SNMP Research, Inc., Hughes LAN Systems, Dover Beach Consulting, Inc., Carnegie Mellon University, April 1993.
- [3] Case, J., McCloghrie, K., Rose, M., and Waldbusser, S., "Protocol Operations for version 2 of the Simple Network Management Protocol (SNMPv2)", RFC 1448, SNMP Research, Inc., Hughes LAN Systems, Dover Beach Consulting, Inc., Carnegie Mellon University, April 1993.
- [4] Galvin, J., and McCloghrie, K., "Administrative Model for version 2 of the Simple Network Management Protocol (SNMPv2)", RFC 1445, Trusted Information Systems, Hughes LAN Systems, April 1993.
- [5] McCloghrie, K., and Galvin, J., "Party MIB for version 2 of the Simple Network Management Protocol (SNMPv2)", RFC 1447, Hughes LAN Systems, Trusted Information Systems, April 1993.

# 6. Security Considerations

Security issues are not discussed in this memo.

# 7. Authors' Addresses

Jeffrey D. Case SNMP Research, Inc. 3001 Kimberlin Heights Rd. Knoxville, TN 37920-9716

Phone: +1 615 573 1434 Email: case@snmp.com

Keith McCloghrie Hughes LAN Systems 1225 Charleston Road Mountain View, CA 94043 US

Phone: +1 415 966 7934 Email: kzm@hls.com

Marshall T. Rose Dover Beach Consulting, Inc. 420 Whisman Court Mountain View, CA 94043-2186

Phone: +1 415 968 1052

Email: mrose@dbc.mtview.ca.us

Steven Waldbusser Carnegie Mellon University 4910 Forbes Ave Pittsburgh, PA 15213 US

Phone: +1 412 268 6628 Email: waldbusser@cmu.edu