Network Working Group Request for Comments: 4008 Category: Standards Track R. Rohit
Mascon Global Limited
P. Srisuresh
Caymas Systems, Inc.
R. Raghunarayan
N. Pai
Cisco Systems, Inc.
C. Wang
Bank One Corp
March 2005

Definitions of Managed Objects for Network Address Translators (NAT)

Status of This Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

Copyright Notice

Copyright (C) The Internet Society (2005).

Abstract

This memo defines a portion of the Management Information Base (MIB) for devices implementing Network Address Translator (NAT) function. This MIB module may be used for configuration as well as monitoring of a device capable of NAT function.

Rohit, et al. Standards Track [Page 1]

Table of Contents

Intro	duction	2
The In	nternet-Standard Management Framework	2
Termin	nology	3
Overv	iew	4
4.1.	natInterfaceTable	4
4.2.	natAddrMapTable	5
4.3.	Default Timeouts, Protocol Table, and Other Scalars	6
4.4.	natAddrBindTable and natAddrPortBindTable	6
4.5.	natSessionTable	6
4.6.	RFC 3489 NAPT Variations, NAT Session and Bind Tables	7
4.7.	Notifications	7
4.8.	Relation Among Tables	8
4.9.	Configuration via the MIB	8
4.10.	Relationship to Interface MIB	9
Defin	itions	9
		59
Security Considerations		59
Refere	ences	60
nors' A	Addresses	62
L Соруз	right Statement	64
	The Intermit Overval 4.1. 4.2. 4.3. 4.4. 4.5. 4.6. 4.7. 4.8. 4.9. 4.10. Define Acknow Securial References 2.2.	4.2. natAddrMapTable

1. Introduction

This memo defines a portion of the Management Information Base (MIB) for devices implementing NAT function. This MIB module may be used for configuration and monitoring of a device capable of NAT function. NAT types and their characteristics are defined in [RFC2663]. Traditional NAT function, in particular is defined in [RFC3022]. This MIB does not address the firewall functions and must not be used for configuring or monitoring these. Section 2 provides references to the SNMP management framework, which was used as the basis for the MIB module definition. Section 3 describes the terms used throughout the document. Section 4 provides an overview of the key objects, their inter-relationship, and how the MIB module may be used to configure and monitor a NAT device. Lastly, section 5 has the complete NAT MIB definition.

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in [RFC2119].

2. The Internet-Standard Management Framework

For a detailed overview of the documents that describe the current Internet-Standard Management Framework, please refer to section 7 of RFC 3410 [RFC3410].

Rohit, et al. Standards Track [Page 2]

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. MIB objects are generally accessed through the Simple Network Management Protocol (SNMP).

Objects in the MIB are defined using the mechanisms defined in the Structure of Management Information (SMI). This memo specifies a MIB module that is compliant to the SMIv2, which is described in STD 58, RFC 2578 [RFC2578], STD 58, RFC 2579 [RFC2579] and STD 58, RFC 2580 [RFC2580].

3. Terminology

Definitions for a majority of the terms used throughout the document may be found in RFC 2663 [RFC2663]. Additional terms that further classify NAPT implementations are defined in RFC 3489 [RFC3489]. Listed below are terms used in this document.

Address realm - An address realm is a realm of unique network addresses that are routable within the realm. For example, an enterprise address realm could be constituted of private IP addresses in the ranges specified in RFC 1918 [RFC1918], which are routable within the enterprise, but not across the Internet. A public realm is constituted of globally unique network addresses.

Symmetric NAT - Symmetric NAT, as defined in RFC 3489 [RFC3489], is a variation of Network Address Port Translator (NAPT). Symmetric NAT does not use port bind for translation across all sessions originating from the same private host. Instead, it assigns a new public port to each new session, irrespective of whether the new session used the same private end-point as before.

Bind or Binding - Several variations of the term 'Bind' (or 'Binding') are used throughout the document. Address Bind (or Address Binding) is a tuple of (Private IP address, Public IP Address) used for translating an IP address end-point in IP packets. Port Bind (or, Port Binding, or Address Port Bind, or Address Port Binding) is a tuple of (transport protocol, Private IP address, Private port, Public IP Address, Public port) used for translating a port end-point tuple of (transport protocol, IP address, port). Bind is used to refer to either Address Bind or Port Bind. Bind Mode identifies whether a bind is Address Bind or Port Bind.

NAT Session - A NAT session is an association between a session as seen in the private realm and a session as seen in the public realm, by virtue of NAT translation. If a session in the private realm were to be represented as (PrivateSrcAddr, PrivateDstAddr, TransportProtocol, PrivateSrcPort, PrivateDstPort) and the same session in the public realm were to be represented as (PublicSrcAddr,

Rohit, et al. Standards Track [Page 3]

PublicDstAddr, TransportProtocol, PublicSrcPort, PublicDstPort), the NAT session will provide the translation glue between the two session representations. NAT sessions in the document are restricted to sessions based on TCP and UDP only. In the future, NAT sessions may be extended to be based on other transport protocols such as SCTP, UDP-lite and DCCP.

The terms 'local' and 'private' are used interchangeably throughout the document when referring to private networks, IP addresses, and ports. Likewise, the terms 'global' and 'public' are used interchangeably when referring to public networks, IP addresses, and ports.

4. Overview

NAT MIB is configurable on a per-interface basis and depends in several parts on the IF-MIB [RFC2863].

NAT MIB requires that an interface for which NAT is configured be connected to either a private or a public realm. The realm association of the interface plays an important role in the definition of address maps for the interface. An address map entry identifies the orientation of the session (inbound or outbound to the interface) for which the entry may be used for NAT translation. The address map entry also identifies the end-point of the session that must be subject to translation. An SNMP Textual-Convention 'NatTranslationEntity' is defined to capture this important characteristic that combines session orientation and applicable session endpoint for translation.

An address map may consist of static or dynamic entries. NAT creates static binds from a static address map entry. Each static bind has a direct one-to-one relationship with a static address map entry. NAT creates dynamic binds from a dynamic address map entry upon seeing the first packet of a new session.

The following subsections define the key objects used in NAT MIB, their inter-relationship, and how to configure a NAT device using the MIB module.

4.1. natInterfaceTable

natInterfaceTable is defined in the MIB module to configure interface specific realm type and the NAT services enabled for the interface. natInterfaceTable is indexed by ifIndex and also includes interface specific NAT statistics.

Rohit, et al. Standards Track [Page 4]

The first step for an operator in configuring a NAT device is determining the interface over which NAT service is to be configured. When NAT service is operational, translated packets traverse the NAT device by ingressing on a private interface and egressing on a public interface or vice versa. An operator may configure the NAT service on either the public interface or the private interface in the traversal path.

As the next step, the operator must identify the NAT service(s) desired for the interface. The operator may configure one or more NAT services on the same interface. The MIB module identifies four types of NAT services: Basic NAT, NAPT, twice NAT and bidirectional NAT. These are NAT varieties as defined in RFC 2663 [RFC2663]. Note that RFC 3489 [RFC3489] further classifies NAPT implementations based on the behavior exhibited by the NAPT devices from different vendors. However, the MIB module does not explicitly distinguish between the NAPT implementations. NAPT implementations may be distinguished between one another by monitoring the BIND and NAT Session objects generated by the NAT device as described in section 4.6.

4.2. natAddrMapTable

natAddrMapTable is defined in the MIB module to configure address maps on a per-interface basis. natAddrMapTable is indexed by the tuple of (ifIndex, natAddrMapIndex). The same table is also used to collect Statistics for the address map entries. Address maps are key to NAT configuration. An operator may configure one or more address map entries per interface. NAT looks up address map entries in the order in which they are defined to determine the translation function at the start of each new session traversing the interface. An address map may consist of static or dynamic entries. A static address map entry has a direct one-to-one relationship with binds. NAT will dynamically create binds from a dynamic address map entry.

The operator must be careful in selecting address map entries for an interface based on the interface realm-type and the type of NAT service desired. The operator can be amiss in the selection of address map entries when not paying attention to the associated interface characteristics defined in natInterfaceTable (described in section 4.1). For example, say the operator wishes to configure a NAPT map entry on an interface of a NAT device. If the operator chooses to configure the NAPT map entry on a public interface (i.e., interface realm-type is public), the operator should set the TranslationEntity of the NAPT address map entry to be outboundSrcEndPoint. On the other hand, if the operator chooses to configure the NAPT map entry on a private interface (i.e., interface realm-type is private), the operator should set the TranslationEntity of the NAPT address map entry to be InboundSrcEndPoint.

Rohit, et al. Standards Track [Page 5]

4.3. Default Timeouts, Protocol Table, and Other Scalars

DefTimeouts is defined in the MIB module to configure idle Bind timeout and IP protocol specific idle NAT session timeouts. The timeouts defined are global to the system and are not interface specific.

Protocol specific statistics are maintained in natProtocolTable, which is indexed by the protocol type.

The scalars natAddrBindNumberOfEntries and natAddrPortBindNumberOfEntries hold the number of entries that currently exist in the Address Bind and the Address Port Bind tables, respectively.

The generation of natPacketDiscard notifications can be configured by using the natNotifThrottlingInterval scalar MIB object.

4.4. natAddrBindTable and natAddrPortBindTable

Two Bind tables, natAddrBindTable and natAddrPortBindTable, are defined to hold the bind entries. Entries are derived from the address map table and are not configurable. natAddrBindTable contains Address Binds, and natAddrPortBindTable contains Address Port Binds. natAddrBindTable is indexed by the tuple of (ifIndex, LocalAddrType, LocalAddr). natAddrPortBindTable is indexed by the tuple of (ifIndex, LocalAddrType, LocalAddr, LocalPort, Protocol). These tables also maintain bind specific statistics. A Symmetric NAT will have no entries in the Bind tables.

4.5. natSessionTable

natSessionTable is defined to hold NAT session entries. NAT session entries are derived from NAT Binds (except in the case of Symmetric NAT) and are not configurable.

The NAT session provides the necessary translation glue between two session representations of the same end-to-end session; that is, a session as seen in the private realm and in the public realm. Session orientation (inbound or outbound) is determined from the orientation of the first packet traversing the NAT interface. Address map entries and bind entries on the interface determine whether a session is subject to NAT translation. One or both endpoints of a session may be subject to translation.

With the exception of symmetric NAT, all other NAT functions use end-point specific bind to perform individual end-point translations. Multiple NAT sessions would use the same bind as long as they share

Rohit, et al. Standards Track [Page 6]

the same endpoint. Symmetric NAT does not retain a consistent port bind across multiple sessions using the same endpoint. For this reason, the bind identifier for a NAT session in symmetric NAT is set to zero. natSessionTable is indexed by the tuple of (ifIndex, natSessionIndex). Statistics for NAT sessions are also maintained in the same table.

4.6. RFC 3489 NAPT Variations, NAT Session and Bind Tables

[RFC3489] defines four variations of NAPT - Full Cone, Restricted Cone, Port Restricted Cone, and Symmetric NAT. These can be differentiated in the NAT MIB based on different values for the objects in the session and the bind tables, as indicated below.

In a Port Restricted Cone NAT, NAT Session objects will contain a non-zero PrivateSrcEPBindId object. Further, all address and port objects within a NAT session will have non-zero values (i.e., no wildcard matches).

An Address Restricted Cone NAT may have been implemented in the same way as a Port Restricted Cone NAT, except that the UDP NAT Sessions may use ANY match on PrivateDstPort and PublicDstPort objects; i.e., PrivateDstPort and PublicDstPort objects within a NAT session may be set to zero.

A Full Cone NAT may have also been implemented in the same way as a Port Restricted Cone NAT, except that the UDP NAT Sessions may use ANY match on PrivateDstAddr, PrivateDstPort, PublicDstAddr, and PublicDstPort objects. Within a NAT Session, all four of these objects may be set to zero. Alternately, all address and port objects within a NAT Session may have non-zero values, yet the TranslationEntity of the PrivateSrcEPBindId for the NAT Sessions may be set bi-directionally, i.e., as a bit mask of (outboundSrcEndPoint and inboundDstEndPoint) or (inboundSrcEndPoint and outboundDstEndPoint), depending on the interface realm type. Lastly, a Symmetric NAT does not maintain Port Bindings. As such, the NAT Session objects will have the PrivateSrcEPBindId set to zero.


4.7. Notifications

natPacketDiscard notifies the end user/manager of packets being discarded due to lack of address mappings.

Rohit, et al. Standards Track [Page 7]

4.8. Relation Among Tables

The association between the various NAT tables can be represented as follows:



All NAT functions, with the exception of Symmetric NAT, use Bind(s) to provide the glue necessary for a NAT Session. natSessionPrivateSrcEPBindId and natSessionPrivateDstEPBindId objects represent the endpoint Binds used by NAT Sessions.

4.9. Configuration via the MIB

Sections 4.1 and 4.2 and part of section 4.3 refer to objects that are configurable on a NAT device. NAT derives Address Bind and Address Port Bind entries from the Address Map table. Hence, an Address Bind or an Address Port Bind entry must not exist without an associated entry in the Address Map table.

Further, NAT derives NAT session entries from NAT Binds, except in the case of symmetric NAT, which derives translation parameters for a NAT session directly from an address map entry. Hence, with the exception of Symmetric NAT, a NAT session entry must not exist in the NAT Session table without a corresponding bind.

Rohit, et al. Standards Track [Page 8]

A Management station may use the following steps to configure entries in the NAT-MIB:

- Create an entry in the natInterfaceTable specifying the value of ifIndex as the interface index of the interface on which NAT is being configured. Specify appropriate values, as applicable, for the other objects (e.g., natInterfaceRealm, natInterfaceServiceType) in the table (refer to Section 4.1).
- Create one or more address map entries sequentially in reduced order of priority in the natAddrMapTable, specifying the value of ifIndex to be the same for all entries. The ifIndex specified would be the same as that specified for natInterfaceTable (refer to Section 4.2).
- Configure the maximum permitted idle time duration for BINDs and TCP, UDP, and ICMP protocol sessions by setting the relevant scalars in natDefTimeouts object (refer to Section 4.3).

4.10. Relationship to Interface MIB

The natInterfaceTable specifies the NAT configuration attributes on each interface. The concept of "interface" is as defined by InterfaceIndex/ifIndex of the IETF Interfaces MIB [RFC2863].

5. Definitions

```
This MIB module IMPORTs objects from RFCs 2578 [RFC2578], 2579 [RFC2579], 2580 [RFC2580], 2863 [RFC2863], 3411 [RFC3411], and 4001 [RFC4001]. It also refers to information in RFCs 792 [RFC792], 2463 [RFC2463], and 3413 [RFC3413].
```

NAT-MIB DEFINITIONS ::= BEGIN

IMPORTS

```
MODULE-IDENTITY,
OBJECT-TYPE,
Integer32,
Unsigned32,
Gauge32,
Counter64,
TimeTicks,
mib-2,
NOTIFICATION-TYPE
FROM SNMPv2-SMI
TEXTUAL-CONVENTION,
StorageType,
RowStatus
```

Rohit, et al. Standards Track [Page 9]

FROM SNMPv2-TC

MODULE-COMPLIANCE,

NOTIFICATION-GROUP,

OBJECT-GROUP

FROM SNMPv2-CONF

ifIndex,

ifCounterDiscontinuityGroup

FROM IF-MIB

SnmpAdminString

FROM SNMP-FRAMEWORK-MIB

InetAddressType,

InetAddress,

InetPortNumber

FROM INET-ADDRESS-MIB;

natMIB MODULE-IDENTITY

LAST-UPDATED "200503210000Z" ORGANIZATION "IETF Transport Area" CONTACT-INFO

Rohit

Mascon Global Limited #59/2 100 ft Ring Road Banashankari II Stage Bangalore 560 070

India

Phone: +91 80 2679 6227 Email: rrohit74@hotmail.com

P. Srisuresh

Caymas Systems, Inc. 1179-A North McDowell Blvd. Petaluma, CA 94954

Tel: (707) 283-5063

Email: srisuresh@yahoo.com

Rajiv Raghunarayan Cisco Systems Inc. 170 West Tasman Drive San Jose, CA 95134

Phone: +1 408 853 9612 Email: raraghun@cisco.com

Nalinaksh Pai Cisco Systems, Inc. Prestige Waterford No. 9, Brunton Road Bangalore - 560 025

Rohit, et al. Standards Track [Page 10]

```
India
               Phone: +91 80 532 1300
               Email: npai@cisco.com
               Cliff Wang
               Information Security
               Bank One Corp
               1111 Polaris Pkwy
               Columbus, OH 43240
              Phone: +1 614 213 6117
              Email: cliffwang2000@yahoo.com
     DESCRIPTION
             "This MIB module defines the generic managed objects
             for NAT.
              Copyright (C) The Internet Society (2005). This version
              of this MIB module is part of RFC 4008; see the RFC
              itself for full legal notices."
              "200503210000Z" -- 21th March 2005
     REVISION
     DESCRIPTION
             "Initial version, published as RFC 4008."
     ::= { mib-2 123 }
natMIBObjects OBJECT IDENTIFIER ::= { natMIB 1 }
NatProtocolType ::= TEXTUAL-CONVENTION
              current
       STATUS
       DESCRIPTION
               "A list of protocols that support the network
               address translation. Inclusion of the values is
               not intended to imply that those protocols
                need to be supported. Any change in this
                TEXTUAL-CONVENTION should also be reflected in
                the definition of NatProtocolMap, which is a
               BITS representation of this."
       SYNTAX INTEGER {
                    none (1), -- not specified
                    other (2), -- none of the following
                    icmp (3),
                    udp (4),
                    tcp (5)
                  }
NatProtocolMap ::= TEXTUAL-CONVENTION
       STATUS current
       DESCRIPTION
               "A bitmap of protocol identifiers that support
```

Rohit, et al. Standards Track [Page 11]

```
the network address translation. Any change
                in this TEXTUAL-CONVENTION should also be
                reflected in the definition of NatProtocolType."
       SYNTAX
               BITS {
                  other (0),
                 icmp (1),
                  udp (2),
                  tcp (3)
NatAddrMapId ::= TEXTUAL-CONVENTION
       DISPLAY-HINT "d"
       STATUS current
       DESCRIPTION
               "A unique id that is assigned to each address map
                by a NAT enabled device."
       SYNTAX
               Unsigned32 (1..4294967295)
NatBindIdOrZero ::= TEXTUAL-CONVENTION
       DISPLAY-HINT "d"
       STATUS current
       DESCRIPTION
               "A unique id that is assigned to each bind by
                a NAT enabled device. The bind id will be zero
                in the case of a Symmetric NAT."
       SYNTAX Unsigned32 (0..4294967295)
NatBindId ::= TEXTUAL-CONVENTION
       DISPLAY-HINT "d"
       STATUS current
       DESCRIPTION
               "A unique id that is assigned to each bind by
                a NAT enabled device."
       SYNTAX
               Unsigned32 (1..4294967295)
NatSessionId ::= TEXTUAL-CONVENTION
      DISPLAY-HINT "d"
       STATUS current
       DESCRIPTION
               "A unique id that is assigned to each session by
                a NAT enabled device."
              Unsigned32 (1..4294967295)
NatBindMode ::= TEXTUAL-CONVENTION
       STATUS current
       DESCRIPTION
               "An indication of whether the bind is
               an address bind or an address port bind."
```

Rohit, et al. Standards Track [Page 12]

```
SYNTAX INTEGER {
                addressBind (1),
                    addressPortBind (2)
                }
NatAssociationType ::= TEXTUAL-CONVENTION
      STATUS current
      DESCRIPTION
               "An indication of whether the association is
               static or dynamic."
       SYNTAX INTEGER {
                    static (1),
                    dynamic (2)
               }
NatTranslationEntity ::= TEXTUAL-CONVENTION
      STATUS
                  current
      DESCRIPTION
              "An indication of a) the direction of a session for
               which an address map entry, address bind or port
               bind is applicable, and b) the entity (source or
               destination) within the session that is subject to
               translation."
       SYNTAX BITS {
                 inboundSrcEndPoint (0),
                 outboundDstEndPoint(1),
                 inboundDstEndPoint (2),
                 outboundSrcEndPoint(3)
                }
-- Default Values for the Bind and NAT Protocol Timers
natDefTimeouts OBJECT IDENTIFIER ::= { natMIBObjects 1 }
natNotifCtrl OBJECT IDENTIFIER ::= { natMIBObjects 2 }
-- Address Bind and Port Bind related NAT configuration
natBindDefIdleTimeout OBJECT-TYPE
   SYNTAX Unsigned32 (0..4294967295)
   UNITS
              "seconds"
   MAX-ACCESS read-write
   STATUS
           current
   DESCRIPTION
```

Rohit, et al. Standards Track [Page 13]

```
"The default Bind (Address Bind or Port Bind) idle
            timeout parameter.
             If the agent is capable of storing non-volatile
             configuration, then the value of this object must be
             restored after a re-initialization of the management
             system."
    DEFVAL { 0 }
    ::= { natDefTimeouts 1 }
-- UDP related NAT configuration
natUdpDefIdleTimeout OBJECT-TYPE
    SYNTAX Unsigned32 (1..4294967295)
    UNITS
              "seconds"
    MAX-ACCESS read-write
    STATUS
           current
    DESCRIPTION
            "The default UDP idle timeout parameter.
             If the agent is capable of storing non-volatile
             configuration, then the value of this object must be
             restored after a re-initialization of the management
            system."
    DEFVAL { 300 }
    ::= { natDefTimeouts 2 }
-- ICMP related NAT configuration
natIcmpDefIdleTimeout OBJECT-TYPE
    SYNTAX Unsigned32 (1..4294967295)
    UNITS
              "seconds"
    MAX-ACCESS read-write
    STATUS
            current
    DESCRIPTION
            "The default ICMP idle timeout parameter.
             If the agent is capable of storing non-volatile
             configuration, then the value of this object must be
            restored after a re-initialization of the management
             system."
    DEFVAL { 300 }
    ::= { natDefTimeouts 3 }
```

Rohit, et al. Standards Track

[Page 14]

```
-- Other protocol parameters
natOtherDefIdleTimeout OBJECT-TYPE
           Unsigned32 (1..4294967295)
    SYNTAX
            "seconds"
    UNITS
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
           "The default idle timeout parameter for protocols
            represented by the value other (2) in
            NatProtocolType.
            If the agent is capable of storing non-volatile
            configuration, then the value of this object must be
            restored after a re-initialization of the management
            system."
   DEFVAL { 60 }
    ::= { natDefTimeouts 4 }
-- TCP related NAT Timers
natTcpDefIdleTimeout OBJECT-TYPE
    SYNTAX Unsigned32 (1..4294967295)
   UNITS
              "seconds"
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
           "The default time interval that a NAT session for an
            established TCP connection is allowed to remain
            valid without any activity on the TCP connection.
            If the agent is capable of storing non-volatile
            configuration, then the value of this object must be
            restored after a re-initialization of the management
            system."
   DEFVAL { 86400 }
    ::= { natDefTimeouts 5 }
natTcpDefNegTimeout OBJECT-TYPE
    SYNTAX Unsigned32 (1..4294967295)
   UNITS
              "seconds"
   MAX-ACCESS read-write
   STATUS current
   DESCRIPTION
```

Rohit, et al. Standards Track [Page 15]

"The default time interval that a NAT session for a TCP connection that is not in the established state is allowed to remain valid without any activity on the TCP connection.

If the agent is capable of storing non-volatile configuration, then the value of this object must be restored after a re-initialization of the management system."

DEFVAL { 60 }
::= { natDefTimeouts 6 }

 ${\tt natNotifThrottlingInterval\ OBJECT-TYPE}$

SYNTAX Integer32 (0 | 5..3600)

UNITS "seconds"
MAX-ACCESS read-write
STATUS current

DESCRIPTION

"This object controls the generation of the natPacketDiscard notification.

If this object has a value of zero, then no natPacketDiscard notifications will be transmitted by the agent.

If this object has a non-zero value, then the agent must not generate more than one natPacketDiscard 'notification-event' in the indicated period, where a 'notification-event' is the generation of a single notification PDU type to a list of notification destinations. If additional NAT packets are discarded within the throttling period, then notification-events for these changes must be suppressed by the agent until the current throttling period expires.

If natNotifThrottlingInterval notification generation is enabled, the suggested default throttling period is 60 seconds, but generation of the natPacketDiscard notification should be disabled by default.

If the agent is capable of storing non-volatile configuration, then the value of this object must be restored after a re-initialization of the management system.

The actual transmission of notifications is controlled via the MIB modules in RFC 3413." DEFVAL { 0 }

Rohit, et al. Standards Track [Page 16]

```
::= { natNotifCtrl 1 }
-- The NAT Interface Table
natInterfaceTable OBJECT-TYPE
    SYNTAX SEQUENCE OF NatInterfaceEntry
    MAX-ACCESS not-accessible
    STATUS current
    DESCRIPTION
             "This table specifies the attributes for interfaces on a
              device supporting NAT function."
    ::= { natMIBObjects 3 }
natInterfaceEntry OBJECT-TYPE
    SYNTAX NatInterfaceEntry
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
             "Each entry in the natInterfaceTable holds a set of
              parameters for an interface, instantiated by
              ifIndex. Therefore, the interface index must have been
              assigned, according to the applicable procedures,
              before it can be meaningfully used.
              Generally, this means that the interface must exist.
              When natStorageType is of type nonVolatile, however,
              this may reflect the configuration for an interface whose
              ifIndex has been assigned but for which the supporting
              implementation is not currently present."
    INDEX { ifIndex }
    ::= { natInterfaceTable 1 }
NatInterfaceEntry ::= SEQUENCE {
    natInterfaceRealm
                                   INTEGER,
    natInterfaceServiceType natInterfaceInTranslates Counter64, natInterfaceOutTranslates natInterfaceDiscards Counter64, natInterfaceStorageType natInterfaceRowStatus RowStatus
}
natInterfaceRealm OBJECT-TYPE
    SYNTAX INTEGER {
                    private (1),
                    public (2)
```

Rohit, et al. Standards Track [Page 17]

```
}
    MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
            "This object identifies whether this interface is
            connected to the private or the public realm."
    DEFVAL { public }
    ::= { natInterfaceEntry 1 }
natInterfaceServiceType OBJECT-TYPE
    SYNTAX BITS {
               basicNat (0),
               napt (1),
               bidirectionalNat (2),
               twiceNat (3)
            }
    MAX-ACCESS read-create
               current
    STATUS
    DESCRIPTION
            "An indication of the direction in which new sessions
            are permitted and the extent of translation done within
            the IP and transport headers."
    ::= { natInterfaceEntry 2 }
natInterfaceInTranslates OBJECT-TYPE
    SYNTAX Counter64
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
            "Number of packets received on this interface that
            were translated.
            Discontinuities in the value of this counter can occur at
             reinitialization of the management system and at other
             times as indicated by the value of
            ifCounterDiscontinuityTime on the relevant interface."
    ::= { natInterfaceEntry 3 }
natInterfaceOutTranslates OBJECT-TYPE
    SYNTAX Counter64
    MAX-ACCESS read-only
    STATUS
           current
    DESCRIPTION
            "Number of translated packets that were sent out this
            interface.
             Discontinuities in the value of this counter can occur at
             reinitialization of the management system and at other
             times as indicated by the value of
```

Rohit, et al. Standards Track [Page 18]

```
ifCounterDiscontinuityTime on the relevant interface."
    ::= { natInterfaceEntry 4 }
natInterfaceDiscards OBJECT-TYPE
    SYNTAX Counter64
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
            "Number of packets that had to be rejected/dropped due to
            a lack of resources for this interface.
            Discontinuities in the value of this counter can occur at
            reinitialization of the management system and at other
             times as indicated by the value of
             ifCounterDiscontinuityTime on the relevant interface."
     ::= { natInterfaceEntry 5 }
natInterfaceStorageType OBJECT-TYPE
    SYNTAX StorageType
    MAX-ACCESS read-create
    STATUS
           current
    DESCRIPTION
            "The storage type for this conceptual row.
             Conceptual rows having the value 'permanent'
            need not allow write-access to any columnar objects
            in the row."
    REFERENCE
            "Textual Conventions for SMIv2, Section 2."
    DEFVAL { nonVolatile }
    ::= { natInterfaceEntry 6 }
natInterfaceRowStatus OBJECT-TYPE
    SYNTAX RowStatus
    MAX-ACCESS read-create
    STATUS
               current
    DESCRIPTION
            "The status of this conceptual row.
             Until instances of all corresponding columns are
             appropriately configured, the value of the
             corresponding instance of the natInterfaceRowStatus
             column is 'notReady'.
             In particular, a newly created row cannot be made
             active until the corresponding instance of
             natInterfaceServiceType has been set.
```

```
None of the objects in this row may be modified
                    while the value of this object is active(1)."
                   "Textual Conventions for SMIv2, Section 2."
      ::= { natInterfaceEntry 7 }
-- The Address Map Table
natAddrMapTable OBJECT-TYPE
      SYNTAX SEQUENCE OF NatAddrMapEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
                 "This table lists address map parameters for NAT."
      ::= { natMIBObjects 4 }
natAddrMapEntry OBJECT-TYPE
      SYNTAX NatAddrMapEntry
      MAX-ACCESS not-accessible
      STATUS
                  current
      DESCRIPTION
                   "This entry represents an address map to be used for
                   NAT and contributes to the dynamic and/or static
                   address mapping tables of the NAT device."
      INDEX { ifIndex, natAddrMapIndex }
      ::= { natAddrMapTable 1 }
NatAddrMapEntry ::= SEQUENCE {
      natAddrMapIndex
                                                      NatAddrMapId,
      natAddrMapName
                                                       SnmpAdminString,
     natAddrMapEntryType
natAddrMapEntryType
natAddrMapTranslationEntity
natAddrMapLocalAddrType
natAddrMapLocalAddrTrom
natAddrMapLocalAddrTo
natAddrMapLocalPortFrom
natAddrMapLocalPortTo
natAddrMapGlobalAddrType
natAddrMapGlobalAddrType
natAddrMapGlobalAddrType
natAddrMapGlobalAddrTo
natAddrMapGlobalAddrType
natAddrMapGlobalAddrTo
natAddrMapGlobalAddrTo
natAddrMapGlobalAddrTo
natAddrMapGlobalPortFrom
natAddrMapGlobalPortFrom
natAddrMapGlobalPortFrom
natAddrMapGlobalPortTo
natAddrMapGlobalPortTo
natAddrMapGlobalPortTo
natAddrMapGlobalPortTo
NatProtocolMap,
      natAddrMapEntryType
                                                       NatAssociationType,
      natAddrMapProtocolNatProtoconatAddrMapInTranslatesCounter64,natAddrMapOutTranslatesCounter64,natAddrMapDiggardsCounter64
      natAddrMapProtocol
                                                     NatProtocolMap,
      natAddrMapDiscards
                                                      Counter64,
```

```
natAddrMapAddrUsed
                                  Gauge32,
   natAddrMapStorageType
                                 StorageType,
   natAddrMapRowStatus
                                 RowStatus
}
natAddrMapIndex OBJECT-TYPE
   SYNTAX NatAddrMapId
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
           "Along with if Index, this object uniquely
            identifies an entry in the natAddrMapTable.
            Address map entries are applied in the order
            specified by natAddrMapIndex."
    ::= { natAddrMapEntry 1 }
natAddrMapName OBJECT-TYPE
   SYNTAX SnmpAdminString (SIZE(1..32))
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
           "Name identifying all map entries in the table associated
            with the same interface. All map entries with the same
            ifIndex MUST have the same map name."
    ::= { natAddrMapEntry 2 }
natAddrMapEntryType OBJECT-TYPE
   SYNTAX NatAssociationType
   MAX-ACCESS read-create
   STATUS
           current
   DESCRIPTION
           "This parameter can be used to set up static
            or dynamic address maps."
    ::= { natAddrMapEntry 3 }
natAddrMapTranslationEntity OBJECT-TYPE
   SYNTAX NatTranslationEntity
   MAX-ACCESS read-create
   STATUS
              current
   DESCRIPTION
           "The end-point entity (source or destination) in
            inbound or outbound sessions (i.e., first packets) that
            may be translated by an address map entry.
            Session direction (inbound or outbound) is
            derived from the direction of the first packet
            of a session traversing a NAT interface.
            NAT address (and Transport-ID) maps may be defined
```

Rohit, et al. Standards Track [Page 21]

to effect inbound or outbound sessions.

Traditionally, address maps for Basic NAT and NAPT are configured on a public interface for outbound sessions, effecting translation of source end-point. The value of this object must be set to outboundSrcEndPoint for those interfaces.

Alternately, if address maps for Basic NAT and NAPT were to be configured on a private interface, the desired value for this object for the map entries would be inboundSrcEndPoint (i.e., effecting translation of source end-point for inbound sessions).

If TwiceNAT were to be configured on a private interface, the desired value for this object for the map entries would be a bitmask of inboundSrcEndPoint and inboundDstEndPoint."

```
::= { natAddrMapEntry 4 }
```

natAddrMapLocalAddrType OBJECT-TYPE

SYNTAX InetAddressType
MAX-ACCESS read-create
STATUS current

DESCRIPTION

"This object specifies the address type used for natAddrMapLocalAddrFrom and natAddrMapLocalAddrTo."

::= { natAddrMapEntry 5 }

natAddrMapLocalAddrFrom OBJECT-TYPE

SYNTAX InetAddress
MAX-ACCESS read-create
STATUS current
DESCRIPTION

"This object specifies the first IP address of the range of IP addresses mapped by this translation entry. The value of this object must be less than or equal to the value of the natAddrMapLocalAddrTo object.

The type of this address is determined by the value of the natAddrMapLocalAddrType object."

::= { natAddrMapEntry 6 }

natAddrMapLocalAddrTo OBJECT-TYPE

SYNTAX InetAddress
MAX-ACCESS read-create
STATUS current

DESCRIPTION

Rohit, et al. Standards Track [Page 22]

> "This object specifies the last IP address of the range of IP addresses mapped by this translation entry. If only a single address is being mapped, the value of this object is equal to the value of natAddrMapLocalAddrFrom. For a static NAT, the number of addresses in the range defined by natAddrMapLocalAddrFrom and natAddrMapLocalAddrTo must be equal to the number of addresses in the range defined by $\verb|natAddrMapGlobalAddrFrom| and \verb|natAddrMapGlobalAddrTo|.$ The value of this object must be greater than or equal to the value of the natAddrMapLocalAddrFrom object.

The type of this address is determined by the value of the natAddrMapLocalAddrType object."

::= { natAddrMapEntry 7 }

natAddrMapLocalPortFrom OBJECT-TYPE

SYNTAX InetPortNumber MAX-ACCESS read-create STATUS current

DESCRIPTION

"If this conceptual row describes a Basic NAT address mapping, then the value of this object must be zero. If this conceptual row describes NAPT, then the value of this object specifies the first port number in the range of ports being mapped.

The value of this object must be less than or equal to the value of the natAddrMapLocalPortTo object. If the translation specifies a single port, then the value of this object is equal to the value of natAddrMapLocalPortTo."

DEFVAL { 0 } ::= { natAddrMapEntry 8 }

natAddrMapLocalPortTo OBJECT-TYPE

SYNTAX InetPortNumber MAX-ACCESS read-create STATUS current

DESCRIPTION

"If this conceptual row describes a Basic NAT address mapping, then the value of this object must be zero. If this conceptual row describes NAPT, then the value of this object specifies the last port number in the range of ports being mapped.

The value of this object must be greater than or equal to the value of the natAddrMapLocalPortFrom object. If the translation specifies a single port, then the value of this object is equal to the value of natAddrMapLocalPortFrom."

Rohit, et al. Standards Track [Page 23]

```
DEFVAL { 0 }
    ::= { natAddrMapEntry 9 }
natAddrMapGlobalAddrType OBJECT-TYPE
    SYNTAX
           InetAddressType
    MAX-ACCESS read-create
    STATUS
           current
    DESCRIPTION
            "This object specifies the address type used for
            natAddrMapGlobalAddrFrom and natAddrMapGlobalAddrTo."
    ::= { natAddrMapEntry 10 }
natAddrMapGlobalAddrFrom OBJECT-TYPE
    SYNTAX InetAddress
    MAX-ACCESS read-create
    STATUS
               current
    DESCRIPTION
            "This object specifies the first IP address of the range of
             IP addresses being mapped to. The value of this object
             must be less than or equal to the value of the
             natAddrMapGlobalAddrTo object.
             The type of this address is determined by the value of
             the natAddrMapGlobalAddrType object."
    ::= { natAddrMapEntry 11 }
natAddrMapGlobalAddrTo OBJECT-TYPE
    SYNTAX
           InetAddress
    MAX-ACCESS read-create
    STATUS
              current
    DESCRIPTION
            "This object specifies the last IP address of the range of
             IP addresses being mapped to. If only a single address is
             being mapped to, the value of this object is equal to the
             value of natAddrMapGlobalAddrFrom. For a static NAT, the
             number of addresses in the range defined by
             natAddrMapGlobalAddrFrom and natAddrMapGlobalAddrTo must be
             equal to the number of addresses in the range defined by
             natAddrMapLocalAddrFrom and natAddrMapLocalAddrTo.
             The value of this object must be greater than or equal to
             the value of the natAddrMapGlobalAddrFrom object.
             The type of this address is determined by the value of
             the natAddrMapGlobalAddrType object."
    ::= { natAddrMapEntry 12 }
natAddrMapGlobalPortFrom OBJECT-TYPE
    SYNTAX
              InetPortNumber
```

```
MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
           "If this conceptual row describes a Basic NAT address
            mapping, then the value of this object must be zero. If
            this conceptual row describes NAPT, then the value of
            this object specifies the first port number in the range
            of ports being mapped to.
            The value of this object must be less than or equal to the
            value of the natAddrMapGlobalPortTo object. If the
            translation specifies a single port, then the value of this
            object is equal to the value natAddrMapGlobalPortTo."
   DEFVAL { 0 }
    ::= { natAddrMapEntry 13 }
natAddrMapGlobalPortTo OBJECT-TYPE
   SYNTAX
              InetPortNumber
   MAX-ACCESS read-create
   STATUS
           current
   DESCRIPTION
            "If this conceptual row describes a Basic NAT address
            mapping, then the value of this object must be zero. If
            this conceptual row describes NAPT, then the value of this
            object specifies the last port number in the range of
            ports being mapped to.
            The value of this object must be greater than or equal to
            the value of the natAddrMapGlobalPortFrom object. If the
            translation specifies a single port, then the value of this
            object is equal to the value of natAddrMapGlobalPortFrom."
   DEFVAL { 0 }
    ::= { natAddrMapEntry 14 }
natAddrMapProtocol OBJECT-TYPE
   SYNTAX NatProtocolMap
   MAX-ACCESS read-create
   STATUS
           current
   DESCRIPTION
            "This object specifies a bitmap of protocol identifiers."
    ::= { natAddrMapEntry 15 }
natAddrMapInTranslates OBJECT-TYPE
   SYNTAX Counter64
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
```

Rohit, et al. Standards Track [Page 25]

```
"The number of inbound packets pertaining to this address
            map entry that were translated.
            Discontinuities in the value of this counter can occur at
            reinitialization of the management system and at other
            times, as indicated by the value of
             ifCounterDiscontinuityTime on the relevant interface."
    ::= { natAddrMapEntry 16 }
natAddrMapOutTranslates OBJECT-TYPE
    SYNTAX Counter64
    MAX-ACCESS read-only
    STATUS
           current
   DESCRIPTION
           "The number of outbound packets pertaining to this
            address map entry that were translated.
            Discontinuities in the value of this counter can occur at
            reinitialization of the management system and at other
            times, as indicated by the value of
             ifCounterDiscontinuityTime on the relevant interface."
    ::= { natAddrMapEntry 17 }
natAddrMapDiscards OBJECT-TYPE
    SYNTAX
           Counter64
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
            "The number of packets pertaining to this address map
            entry that were dropped due to lack of addresses in the
            address pool identified by this address map. The value of
            this object must always be zero in case of static
            address map.
            Discontinuities in the value of this counter can occur at
            reinitialization of the management system and at other
            times, as indicated by the value of
             ifCounterDiscontinuityTime on the relevant interface."
    ::= { natAddrMapEntry 18 }
natAddrMapAddrUsed OBJECT-TYPE
    SYNTAX Gauge32
   MAX-ACCESS read-only
   STATUS
           current
   DESCRIPTION
            "The number of addresses pertaining to this address map
            that are currently being used from the NAT pool.
            The value of this object must always be zero in the case
```

```
of a static address map."
    ::= { natAddrMapEntry 19 }
natAddrMapStorageType OBJECT-TYPE
    SYNTAX
           StorageType
    MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
            "The storage type for this conceptual row.
            Conceptual rows having the value 'permanent'
            need not allow write-access to any columnar objects
            in the row."
    REFERENCE
            "Textual Conventions for SMIv2, Section 2."
    DEFVAL { nonVolatile }
    ::= { natAddrMapEntry 20 }
natAddrMapRowStatus OBJECT-TYPE
    SYNTAX
              RowStatus
    MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
            "The status of this conceptual row.
             Until instances of all corresponding columns are
             appropriately configured, the value of the
             corresponding instance of the natAddrMapRowStatus
             column is 'notReady'.
            None of the objects in this row may be modified
            while the value of this object is active(1)."
    REFERENCE
           "Textual Conventions for SMIv2, Section 2."
    ::= { natAddrMapEntry 21 }
-- Address Bind section
natAddrBindNumberOfEntries OBJECT-TYPE
    SYNTAX Gauge32
    MAX-ACCESS read-only
    STATUS
           current
    DESCRIPTION
            "This object maintains a count of the number of entries
            that currently exist in the natAddrBindTable."
    ::= { natMIBObjects 5 }
```

Rohit, et al. Standards Track [Page 27]

```
-- The NAT Address BIND Table
natAddrBindTable OBJECT-TYPE
    SYNTAX SEQUENCE OF NatAddrBindEntry
   MAX-ACCESS not-accessible
    STATUS current
   DESCRIPTION
            "This table holds information about the currently
            active NAT BINDs."
    ::= { natMIBObjects 6 }
natAddrBindEntry OBJECT-TYPE
    SYNTAX NatAddrBindEntry
   MAX-ACCESS not-accessible
    STATUS
           current
   DESCRIPTION
            "Each entry in this table holds information about
            an active address BIND. These entries are lost
             upon agent restart.
             This row has indexing which may create variables with
             more than 128 subidentifiers. Implementers of this table
             must be careful not to create entries that would result
             in OIDs which exceed the 128 subidentifier limit.
             Otherwise, the information cannot be accessed using
             SNMPv1, SNMPv2c or SNMPv3."
    INDEX { ifIndex, natAddrBindLocalAddrType, natAddrBindLocalAddr }
    ::= { natAddrBindTable 1 }
NatAddrBindEntry ::= SEQUENCE {
   natAddrBindLocalAddrType
                                   InetAddressType,
   natAddrBindLocalAddr
                                   InetAddress,
   natAddrBindGlobalAddrType InetAddressType, natAddrBindGlobalAddr InetAddress,
   natAddrBindId
                                  NatBindId,
   {\tt natAddrBindTranslationEntity} \qquad {\tt NatTranslationEntity},
                                  NatAssociationType,
   natAddrBindType
                                  NatAddrMapId,
   natAddrBindMapIndex
   natAddrBindSessions
                                   Gauge32,
   natAddrBindMaxIdleTime
                                   TimeTicks,
   natAddrBindCurrentIdleTime TimeTicks,
   natAddrBindInTranslates
                                  Counter64,
   natAddrBindOutTranslates
                                  Counter64
}
```

Rohit, et al. Standards Track [Page 28]

```
natAddrBindLocalAddrType OBJECT-TYPE
    SYNTAX InetAddressType
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
           "This object specifies the address type used for
            natAddrBindLocalAddr."
    ::= { natAddrBindEntry 1 }
natAddrBindLocalAddr OBJECT-TYPE
   SYNTAX InetAddress
    MAX-ACCESS not-accessible
    STATUS
           current
   DESCRIPTION
           "This object represents the private-realm specific network
            layer address, which maps to the public-realm address
            represented by natAddrBindGlobalAddr.
            The type of this address is determined by the value of
            the natAddrBindLocalAddrType object."
   ::= { natAddrBindEntry 2 }
natAddrBindGlobalAddrType OBJECT-TYPE
   SYNTAX InetAddressType
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
            "This object specifies the address type used for
            natAddrBindGlobalAddr."
    ::= { natAddrBindEntry 3 }
natAddrBindGlobalAddr OBJECT-TYPE
    SYNTAX InetAddress
   MAX-ACCESS read-only
    STATUS
           current
   DESCRIPTION
            "This object represents the public-realm network layer
            address that maps to the private-realm network layer
            address represented by natAddrBindLocalAddr.
            The type of this address is determined by the value of
             the natAddrBindGlobalAddrType object."
    ::= { natAddrBindEntry 4 }
natAddrBindId OBJECT-TYPE
    SYNTAX NatBindId
   MAX-ACCESS read-only
   STATUS current
```

```
DESCRIPTION
           "This object represents a bind id that is dynamically
            assigned to each bind by a NAT enabled device. Each
            bind is represented by a bind id that is
            unique across both, the natAddrBindTable and the
            natAddrPortBindTable."
    ::= { natAddrBindEntry 5 }
natAddrBindTranslationEntity OBJECT-TYPE
    SYNTAX NatTranslationEntity
   MAX-ACCESS read-only
    STATUS current
   DESCRIPTION
            "This object represents the direction of sessions
            for which this bind is applicable and the endpoint entity
             (source or destination) within the sessions that is
            subject to translation using the BIND.
            Orientation of the bind can be a superset of
            translationEntity of the address map entry which
            forms the basis for this bind.
            For example, if the translationEntity of an
            address map entry is outboundSrcEndPoint, the
            translationEntity of a bind derived from this
            map entry may either be outboundSrcEndPoint or
            it may be bidirectional (a bitmask of
            outboundSrcEndPoint and inboundDstEndPoint)."
    ::= { natAddrBindEntry 6 }
natAddrBindType OBJECT-TYPE
    SYNTAX NatAssociationType
    MAX-ACCESS read-only
    STATUS
           current
   DESCRIPTION
            "This object indicates whether the bind is static or
            dynamic."
    ::= { natAddrBindEntry 7 }
natAddrBindMapIndex OBJECT-TYPE
    SYNTAX NatAddrMapId
   MAX-ACCESS read-only
    STATUS
           current
    DESCRIPTION
            "This object is a pointer to the natAddrMapTable entry
            (and the parameters of that entry) which was used in
            creating this BIND. This object, in conjunction with the
```

ifIndex (which identifies a unique addrMapName) points to

```
a unique entry in the natAddrMapTable."
    ::= { natAddrBindEntry 8 }
natAddrBindSessions OBJECT-TYPE
    SYNTAX Gauge32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
            "Number of sessions currently using this BIND."
    ::= { natAddrBindEntry 9 }
natAddrBindMaxIdleTime OBJECT-TYPE
    SYNTAX TimeTicks
    MAX-ACCESS read-only
    STATUS
           current
    DESCRIPTION
            "This object indicates the maximum time for
            which this bind can be idle with no sessions
             attached to it.
             The value of this object is of relevance only for
             dynamic NAT."
    ::= { natAddrBindEntry 10 }
natAddrBindCurrentIdleTime OBJECT-TYPE
    SYNTAX TimeTicks
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
            "At any given instance, this object indicates the
            time that this bind has been idle without any sessions
             attached to it.
             The value of this object is of relevance only for
             dynamic NAT."
    ::= { natAddrBindEntry 11 }
natAddrBindInTranslates OBJECT-TYPE
    SYNTAX Counter64
    MAX-ACCESS read-only
    STATUS
           current
    DESCRIPTION
            "The number of inbound packets that were successfully
            translated by using this bind entry.
             Discontinuities in the value of this counter can occur at
             reinitialization of the management system and at other
             times, as indicated by the value of
```

```
ifCounterDiscontinuityTime on the relevant interface."
    ::= { natAddrBindEntry 12 }
natAddrBindOutTranslates OBJECT-TYPE
   SYNTAX Counter64
   MAX-ACCESS read-only
   STATUS current
    DESCRIPTION
            "The number of outbound packets that were successfully
            translated using this bind entry.
            Discontinuities in the value of this counter can occur at
            reinitialization of the management system and at other
            times as indicated by the value of
            ifCounterDiscontinuityTime on the relevant interface."
    ::= { natAddrBindEntry 13 }
-- Address Port Bind section
natAddrPortBindNumberOfEntries OBJECT-TYPE
   SYNTAX Gauge32
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
            "This object maintains a count of the number of entries
            that currently exist in the natAddrPortBindTable."
    ::= { natMIBObjects 7 }
-- The NAT Address Port Bind Table
natAddrPortBindTable OBJECT-TYPE
   SYNTAX SEQUENCE OF NatAddrPortBindEntry
   MAX-ACCESS not-accessible
           current
   DESCRIPTION
            "This table holds information about the currently
            active NAPT BINDs."
    ::= { natMIBObjects 8 }
natAddrPortBindEntry OBJECT-TYPE
    SYNTAX NatAddrPortBindEntry
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
```

```
"Each entry in the this table holds information
              about a NAPT bind that is currently active.
              These entries are lost upon agent restart.
              This row has indexing which may create variables with
              more than 128 subidentifiers. Implementers of this table
              must be careful not to create entries which would result
              in OIDs that exceed the 128 subidentifier limit.
              Otherwise, the information cannot be accessed using
              SNMPv1, SNMPv2c or SNMPv3."
    INDEX { ifIndex, natAddrPortBindLocalAddrType,
               natAddrPortBindLocalAddr, natAddrPortBindLocalPort,
               natAddrPortBindProtocol }
    ::= { natAddrPortBindTable 1 }
NatAddrPortBindEntry ::= SEQUENCE {
    natAddrPortBindLocalAddrType InetAddressType,
natAddrPortBindLocalAddr InetAddress,
    natAddrPortBindLocalPort
                                         Inetroless
NatProtocolType,
                                           InetPortNumber,
    natAddrPortBindEocalFort
natAddrPortBindProtocol
natAddrPortBindGlobalAddrType
natAddrPortBindGlobalAddr
natAddrPortBindGlobalPort
natAddrPortBindGlobalPort
natAddrPortBindId
NatBindId,
    natAddrPortBindId
                                           NatBindId,
    {\tt natAddrPortBindTranslationEntity} \qquad {\tt NatTranslationEntity},
                                NatAssociationType,
NatAddrMapId,
    natAddrPortBindType
    natAddrPortBindMapIndex
    natAddrPortBindSessions
                                          Gauge32,
    natAddrPortBindMaxIdleTime
                                           TimeTicks,
    \verb"natAddrPortBindCurrentIdleTime" TimeTicks",
    natAddrPortBindInTranslates
                                          Counter64,
    natAddrPortBindOutTranslates
                                           Counter64
}
natAddrPortBindLocalAddrType OBJECT-TYPE
    SYNTAX InetAddressType
    MAX-ACCESS not-accessible
    STATUS
            current
    DESCRIPTION
             "This object specifies the address type used for
              natAddrPortBindLocalAddr."
    ::= { natAddrPortBindEntry 1 }
natAddrPortBindLocalAddr OBJECT-TYPE
    SYNTAX InetAddress
    MAX-ACCESS not-accessible
    STATUS current
    DESCRIPTION
```

"This object represents the private-realm specific network layer address which, in conjunction with natAddrPortBindLocalPort, maps to the public-realm network layer address and transport id represented by natAddrPortBindGlobalAddr and natAddrPortBindGlobalPort respectively.

The type of this address is determined by the value of the natAddrPortBindLocalAddrType object."
::= { natAddrPortBindEntry 2 }

natAddrPortBindLocalPort OBJECT-TYPE
 SYNTAX InetPortNumber
 MAX-ACCESS not-accessible

STATUS current

DESCRIPTION

"For a protocol value TCP or UDP, this object represents the private-realm specific port number. On the other hand, for ICMP a bind is created only for query/response type ICMP messages such as ICMP echo, Timestamp, and Information request messages, and this object represents the private-realm specific identifier in the ICMP message, as defined in RFC 792 for ICMPv4 and in RFC 2463 for ICMPv6.

This object, together with natAddrPortBindProtocol, natAddrPortBindLocalAddrType, and natAddrPortBindLocalAddr, constitutes a session endpoint in the private realm. A bind entry binds a private realm specific endpoint to a public realm specific endpoint, as represented by the tuple of (natAddrPortBindGlobalPort, natAddrPortBindProtocol, natAddrPortBindGlobalAddrType, and natAddrPortBindGlobalAddr)."

::= { natAddrPortBindEntry 3 }

natAddrPortBindProtocol OBJECT-TYPE

SYNTAX NatProtocolType
MAX-ACCESS not-accessible
STATUS current

DESCRIPTION

"This object specifies a protocol identifier. If the value of this object is none(1), then this bind entry applies to all IP traffic. Any other value of this object specifies the class of IP traffic to which this BIND applies."

::= { natAddrPortBindEntry 4 }

Rohit, et al. Standards Track [Page 34]

```
natAddrPortBindGlobalAddrType OBJECT-TYPE
    SYNTAX InetAddressType
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
            "This object specifies the address type used for
            natAddrPortBindGlobalAddr."
    ::= { natAddrPortBindEntry 5 }
natAddrPortBindGlobalAddr OBJECT-TYPE
    SYNTAX InetAddress
    MAX-ACCESS read-only
    STATUS
           current
    DESCRIPTION
            "This object represents the public-realm specific network
             layer address that, in conjunction with
             natAddrPortBindGlobalPort, maps to the private-realm
             network layer address and transport id represented by
             natAddrPortBindLocalAddr and natAddrPortBindLocalPort,
             respectively.
             The type of this address is determined by the value of
             the natAddrPortBindGlobalAddrType object."
    ::= { natAddrPortBindEntry 6 }
natAddrPortBindGlobalPort OBJECT-TYPE
    SYNTAX InetPortNumber
    MAX-ACCESS read-only
    STATUS
            current
    DESCRIPTION
            "For a protocol value TCP or UDP, this object represents
             the public-realm specific port number. On the other
             hand, for ICMP a bind is created only for query/response
             type ICMP messages such as ICMP echo, Timestamp, and
             Information request messages, and this object represents
             the public-realm specific identifier in the ICMP message,
             as defined in RFC 792 for ICMPv4 and in RFC 2463 for
             ICMPv6.
             This object, together with natAddrPortBindProtocol,
             natAddrPortBindGlobalAddrType, and
             natAddrPortBindGlobalAddr, constitutes a session endpoint
```

as represented by the tuple of

natAddrPortBindLocalAddrType, and

in the public realm. A bind entry binds a public realm specific endpoint to a private realm specific endpoint,

(natAddrPortBindLocalPort, natAddrPortBindProtocol,

```
natAddrPortBindLocalAddr)."
    ::= { natAddrPortBindEntry 7 }
natAddrPortBindId OBJECT-TYPE
    SYNTAX NatBindId
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
            "This object represents a bind id that is dynamically
             assigned to each bind by a NAT enabled device. Each
             bind is represented by a unique bind id across both
             the natAddrBindTable and the natAddrPortBindTable."
    ::= { natAddrPortBindEntry 8 }
natAddrPortBindTranslationEntity OBJECT-TYPE
    SYNTAX NatTranslationEntity
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
            "This object represents the direction of sessions
            for which this bind is applicable and the entity
             (source or destination) within the sessions that is
             subject to translation with the BIND.
             Orientation of the bind can be a superset of the
             translationEntity of the address map entry that
             forms the basis for this bind.
             For example, if the translationEntity of an
             address map entry is outboundSrcEndPoint, the
             translationEntity of a bind derived from this
             map entry may either be outboundSrcEndPoint or
             may be bidirectional (a bitmask of
             outboundSrcEndPoint and inboundDstEndPoint)."
    ::= { natAddrPortBindEntry 9 }
natAddrPortBindType OBJECT-TYPE
            NatAssociationType
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
            "This object indicates whether the bind is static or
             dynamic."
    ::= { natAddrPortBindEntry 10 }
natAddrPortBindMapIndex OBJECT-TYPE
    SYNTAX NatAddrMapId
    MAX-ACCESS read-only
```

```
STATUS
           current
   DESCRIPTION
           "This object is a pointer to the natAddrMapTable entry
            (and the parameters of that entry) used in
            creating this BIND. This object, in conjunction with the
            ifIndex (which identifies a unique addrMapName), points
             to a unique entry in the natAddrMapTable."
    ::= { natAddrPortBindEntry 11 }
natAddrPortBindSessions OBJECT-TYPE
   SYNTAX Gauge32
   MAX-ACCESS read-only
    STATUS current
   DESCRIPTION
          "Number of sessions currently using this BIND."
    ::= { natAddrPortBindEntry 12 }
natAddrPortBindMaxIdleTime OBJECT-TYPE
    SYNTAX TimeTicks
   MAX-ACCESS read-only
    STATUS current
   DESCRIPTION
            "This object indicates the maximum time for
            which this bind can be idle without any sessions
            attached to it.
            The value of this object is of relevance
            only for dynamic NAT."
    ::= { natAddrPortBindEntry 13 }
natAddrPortBindCurrentIdleTime OBJECT-TYPE
   SYNTAX TimeTicks
    MAX-ACCESS read-only
    STATUS
           current
   DESCRIPTION
           "At any given instance, this object indicates the
            time that this bind has been idle without any sessions
            attached to it.
            The value of this object is of relevance
            only for dynamic NAT."
    ::= { natAddrPortBindEntry 14 }
natAddrPortBindInTranslates OBJECT-TYPE
   SYNTAX Counter64
   MAX-ACCESS read-only
    STATUS current
   DESCRIPTION
```

Rohit, et al. Standards Track [Page 37]

```
"The number of inbound packets that were translated as per
            this bind entry.
            Discontinuities in the value of this counter can occur at
             reinitialization of the management system and at other
             times, as indicated by the value of
             ifCounterDiscontinuityTime on the relevant interface."
    ::= { natAddrPortBindEntry 15 }
natAddrPortBindOutTranslates OBJECT-TYPE
    SYNTAX Counter64
    MAX-ACCESS read-only
    STATUS
           current
    DESCRIPTION
           "The number of outbound packets that were translated as per
            this bind entry.
             Discontinuities in the value of this counter can occur at
             reinitialization of the management system and at other
             times, as indicated by the value of
             ifCounterDiscontinuityTime on the relevant interface."
    ::= { natAddrPortBindEntry 16 }
-- The Session Table
natSessionTable OBJECT-TYPE
    SYNTAX SEQUENCE OF NatSessionEntry
    MAX-ACCESS not-accessible
    STATUS current
    DESCRIPTION
            "The (conceptual) table containing one entry for each
            NAT session currently active on this NAT device."
    ::= { natMIBObjects 9 }
natSessionEntry OBJECT-TYPE
    SYNTAX NatSessionEntry
    MAX-ACCESS not-accessible
    STATUS
           current
    DESCRIPTION
            "An entry (conceptual row) containing information
            about an active NAT session on this NAT device.
            These entries are lost upon agent restart."
    INDEX { ifIndex, natSessionIndex }
    ::= { natSessionTable 1 }
NatSessionEntry ::= SEQUENCE {
```

Rohit, et al. Standards Track [Page 38]

```
natSessionIndex
                                         NatSessionId,
   natSessionPrivateSrcEPBindId
                                        NatBindIdOrZero,
   natSessionPrivateSrcEPBindMode
                                        NatBindMode,
   natSessionPrivateDstEPBindId
                                        NatBindIdOrZero,
   natSessionPrivateDstEPBindMode
                                        NatBindMode,
   natSessionDirection
                                         INTEGER,
   natSessionUpTime
                                         TimeTicks,
   natSessionAddrMapIndex
                                         NatAddrMapId,
   natSessionProtocolType
                                        NatProtocolType,
   natSessionPrivateAddrType
                                        InetAddressType,
   natSessionPrivateSrcAddr
                                        InetAddress,
   natSessionPrivateSrcPort
                                        InetPortNumber,
   natSessionPrivateDstAddr
                                        InetAddress,
   natSessionPrivateDstPort
                                        InetPortNumber,
   natSessionPublicAddrType
                                        InetAddressType,
   natSessionPublicSrcAddr
                                         InetAddress,
   natSessionPublicSrcPort
                                         InetPortNumber,
   natSessionPublicDstAddr
                                        InetAddress,
   natSessionPublicDstPort
                                        InetPortNumber,
   natSessionMaxIdleTime
                                        TimeTicks,
   natSessionCurrentIdleTime
                                        TimeTicks,
   natSessionInTranslates
                                        Counter64,
   natSessionOutTranslates
                                         Counter64
}
natSessionIndex OBJECT-TYPE
   SYNTAX NatSessionId
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
           "The session ID for this NAT session."
    ::= { natSessionEntry 1 }
natSessionPrivateSrcEPBindId OBJECT-TYPE
   SYNTAX NatBindIdOrZero
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
           "The bind id associated between private and public
            source end points. In the case of Symmetric-NAT,
            this should be set to zero."
    ::= { natSessionEntry 2 }
natSessionPrivateSrcEPBindMode OBJECT-TYPE
   SYNTAX NatBindMode
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
```

Rohit, et al. Standards Track [Page 39]

```
"This object indicates whether the bind indicated
            by the object natSessionPrivateSrcEPBindId
            is an address bind or an address port bind."
    ::= { natSessionEntry 3 }
natSessionPrivateDstEPBindId OBJECT-TYPE
    SYNTAX NatBindIdOrZero
   MAX-ACCESS read-only
   STATUS
           current
   DESCRIPTION
            "The bind id associated between private and public
            destination end points."
    ::= { natSessionEntry 4 }
natSessionPrivateDstEPBindMode OBJECT-TYPE
    SYNTAX NatBindMode
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
            "This object indicates whether the bind indicated
            by the object natSessionPrivateDstEPBindId
            is an address bind or an address port bind."
    ::= { natSessionEntry 5 }
natSessionDirection OBJECT-TYPE
   SYNTAX INTEGER {
                  inbound (1),
                  outbound (2)
               }
   MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
            "The direction of this session with respect to the
            local network. 'inbound' indicates that this session
            was initiated from the public network into the private
            network. 'outbound' indicates that this session was
            initiated from the private network into the public
            network."
    ::= { natSessionEntry 6 }
natSessionUpTime OBJECT-TYPE
    SYNTAX TimeTicks
   MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
           "The up time of this session in one-hundredths of a
            second."
```

Rohit, et al. Standards Track [Page 40]

```
::= { natSessionEntry 7 }
natSessionAddrMapIndex OBJECT-TYPE
   SYNTAX NatAddrMapId
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
            "This object is a pointer to the natAddrMapTable entry
            (and the parameters of that entry) used in
            creating this session. This object, in conjunction with
            the ifIndex (which identifies a unique addrMapName), points
            to a unique entry in the natAddrMapTable."
    ::= { natSessionEntry 8 }
natSessionProtocolType OBJECT-TYPE
   SYNTAX NatProtocolType
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
           "The protocol type of this session."
    ::= { natSessionEntry 9 }
natSessionPrivateAddrType OBJECT-TYPE
   SYNTAX InetAddressType
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
           "This object specifies the address type used for
            natSessionPrivateSrcAddr and natSessionPrivateDstAddr."
    ::= { natSessionEntry 10 }
natSessionPrivateSrcAddr OBJECT-TYPE
   SYNTAX InetAddress
   MAX-ACCESS read-only
   STATUS
           current
   DESCRIPTION
           "The source IP address of the session endpoint that
            lies in the private network.
            The value of this object must be zero only when the
            natSessionPrivateSrcEPBindId object has a zero value.
            When the value of this object is zero, the NAT session
            lookup will match any IP address to this field.
            The type of this address is determined by the value of
            the natSessionPrivateAddrType object."
    ::= { natSessionEntry 11 }
```

natSessionPrivateSrcPort OBJECT-TYPE

SYNTAX InetPortNumber
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"When the value of protocol is TCP or UDP, this object represents the source port in the first packet of session while in private-realm. On the other hand, when the protocol is ICMP, a NAT session is created only for query/response type ICMP messages such as ICMP echo, Timestamp, and Information request messages, and this object represents the private-realm specific identifier in the ICMP message, as defined in RFC 792 for ICMPv4 and in RFC 2463 for ICMPv6.

The value of this object must be zero when the natSessionPrivateSrcEPBindId object has zero value and value of natSessionPrivateSrcEPBindMode is addressPortBind(2). In such a case, the NAT session lookup will match any port number to this field.

The value of this object must be zero when the object is not a representative field (SrcPort, DstPort, or ICMP identifier) of the session tuple in either the public realm or the private realm."

::= { natSessionEntry 12 }

natSessionPrivateDstAddr OBJECT-TYPE

SYNTAX InetAddress
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"The destination IP address of the session endpoint that lies in the private network.

The value of this object must be zero when the natSessionPrivateDstEPBindId object has a zero value. In such a scenario, the NAT session lookup will match any IP address to this field.

The type of this address is determined by the value of the natSessionPrivateAddrType object."

::= { natSessionEntry 13 }

natSessionPrivateDstPort OBJECT-TYPE

SYNTAX InetPortNumber
MAX-ACCESS read-only
STATUS current

Rohit, et al. Standards Track [Page 42]

DESCRIPTION

"When the value of protocol is TCP or UDP, this object represents the destination port in the first packet of session while in private-realm. On the other hand, when the protocol is ICMP, this object is not relevant and should be set to zero.

The value of this object must be zero when the natSessionPrivateDstEPBindId object has a zero value and natSessionPrivateDstEPBindMode is set to addressPortBind(2). In such a case, the NAT session lookup will match any port number to this field.

The value of this object must be zero when the object is not a representative field (SrcPort, DstPort, or ICMP identifier) of the session tuple in either the public realm or the private realm."

::= { natSessionEntry 14 }

natSessionPublicAddrType OBJECT-TYPE

SYNTAX InetAddressType

MAX-ACCESS read-only STATUS current

DESCRIPTION

natSessionPublicSrcAddr OBJECT-TYPE

SYNTAX InetAddress
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"The source IP address of the session endpoint that lies in the public network.

The value of this object must be zero when the natSessionPrivateSrcEPBindId object has a zero value. In such a scenario, the NAT session lookup will match any IP address to this field.

The type of this address is determined by the value of the natSessionPublicAddrType object."

::= { natSessionEntry 16 }

natSessionPublicSrcPort OBJECT-TYPE

SYNTAX InetPortNumber MAX-ACCESS read-only

Rohit, et al. Standards Track [Page 43]

STATUS current DESCRIPTION

"When the value of protocol is TCP or UDP, this object represents the source port in the first packet of session while in public-realm. On the other hand, when protocol is ICMP, a NAT session is created only for query/response type ICMP messages such as ICMP echo, Timestamp, and Information request messages, and this object represents the public-realm specific identifier in the ICMP message, as defined in RFC 792 for ICMPv4 and in RFC 2463 for ICMPv6.

The value of this object must be zero when the natSessionPrivateSrcEPBindId object has a zero value and natSessionPrivateSrcEPBindMode is set to addressPortBind(2). In such a scenario, the NAT session lookup will match any port number to this field.

The value of this object must be zero when the object is not a representative field (SrcPort, DstPort or ICMP identifier) of the session tuple in either the public realm or the private realm."

::= { natSessionEntry 17 }

natSessionPublicDstAddr OBJECT-TYPE

SYNTAX InetAddress
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"The destination IP address of the session endpoint that lies in the public network.

The value of this object must be non-zero when the natSessionPrivateDstEPBindId object has a non-zero value. If the value of this object and the corresponding natSessionPrivateDstEPBindId object value is zero, then the NAT session lookup will match any IP address to this field.

The type of this address is determined by the value of the natSessionPublicAddrType object."

::= { natSessionEntry 18 }

natSessionPublicDstPort OBJECT-TYPE

SYNTAX InetPortNumber
MAX-ACCESS read-only
STATUS current

Rohit, et al. Standards Track [Page 44]

DESCRIPTION

"When the value of protocol is TCP or UDP, this object represents the destination port in the first packet of session while in public-realm. On the other hand, when the protocol is ICMP, this object is not relevant for translation and should be zero.

The value of this object must be zero when the natSessionPrivateDstEPBindId object has a zero value and natSessionPrivateDstEPBindMode is addressPortBind(2). In such a scenario, the NAT session lookup will match any port number to this field.

The value of this object must be zero when the object is not a representative field (SrcPort, DstPort, or ICMP identifier) of the session tuple in either the public realm or the private realm."

```
::= { natSessionEntry 19 }
```

natSessionMaxIdleTime OBJECT-TYPE

SYNTAX TimeTicks
MAX-ACCESS read-only
STATUS current

DESCRIPTION

"The max time for which this session can be idle without detecting a packet."

::= { natSessionEntry 20 }

natSessionCurrentIdleTime OBJECT-TYPE

SYNTAX TimeTicks
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"The time since a packet belonging to this session was last detected."

::= { natSessionEntry 21 }

natSessionInTranslates OBJECT-TYPE

SYNTAX Counter64
MAX-ACCESS read-only
STATUS current
DESCRIPTION

"The number of inbound packets that were translated for this session.

Discontinuities in the value of this counter can occur at reinitialization of the management system and at other

Rohit, et al. Standards Track [Page 45]

```
times, as indicated by the value of
             ifCounterDiscontinuityTime on the relevant interface."
    ::= { natSessionEntry 22 }
natSessionOutTranslates OBJECT-TYPE
    SYNTAX Counter64
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
            "The number of outbound packets that were translated for
            this session.
             Discontinuities in the value of this counter can occur at
             reinitialization of the management system and at other
             times, as indicated by the value of
             ifCounterDiscontinuityTime on the relevant interface."
    ::= { natSessionEntry 23 }
-- The Protocol table
natProtocolTable OBJECT-TYPE
    SYNTAX SEQUENCE OF NatProtocolEntry
    MAX-ACCESS not-accessible
    STATUS
           current
    DESCRIPTION
            "The (conceptual) table containing per protocol NAT
            statistics."
    ::= { natMIBObjects 10 }
natProtocolEntry OBJECT-TYPE
    SYNTAX NatProtocolEntry
    MAX-ACCESS not-accessible
    STATUS
           current
    DESCRIPTION
            "An entry (conceptual row) containing NAT statistics
            pertaining to a particular protocol."
    INDEX { natProtocol }
    ::= { natProtocolTable 1 }
NatProtocolEntry ::= SEQUENCE {
    natProtocol
                               NatProtocolType,
   natProtocol NatProtocol natProtocolInTranslates Counter64,
   natProtocolOutTranslates Counter64,
   natProtocolDiscards
                            Counter64
}
```

Rohit, et al. Standards Track [Page 46]

```
natProtocol OBJECT-TYPE
   SYNTAX
            NatProtocolType
   MAX-ACCESS not-accessible
    STATUS
           current
   DESCRIPTION
           "This object represents the protocol pertaining to which
            parameters are reported."
    ::= { natProtocolEntry 1 }
natProtocolInTranslates OBJECT-TYPE
   SYNTAX Counter64
   MAX-ACCESS read-only
    STATUS
           current
   DESCRIPTION
           "The number of inbound packets pertaining to the protocol
            identified by natProtocol that underwent NAT.
            Discontinuities in the value of this counter can occur at
            reinitialization of the management system and at other
            times, as indicated by the value of
             ifCounterDiscontinuityTime on the relevant interface."
    ::= { natProtocolEntry 2 }
natProtocolOutTranslates OBJECT-TYPE
    SYNTAX Counter64
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
            "The number of outbound packets pertaining to the protocol
            identified by natProtocol that underwent NAT.
            Discontinuities in the value of this counter can occur at
            reinitialization of the management system and at other
            times, as indicated by the value of
            ifCounterDiscontinuityTime on the relevant interface."
    ::= { natProtocolEntry 3 }
natProtocolDiscards OBJECT-TYPE
   SYNTAX Counter64
   MAX-ACCESS read-only
   STATUS
           current
    DESCRIPTION
            "The number of packets pertaining to the protocol
            identified by natProtocol that had to be
            rejected/dropped due to lack of resources. These
            rejections could be due to session timeout, resource
            unavailability, lack of address space, etc.
```

```
Discontinuities in the value of this counter can occur at
             reinitialization of the management system and at other
             times, as indicated by the value of
             ifCounterDiscontinuityTime on the relevant interface."
     ::= { natProtocolEntry 4 }
-- Notifications section
natMIBNotifications OBJECT IDENTIFIER ::= { natMIB 0 }
-- Notifications
natPacketDiscard NOTIFICATION-TYPE
    OBJECTS { ifIndex }
    STATUS current
    DESCRIPTION
            "This notification is generated when IP packets are
             discarded by the NAT function; e.g., due to lack of
             mapping space when NAT is out of addresses or ports.
             Note that the generation of natPacketDiscard
             notifications is throttled by the agent, as specified
             by the 'natNotifThrottlingInterval' object."
    ::= { natMIBNotifications 1 }
-- Conformance information.
natMIBConformance OBJECT IDENTIFIER ::= { natMIB 2 }
natMIBGroups      OBJECT IDENTIFIER ::= { natMIBConformance 1 }
natMIBCompliances OBJECT IDENTIFIER ::= { natMIBConformance 2 }
-- Units of conformance
natConfigGroup OBJECT-GROUP
    OBJECTS { natInterfaceRealm,
             natInterfaceServiceType,
              natInterfaceStorageType,
              natInterfaceRowStatus,
              natAddrMapName,
```

Rohit, et al. Standards Track [Page 48]

```
natAddrMapEntryType,
              natAddrMapTranslationEntity,
              natAddrMapLocalAddrType,
              natAddrMapLocalAddrFrom,
              natAddrMapLocalAddrTo,
              natAddrMapLocalPortFrom,
              natAddrMapLocalPortTo,
              natAddrMapGlobalAddrType,
              natAddrMapGlobalAddrFrom,
              natAddrMapGlobalAddrTo,
              natAddrMapGlobalPortFrom,
              natAddrMapGlobalPortTo,
              natAddrMapProtocol,
              natAddrMapStorageType,
              natAddrMapRowStatus,
              natBindDefIdleTimeout,
              natUdpDefIdleTimeout,
              natIcmpDefIdleTimeout,
              natOtherDefIdleTimeout,
              natTcpDefIdleTimeout,
              natTcpDefNegTimeout,
              natNotifThrottlingInterval }
    STATUS current
    DESCRIPTION
            "A collection of configuration-related information
             required to support management of devices supporting
             NAT."
    ::= { natMIBGroups 1 }
natTranslationGroup OBJECT-GROUP
    OBJECTS { natAddrBindNumberOfEntries,
              natAddrBindGlobalAddrType,
              natAddrBindGlobalAddr,
              natAddrBindId,
              natAddrBindTranslationEntity,
              natAddrBindType,
              natAddrBindMapIndex,
              natAddrBindSessions,
              natAddrBindMaxIdleTime,
              natAddrBindCurrentIdleTime,
              natAddrBindInTranslates,
              natAddrBindOutTranslates,
              natAddrPortBindNumberOfEntries,
              natAddrPortBindGlobalAddrType,
              natAddrPortBindGlobalAddr,
              natAddrPortBindGlobalPort,
              natAddrPortBindId,
              natAddrPortBindTranslationEntity,
```

Rohit, et al. Standards Track [Page 49]

```
natAddrPortBindType,
              natAddrPortBindMapIndex,
              natAddrPortBindSessions,
              natAddrPortBindMaxIdleTime,
              natAddrPortBindCurrentIdleTime,
              natAddrPortBindInTranslates,
              natAddrPortBindOutTranslates,
              natSessionPrivateSrcEPBindId,
              natSessionPrivateSrcEPBindMode,
              natSessionPrivateDstEPBindId,
              natSessionPrivateDstEPBindMode,
              natSessionDirection,
              natSessionUpTime,
              natSessionAddrMapIndex,
              natSessionProtocolType,
              natSessionPrivateAddrType,
              natSessionPrivateSrcAddr.
              natSessionPrivateSrcPort,
              natSessionPrivateDstAddr,
              natSessionPrivateDstPort,
              natSessionPublicAddrType,
              natSessionPublicSrcAddr,
              natSessionPublicSrcPort,
              natSessionPublicDstAddr,
              natSessionPublicDstPort,
              natSessionMaxIdleTime,
              natSessionCurrentIdleTime,
              natSessionInTranslates,
              natSessionOutTranslates }
    STATUS current
    DESCRIPTION
            "A collection of BIND-related objects required to support
             management of devices supporting NAT."
    ::= { natMIBGroups 2 }
natStatsInterfaceGroup OBJECT-GROUP
    OBJECTS { natInterfaceInTranslates,
              natInterfaceOutTranslates,
              natInterfaceDiscards }
    STATUS current
    DESCRIPTION
            "A collection of NAT statistics associated with the
             interface on which NAT is configured, to aid
             troubleshooting/monitoring of the NAT operation."
    ::= { natMIBGroups 3 }
natStatsProtocolGroup OBJECT-GROUP
```

Rohit, et al. Standards Track [Page 50]

```
OBJECTS { natProtocolInTranslates,
             natProtocolOutTranslates,
             natProtocolDiscards }
    STATUS current
    DESCRIPTION
            "A collection of protocol specific NAT statistics,
             to aid troubleshooting/monitoring of NAT operation."
    ::= { natMIBGroups 4 }
natStatsAddrMapGroup OBJECT-GROUP
    OBJECTS { natAddrMapInTranslates,
              natAddrMapOutTranslates,
              natAddrMapDiscards,
             natAddrMapAddrUsed }
    STATUS current
    DESCRIPTION
            "A collection of address map specific NAT statistics,
             to aid troubleshooting/monitoring of NAT operation."
    ::= { natMIBGroups 5 }
natMIBNotificationGroup NOTIFICATION-GROUP
    NOTIFICATIONS { natPacketDiscard }
    STATUS
             current
    DESCRIPTION
            "A collection of notifications generated by
            devices supporting this MIB."
    ::= { natMIBGroups 6 }
-- Compliance statements
natMIBFullCompliance MODULE-COMPLIANCE
    STATUS current
    DESCRIPTION
            "When this MIB is implemented with support for
             read-create, then such an implementation can claim
             full compliance. Such devices can then be both
             monitored and configured with this MIB.
             The following index objects cannot be added as OBJECT
             clauses but nevertheless have the compliance
             requirements:
             -- OBJECT natAddrBindLocalAddrType
             -- SYNTAX InetAddressType { ipv4(1), ipv6(2) }
             -- DESCRIPTION
                        "An implementation is required to support
```

```
global IPv4 and/or IPv6 addresses, depending
                    on its support for IPv4 and IPv6."
         -- OBJECT natAddrBindLocalAddr
         -- SYNTAX InetAddress (SIZE(4|16))
         -- DESCRIPTION
                   "An implementation is required to support
                    global IPv4 and/or IPv6 addresses, depending
                    on its support for IPv4 and IPv6."
        -- OBJECT natAddrPortBindLocalAddrType
         -- SYNTAX InetAddressType { ipv4(1), ipv6(2) }
        -- DESCRIPTION
                   "An implementation is required to support
                    global IPv4 and/or IPv6 addresses, depending
                    on its support for IPv4 and IPv6."
         -- OBJECT natAddrPortBindLocalAddr
        -- SYNTAX InetAddress (SIZE(4|16))
         -- DESCRIPTION
                   "An implementation is required to support
                    global IPv4 and/or IPv6 addresses, depending
                    on its support for IPv4 and IPv6."
MODULE IF-MIB -- The interfaces MIB, RFC2863
 MANDATORY-GROUPS {
   ifCounterDiscontinuityGroup
MODULE -- this module
 MANDATORY-GROUPS { natConfigGroup, natTranslationGroup,
                    natStatsInterfaceGroup }
  GROUP
            natStatsProtocolGroup
  DESCRIPTION
         "This group is optional."
          natStatsAddrMapGroup
  GROUP
  DESCRIPTION
          "This group is optional."
  GROUP
           natMIBNotificationGroup
  DESCRIPTION
           "This group is optional."
  OBJECT natAddrMapLocalAddrType
  SYNTAX InetAddressType { ipv4(1), ipv6(2) }
  DESCRIPTION
          "An implementation is required to support global IPv4
          and/or IPv6 addresses, depending on its support
```

Rohit, et al. Standards Track [Page 52]

for IPv4 and IPv6."

OBJECT natAddrMapLocalAddrFrom SYNTAX InetAddress (SIZE(4|16))

DESCRIPTION

"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrMapLocalAddrTo SYNTAX InetAddress (SIZE(4|16))

DESCRIPTION

"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6." $\,$

OBJECT natAddrMapGlobalAddrType

SYNTAX InetAddressType { ipv4(1), ipv6(2) }

DESCRIPTION

"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrMapGlobalAddrFrom
SYNTAX InetAddress (SIZE(4|16))

DESCRIPTION

"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrMapGlobalAddrTo SYNTAX InetAddress (SIZE(4|16))

DESCRIPTION

"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrBindGlobalAddrType

SYNTAX InetAddressType { ipv4(1), ipv6(2) }

DESCRIPTION

"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

 ${\tt OBJECT} \quad {\tt natAddrBindGlobalAddr}$

SYNTAX InetAddress (SIZE(4|16))

DESCRIPTION

"An implementation is required to support global IPv4

Rohit, et al. Standards Track [Page 53]

```
and/or IPv6 addresses, depending on its support
         for IPv4 and IPv6."
OBJECT natAddrPortBindGlobalAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
        "An implementation is required to support global IPv4
         and/or IPv6 addresses, depending on its support
         for IPv4 and IPv6."
OBJECT natAddrPortBindGlobalAddr
SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION
        "An implementation is required to support global IPv4
         and/or IPv6 addresses, depending on its support
         for IPv4 and IPv6."
OBJECT natSessionPrivateAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
        "An implementation is required to support global IPv4
         and/or IPv6 addresses, depending on its support
         for IPv4 and IPv6."
{\tt OBJECT} \quad {\tt natSessionPrivateSrcAddr}
SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION
        "An implementation is required to support global IPv4
         and/or IPv6 addresses, depending on its support
         for IPv4 and IPv6."
{\tt OBJECT} \quad {\tt natSessionPrivateDstAddr}
SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION
        "An implementation is required to support global IPv4
         and/or IPv6 addresses, depending on its support
         for IPv4 and IPv6."
OBJECT natSessionPublicAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
        "An implementation is required to support global IPv4
         and/or IPv6 addresses, depending on its support
         for IPv4 and IPv6."
OBJECT natSessionPublicSrcAddr
SYNTAX InetAddress (SIZE(4|16))
```

DESCRIPTION "An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6." OBJECT natSessionPublicDstAddr SYNTAX InetAddress (SIZE(4|16)) DESCRIPTION "An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6." ::= { natMIBCompliances 1 } natMIBReadOnlyCompliance MODULE-COMPLIANCE STATUS current DESCRIPTION "When this MIB is implemented without support for read-create (i.e., in read-only mode), then such an implementation can claim read-only compliance. Such a device can then be monitored but cannot be configured with this MIB. The following index objects cannot be added as OBJECT clauses but nevertheless have the compliance requirements: -- OBJECT natAddrBindLocalAddrType -- SYNTAX InetAddressType { ipv4(1), ipv6(2) } -- DESCRIPTION "An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6." -- OBJECT natAddrBindLocalAddr -- SYNTAX InetAddress (SIZE(4|16)) -- DESCRIPTION "An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6." -- OBJECT natAddrPortBindLocalAddrType -- SYNTAX InetAddressType { ipv4(1), ipv6(2) } -- DESCRIPTION "An implementation is required to support

global IPv4 and/or IPv6 addresses, depending

on its support for IPv4 and IPv6."

```
-- OBJECT natAddrPortBindLocalAddr
         -- SYNTAX InetAddress (SIZE(4|16))
         -- DESCRIPTION
                   "An implementation is required to support
                    global IPv4 and/or IPv6 addresses, depending
                    on its support for IPv4 and IPv6."
MODULE IF-MIB -- The interfaces MIB, RFC2863
  MANDATORY-GROUPS {
    ifCounterDiscontinuityGroup
MODULE -- this module
  MANDATORY-GROUPS { natConfigGroup, natTranslationGroup,
                     natStatsInterfaceGroup }
  GROUP
            natStatsProtocolGroup
  DESCRIPTION
         "This group is optional."
          natStatsAddrMapGroup
  DESCRIPTION
          "This group is optional."
  GROUP natMIBNotificationGroup
  DESCRIPTION
          "This group is optional."
  OBJECT natInterfaceRowStatus
  SYNTAX RowStatus { active(1) }
  MIN-ACCESS
             read-only
  DESCRIPTION
          "Write access is not required, and active is the only
          status that needs to be supported."
  {\tt OBJECT} \quad {\tt natAddrMapLocalAddrType}
  SYNTAX InetAddressType { ipv4(1), ipv6(2) }
  MIN-ACCESS
             read-only
  DESCRIPTION
          "Write access is not required. An implementation is
           required to support global IPv4 and/or IPv6 addresses,
           depending on its support for IPv4 and IPv6."
  OBJECT natAddrMapLocalAddrFrom
  SYNTAX InetAddress (SIZE(4|16))
  MIN-ACCESS
             read-only
  DESCRIPTION
          "Write access is not required. An implementation is
           required to support global IPv4 and/or IPv6 addresses,
           depending on its support for IPv4 and IPv6."
```

Rohit, et al. Standards Track [Page 56]

```
OBJECT natAddrMapLocalAddrTo
SYNTAX InetAddress (SIZE(4|16))
MIN-ACCESS read-only
DESCRIPTION
        "Write access is not required. An implementation is
         required to support global IPv4 and/or IPv6 addresses,
         depending on its support for IPv4 and IPv6."
OBJECT natAddrMapGlobalAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
MIN-ACCESS read-only
DESCRIPTION
        "Write access is not required. An implementation is
        required to support global IPv4 and/or IPv6 addresses,
         depending on its support for IPv4 and IPv6."
{\tt OBJECT} \quad {\tt natAddrMapGlobalAddrFrom}
SYNTAX InetAddress (SIZE(4|16))
MIN-ACCESS read-only
DESCRIPTION
        "Write access is not required. An implementation is
        required to support global IPv4 and/or IPv6 addresses,
         depending on its support for IPv4 and IPv6."
OBJECT natAddrMapGlobalAddrTo
SYNTAX InetAddress (SIZE(4|16))
MIN-ACCESS
           read-only
DESCRIPTION
        "Write access is not required. An implementation is
         required to support global IPv4 and/or IPv6 addresses,
         depending on its support for IPv4 and IPv6."
OBJECT natAddrMapRowStatus
SYNTAX RowStatus { active(1) }
MIN-ACCESS
           read-only
DESCRIPTION
        "Write access is not required, and active is the only
        status that needs to be supported."
OBJECT natAddrBindGlobalAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION
        "An implementation is required to support global IPv4
         and/or IPv6 addresses, depending on its support for
         IPv4 and IPv6."
OBJECT natAddrBindGlobalAddr
SYNTAX InetAddress (SIZE(4|16))
```

DESCRIPTION

"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrPortBindGlobalAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION

"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natAddrPortBindGlobalAddr SYNTAX InetAddress (SIZE(4|16)) DESCRIPTION

"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natSessionPrivateAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION

OBJECT natSessionPrivateSrcAddr SYNTAX InetAddress (SIZE(4|16)) DESCRIPTION

"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6." $\,$

OBJECT natSessionPrivateDstAddr SYNTAX InetAddress (SIZE(4|16)) DESCRIPTION

"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natSessionPublicAddrType
SYNTAX InetAddressType { ipv4(1), ipv6(2) }
DESCRIPTION

"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natSessionPublicSrcAddr

Rohit, et al. Standards Track [Page 58]

SYNTAX InetAddress (SIZE(4|16))
DESCRIPTION

"An implementation is required to support global IPv4 and/or IPv6 addresses, depending on its support for IPv4 and IPv6."

OBJECT natSessionPublicDstAddr SYNTAX InetAddress (SIZE(4|16)) DESCRIPTION

::= { natMIBCompliances 2 }

END

6. Acknowledgements

The authors of the document would like to thank Randy Turner, Ashwini S.T., Kevin Luehrs, Sam Sankoorikal, and Juergen Quittek for their valuable feedback.

The authors would like to especially thank Juergen Schoenwaelder for his patient and fine-combed review and detailed comments as a MIB doctor. The NAT MIB is much clearer and flatter as a result of Juergen's suggestions.

7. Security Considerations

It is clear that this MIB can potentially be useful for configuration. Unauthorized access to the write-able objects could cause a denial of service and/or widespread network disturbance. Hence, the support for SET operations in a non-secure environment without proper protection can have a negative effect on network operations.

At this writing, no security holes have been identified beyond those that SNMP Security is itself intended to address. These relate primarily to controlled access to sensitive information and the ability to configure a device - or which might result from operator error, which is beyond the scope of any security architecture.

There are a number of managed objects in this MIB that may contain information that may be sensitive from a business perspective, in that they may represent NAT bind and session information. The NAT bind and session objects reveal the identity of private hosts that are engaged in a session with external end nodes. A curious outsider

Rohit, et al. Standards Track [Page 59]

could monitor these two objects to assess the number of private hosts being supported by the NAT device. Further, a disgruntled former employee of an enterprise could use the NAT bind and session information to break into specific private hosts by intercepting the existing sessions or originating new sessions into the host. There are no objects that are sensitive in their own right, such as passwords or monetary amounts. It may even be important to control GET access to these objects and possibly to encrypt the values of these objects when they are sent over the network via SNMP. Not all versions of SNMP provide features for such a secure environment.

SNMP versions prior to SNMPv3 did not include adequate security. Even if the network itself is secure (for example by using IPSec), even then, there is no control as to who on the secure network is allowed to access and GET/SET (read/change/create/delete) the objects in this MIB.

It is recommended that the implementers consider the security features as provided by the SNMPv3 framework (see [RFC3410], section 8), including full support for the SNMPv3 cryptographic mechanisms (for authentication and privacy).

Further, deployment of SNMP versions prior to SNMPv3 is NOT RECOMMENDED. Instead, it is RECOMMENDED to deploy SNMPv3 and to enable cryptographic security. It is then a customer/operator responsibility to ensure that the SNMP entity giving access to an instance of this MIB module is properly configured to give access to the objects only to those principals (users) that have legitimate rights to indeed GET or SET (change/create/delete) them.

8. References

8.1. Normative References

- [RFC2579] McCloghrie, K., Perkins, D., and J. Schoenwaelder, "Textual Conventions for SMIv2", STD 58, RFC 2579, April 1999.
- [RFC3022] Srisuresh, P. and K. Egevang, "Traditional IP Network Address Translator (Traditional NAT)", RFC 3022, January 2001.

Rohit, et al. Standards Track [Page 60]

- [RFC2663] Srisuresh, P. and M. Holdrege, "IP Network Address Translator (NAT) Terminology and Considerations", RFC 2663, August 1999.
- [RFC4001] Daniele, M., Haberman, B., Routhier, S., Schoenwaelder, J., "Textual Conventions for Internet Network Addresses", RFC 4001, February 2005.
- [RFC792] Postel, J., "Internet Control Message Protocol", STD 5, RFC 792, September 1981.
- [RFC3489] Rosenberg, J., Weinberger, J., Huitema, C., and R. Mahy,
 "STUN Simple Traversal of User Datagram Protocol (UDP)
 Through Network Address Translators (NATs)", RFC 3489,
 March 2003.
- [RFC2863] McCloghrie, K. and F. Kastenholz, "The Interfaces Group MIB", RFC 2863, June 2000.
- [RFC2463] Conta, A. and S. Deering, "Internet Control Message Protocol (ICMPv6) for the Internet Protocol Version 6 (IPv6) Specification", RFC 2463, December 1998.
- [RFC3411] Harrington, D., Presuhn, R., and B. Wijnen, "An
 Architecture for Describing Simple Network Management
 Protocol (SNMP) Management Frameworks", STD 62, RFC 3411,
 December 2002.
- [RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997.
- [RFC3413] Levi, D., Meyer, P., and B. Stewart, "Simple Network Management Protocol (SNMP) Applications", STD 62, RFC 3413, December 2002.

8.2. Informative References

- [RFC1918] Rekhter, Y., Moskowitz, B., Karrenberg, D., de Groot, G.,
 and E. Lear, "Address Allocation for Private Internets",
 BCP 5, RFC 1918, February 1996.
- [RFC3410] Case, J., Mundy, R., Partain, D., and B. Stewart,
 "Introduction and Applicability Statements for InternetStandard Management Framework", RFC 3410, December 2002.

Rohit, et al. Standards Track [Page 61]

Authors' Addresses

R. Rohit Mascon Global Limited #59/2 100 ft Ring Road Banashankari II Stage Bangalore 560 070 India

Phone: +91 80 679 6227 EMail: rrohit74@hotmail.com

P. Srisuresh Caymas Systems, Inc. 1179-A North McDowell Blvd. Petaluma, CA 94954

Phone: (707) 283-5063 EMail: srisuresh@yahoo.com

Rajiv Raghunarayan Cisco Systems Inc. 170 West Tasman Drive San Jose, CA 95134

Phone: +1 408 853 9612 EMail: raraghun@cisco.com

Nalinaksh Pai Cisco Systems, Inc. Prestige Waterford No. 9, Brunton Road Bangalore - 560 025 India

Phone: +91 80 532 1300 extn. 6354

EMail: npai@cisco.com

Cliff Wang Information Security Bank One Corp 1111 Polaris Pkwy Columbus, OH 43240

Phone: +1 614 213 6117

EMail: cliffwang2000@yahoo.com

Rohit, et al. Standards Track [Page 63]

Full Copyright Statement

Copyright (C) The Internet Society (2005).

This document is subject to the rights, licenses and restrictions contained in BCP 78, and except as set forth therein, the authors retain all their rights.

This document and the information contained herein are provided on an "AS IS" basis and THE CONTRIBUTOR, THE ORGANIZATION HE/SHE REPRESENTS OR IS SPONSORED BY (IF ANY), THE INTERNET SOCIETY AND THE INTERNET ENGINEERING TASK FORCE DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Intellectual Property

The IETF takes no position regarding the validity or scope of any Intellectual Property Rights or other rights that might be claimed to pertain to the implementation or use of the technology described in this document or the extent to which any license under such rights might or might not be available; nor does it represent that it has made any independent effort to identify any such rights. Information on the procedures with respect to rights in RFC documents can be found in BCP 78 and BCP 79.

Copies of IPR disclosures made to the IETF Secretariat and any assurances of licenses to be made available, or the result of an attempt made to obtain a general license or permission for the use of such proprietary rights by implementers or users of this specification can be obtained from the IETF on-line IPR repository at http://www.ietf.org/ipr.

The IETF invites any interested party to bring to its attention any copyrights, patents or patent applications, or other proprietary rights that may cover technology that may be required to implement this standard. Please address the information to the IETF at ietf-ipr@ietf.org.

Acknowledgement

Funding for the RFC Editor function is currently provided by the Internet Society.

Rohit, et al. Standards Track [Page 64]