Network Working Group Request for Comments: 4750

Obsoletes: 1850

Category: Standards Track

D. Joyal, Ed.
Nortel
P. Galecki, Ed.
Airvana
S. Giacalone, Ed.
CSFB
Original Authors:
R. Coltun
Touch Acoustra
F. Baker
Cisco Systems
December 2006

OSPF Version 2 Management Information Base

Status of This Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

Copyright Notice

Copyright (C) The IETF Trust (2006).

Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in TCP/IP-based internets. In particular, it defines objects for managing version 2 of the Open Shortest Path First Routing Protocol. Version 2 of the OSPF protocol is specific to the IPv4 address family. Version 3 of the OSPF protocol is specific to the IPv6 address family.

This memo obsoletes RFC 1850; however, it is designed to be backwards compatible. The functional differences between this memo and RFC 1850 are explained in Appendix B.

Table of Contents

1.	Overview
	1.1. The Internet-Standard Management Framework
	1.2. Conceptual Row Creation3
	1.3. Default Configuration4
	1.4. OSPF Counters5
	1.5. Multiple OSPF Instances5
	1.6. Conventions
2.	Structure of This MIB6
	2.1. The Purposes of the Sections in This MIB6
	2.1.1. General Variables6
	2.1.2. Area Data Structure and Area Stub Metric Table6
	2.1.3. Link State Database and External Link State
	Database7
	2.1.4. Address Table and Host Tables7
	2.1.5. Interface and Interface Metric Tables7
	2.1.6. Virtual Interface Table7
	2.1.7. Neighbor and Virtual Neighbor Tables7
	2.1.8. Local Link State Database Table and Virtual
	Local Link State Database Table7
	2.1.9. AS-scope Link State Database Table7
	2.1.10. Area LSA Count Table7
	OSPF MIB Module8
4.	OSPF Trap Overview94
	4.1. Introduction94
	4.2. Approach95
	4.3. Ignoring Initial Activity95
	4.4. Throttling Traps95
	4.5. One Trap Per OSPF Event96
	4.6. Polling Event Counters96
	4.7. Translating Notification Parameters97
_	4.8. Historical Artifacts
	OSPF Trap Definitions98
6.	
7.	
	Acknowledgements
9.	References
	9.1. Normative References
_	9.2. Informative References
	pendix A. TOS Support
Ap]	pendix B. Changes from RFC 1850
	B.1. General Group Changes
	B.2. OSPF NSSA Enhancement Support
	B.3. Opaque LSA Support
	B.4. Graceful Restart Support
	B.5. OSPF Compliances
	B.6. OSPF Authentication and Security117

B.7.	OSPF Trap MIB	 .117
B.8.	Miscellaneous	 .118

1. Overview

1.1. The Internet-Standard Management Framework

For a detailed overview of the documents that describe the current Internet-Standard Management Framework, please refer to section 7 of RFC 3410 [RFC3410].

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. MIB objects are generally accessed through the Simple Network Management Protocol (SNMP). Objects in the MIB are defined using the mechanisms defined in the Structure of Management Information (SMI). This memo specifies a MIB module that is compliant to the SMIv2, which is described in STD 58, RFC 2578 [RFC2578], STD 58, RFC 2579 [RFC2579] and STD 58, RFC 2580 [RFC2580].

1.2. Conceptual Row Creation

For the benefit of row-creation in "conceptual" tables, DEFVAL (Default Value) clauses are included in the definitions in section 3, suggesting values that an agent should use for instances of variables that need to be created due to a Set-Request, but that are not specified in the Set-Request. DEFVAL clauses have not been specified for some objects that are read-only, implying that they are zeroed upon row creation. These objects are of the SYNTAX Counter32 or Gauge32.

For those objects not having a DEFVAL clause, both management stations and agents should heed the Robustness Principle of the Internet (see [RFC791]):

"be liberal in what you accept, conservative in what you send"

Therefore, management stations should include as many of these columnar objects as possible (e.g., all read-write objects) in a Set-Request when creating a conceptual row. Agents should accept a Set-Request with as few of these columnar objects as they need (e.g., the minimum contents of a "row-creating" SET consists of those objects for which, as they cannot be intuited, no default is specified).

1.3. Default Configuration

OSPF is a powerful routing protocol, equipped with features to handle virtually any configuration requirement that might reasonably be found within an Autonomous System (AS). With this power comes a fair degree of complexity, which the sheer number of objects in the MIB will attest to. Care has therefore been taken, in constructing this MIB, to define default values for virtually every object, to minimize the amount of parameterization required in the typical case. That default configuration is as follows:

Given the following assumptions:

- IP has already been configured.
- The ifTable has already been configured.
- ifSpeed is estimated by the interface drivers.
- The OSPF process automatically discovers all IP interfaces and creates corresponding OSPF interfaces.
- The OSPF process automatically creates the areas required for the interfaces.

The simplest configuration of an OSPF process requires the following:

- The OSPF process be enabled.

This can be accomplished with a single SET:

ospfAdminStat := enabled.

The configured system will have the following attributes:

- The RouterID will be one of the IP addresses of the device.
- The device will be neither an Area Border Router nor an Autonomous System Border Router.
- Every IP interface, with or without an address, will be an OSPF interface.
- The AreaID of each interface will be 0.0.0.0, the backbone.
- Authentication will be disabled.

- All broadcast and point-to-point interfaces will be operational. Non-broadcast multi-access (NBMA) interfaces require the configuration of at least one neighbor.
- Timers on all direct interfaces will be:

Hello Interval: 10 seconds
Dead Timeout: 40 Seconds
Retransmission: 5 Seconds
Transit Delay: 1 Second
Poll Interval: 120 Seconds

- No direct links to hosts will be configured.
- No addresses will be summarized.
- Metrics, being a measure of bit duration, are unambiguous and intelligent.
- No virtual links will be configured.

1.4. OSPF Counters

This MIB defines several counters, namely:

- ospfOriginateNewLsas, ospfRxNewLsas in the ospfGeneralGroup
- ospfSpfRuns, ospfAreaNssaTranslatorEvents in the ospfAreaTable
- ospfIfEvents in the ospfIfTable
- ospfVirtIfEvents in the ospfVirtIfTable
- ospfNbrEvents in the ospfNbrTable
- ospfVirtNbrEvents in the ospfVirtNbrTable

As a best practice, a management entity, when reading these counters, should use the discontinuity object, ospfDiscontinuityTime, to determine if an event that would invalidate the management entity understanding of the counters has occurred. A restart of the OSPF routing process is a possible example of a discontinuity event.

1.5. Multiple OSPF Instances

SNMPv3 supports "Contexts" that can be used to implement MIB views on multiple OSPF instances on the same system. See [RFC3411] or its successors for details.

1.6. Conventions

The key words "MUST", "MUST NOT", "REQUIRED", "SHALL", "SHALL NOT", "SHOULD", "SHOULD NOT", "RECOMMENDED", "MAY", and "OPTIONAL" in this document are to be interpreted as described in RFC 2119 [RFC2119].

2. Structure of This MIB

This MIB is composed of the following sections:

General Variables
Area Data Structure
Area Stub Metric Table
Link State Database (LSDB)
Address Range Table
Host Table
Interface Table
Interface Metric Table
Virtual Interface Table
Neighbor Table
Virtual Neighbor Table
External Link State Database
Aggregate Range Table
Local Link State Database
AS-scope Link State Database

It supports the base OSPFv2 specification [RFC2328] and extensions to OSPFv2 such as [RFC1765], [RFC1793], [RFC2370], [RFC3101] and [RFC3623].

There exists a separate MIB for notifications ("traps"), which is entirely optional.

2.1. The Purposes of the Sections in This MIB

2.1.1. General Variables

The general variables describe (as it may seem from the name) variables that are global to the OSPF Process.

2.1.2. Area Data Structure and Area Stub Metric Table

The Area Data Structure describes all of the OSPF Areas that the router participates in. The Area Table includes data for Not-So-Stubby-Area (NSSA) translation.

The Area Stub Metric Table describes the metrics advertised into a stub area by the default router(s).

Galecki, et al.

Standards Track

2.1.3. Link State Database and External Link State Database

The link state database is provided primarily to provide detailed information for network debugging.

2.1.4. Address Table and Host Tables

The Address Range Table and Host Table are provided to view configured Network Summary and host route information.

2.1.5. Interface and Interface Metric Tables

The Interface Table and the Interface Metric Table together describe the various IP interfaces to OSPF. The metrics are placed in separate tables in order to simplify dealing with multiple types of service. The Interface table includes link-local (Opaque type-9) link state advertisement (LSA) statistics.

2.1.6. Virtual Interface Table

The Virtual Interface Table describes virtual links to the OSPF Process, similarly to the (non-virtual) Interface Tables. This Table includes link-local (Opaque type-9) LSA statistics.

2.1.7. Neighbor and Virtual Neighbor Tables

The Neighbor Table and the Virtual Neighbor Table describe the neighbors to the OSPF Process.

2.1.8. Local Link State Database Table and Virtual Local Link State Database Table

The Local Link State Database Table and Virtual Local Link State Database Table are identical to the OSPF LSDB Table in format, but contain only link-local (Opaque type-9) link state advertisements for non-virtual and virtual links.

2.1.9. AS-scope Link State Database Table

The AS-scope Link State Database Table is identical to the OSPF LSDB Table in format, but contains only AS-scoped link state advertisements.

2.1.10. Area LSA Count Table

The table, which maintains number of link state advertisements on the per-area, per-LSA-type basis.

Galecki, et al.

Standards Track

3. OSPF MIB Module

OSPF-MIB DEFINITIONS ::= BEGIN

IMPORTS

MODULE-IDENTITY, OBJECT-TYPE, Counter32, Gauge32,

Integer32, Unsigned32, IpAddress, mib-2

FROM SNMPv2-SMI

TEXTUAL-CONVENTION, TruthValue, RowStatus, TimeStamp

FROM SNMPv2-TC

MODULE-COMPLIANCE, OBJECT-GROUP

FROM SNMPv2-CONF

InterfaceIndexOrZero

FROM IF-MIB;

ospf MODULE-IDENTITY

LAST-UPDATED "200611100000Z" -- November 10, 2006 00:00:00 EST

ORGANIZATION "IETF OSPF Working Group"

CONTACT-INFO

"WG E-Mail: ospf@ietf.org

WG Chairs: acee@cisco.com

rohit@gmail.com

Editors: Dan Joyal

Nortel

600 Technology Park Drive Billerica, MA 01821 djoyal@nortel.com

Piotr Galecki

Airvana

19 Alpha Road

Chelmsford, MA 01824 pgalecki@airvana.com

Spencer Giacalone

CSFB

Eleven Madison Ave New York, NY 10010-3629 spencer.giacalone@gmail.com"

DESCRIPTION

"The MIB module to describe the OSPF Version 2 Protocol. Note that some objects in this MIB module may pose a significant security risk. Refer to the Security Considerations section in RFC 4750 for more information.

Copyright (C) The IETF Trust (2006).

```
This version of this MIB module is part of
          RFC 4750; see the RFC itself for full legal
          notices."
       REVISION "200611100000Z" -- November 10, 2006 09:00:00 EST
       DESCRIPTION
         "Updated for latest changes to OSPF Version 2:
          - updated the General Group with the new
            ospfRFC1583Compatibility, ospfReferenceBandwidth
            and ospfDiscontinuityTime objects
          - added graceful-restart-related objects
          - added stub-router-related objects
          - updated the Area Table with NSSA-related objects

    added ospfAreaAggregateExtRouteTag object

          - added Opaque LSA-related objects
          - updates to the Compliances and Security sections
          - added area LSA counter table
          - added section describing translation of notification
           parameters between SNMP versions
          - added ospfComplianceObsolete to contain obsolete
           object groups

    deprecated ospfExtLsdbTable

          See Appendix B of RFC 4750 for more details.
          This version published as part of RFC 4750"
       REVISION "199501201225Z" -- Fri Jan 20 12:25:50 PST 1995
       DESCRIPTION
          "The initial SMIv2 revision of this MIB module, published
         in RFC 1850."
       ::= \{ mib-2 14 \}
AreaID ::= TEXTUAL-CONVENTION
       STATUS current
       DESCRIPTION
          "An OSPF Area Identifier.
          Note that the Area ID, in OSPF, has the same format
           as an IP address, but has the function of defining
           a summarization point for link state advertisements."
       SYNTAX
                   IpAddress
RouterID ::= TEXTUAL-CONVENTION
       STATUS
               current
       DESCRIPTION
          "A OSPF Router Identifier.
          Note that the Router ID, in OSPF, has the same format
          as an IP address, but identifies the router independent
```

```
of its IP address."
      SYNTAX IpAddress
Metric ::= TEXTUAL-CONVENTION
      DISPLAY-HINT "d-0"
      STATUS
               current
      DESCRIPTION
          "The OSPF internal metric.
          Note that the OSPF metric is defined as an unsigned value
          in the range."
      SYNTAX Integer32 (0..'FFFF'h)
BigMetric ::= TEXTUAL-CONVENTION
      DISPLAY-HINT "d-0"
      STATUS
              current
      DESCRIPTION
         "The OSPF external metric."
      SYNTAX
                  Integer32 (0..'FFFFFF'h)
Status ::= TEXTUAL-CONVENTION
      STATUS
                   current
      DESCRIPTION
         "An indication of the operability of an OSPF
         function or feature. For example, the status
         of an interface: 'enabled' indicates that
         it is willing to communicate with other OSPF routers,
         and 'disabled' indicates that it is not."
      SYNTAX
                   INTEGER { enabled (1), disabled (2) }
PositiveInteger ::= TEXTUAL-CONVENTION
      DISPLAY-HINT "d-0"
      STATUS
               current
      DESCRIPTION
         "A positive integer. Values in excess are precluded as
         unnecessary and prone to interoperability issues."
      SYNTAX Integer32 (0...'7FFFFFFF'h)
HelloRange ::= TEXTUAL-CONVENTION
      DISPLAY-HINT "d-0"
      STATUS
               current
      DESCRIPTION
         "The range of intervals in seconds on which Hello messages
         are exchanged."
      SYNTAX
               Integer32 (1..'FFFF'h)
UpToMaxAge ::= TEXTUAL-CONVENTION
      DISPLAY-HINT "d-0"
      STATUS
                  current
```

DESCRIPTION

"The values in seconds that one might find or configure for variables bounded by the maximum age of an LSA."

SYNTAX Integer32 (0...3600)

DesignatedRouterPriority ::= TEXTUAL-CONVENTION

DISPLAY-HINT "d-0" STATUS current

DESCRIPTION

"The range of values defined for the priority of a system for becoming the designated router."


SYNTAX Integer32 (0..'FF'h)

TOSType ::= TEXTUAL-CONVENTION

DISPLAY-HINT "d-0"
STATUS current
DESCRIPTION

"Type of Service (TOS) is defined as a mapping to the IP Type of Service Flags as defined in the IP Forwarding

Table MIB



IP TOS							IP TOS					
Field		Policy			Field			Policy				
Contents			С	ode	Contents				Code			
0	0	0	0	==>	0		0	0	0	1	==>	2
0	0	1	0	==>	4		0	0	1	1	==>	6
0	1	0	0	==>	8		0	1	0	1	==>	10
0	1	1	0	==>	12		0	1	1	1	==>	14
1	0	0	0	==>	16		1	0	0	1	==>	18
1	0	1	0	==>	20		1	0	1	1	==>	22
1	1	0	0	==>	24		1	1	0	1	==>	26
1	1	1	0	==>	28		1	1	1	1	==>	30

The remaining values are left for future definition."

SYNTAX Integer32 (0..30)

OspfAuthenticationType ::= TEXTUAL-CONVENTION

STATUS current

DESCRIPTION

"The authentication type."

SYNTAX INTEGER {

Galecki, et al.

Standards Track

```
none (0),
                      simplePassword (1),
                      md5(2)
                      -- reserved for specification by IANA (> 2)
                   }
-- OSPF General Variables
       Note: These parameters apply globally to the Router's
       OSPF Process.
ospfGeneralGroup OBJECT IDENTIFIER ::= { ospf 1 }
 ospfRouterId OBJECT-TYPE
      SYNTAX
              RouterID
      MAX-ACCESS read-write
      STATUS
                   current
      DESCRIPTION
         "A 32-bit integer uniquely identifying the
         router in the Autonomous System.
         By convention, to ensure uniqueness, this
         should default to the value of one of the
         router's IP interface addresses.
         This object is persistent and when written
         the entity SHOULD save the change to non-volatile storage."
      REFERENCE
         "OSPF Version 2, C.1 Global parameters"
       ::= { ospfGeneralGroup 1 }
 ospfAdminStat OBJECT-TYPE
      SYNTAX
               Status
      MAX-ACCESS read-write
                   current
      DESCRIPTION
         "The administrative status of OSPF in the
         router. The value 'enabled' denotes that the
         OSPF Process is active on at least one interface;
         'disabled' disables it on all interfaces.
         This object is persistent and when written
         the entity SHOULD save the change to non-volatile storage."
       ::= { ospfGeneralGroup 2 }
 ospfVersionNumber OBJECT-TYPE
      SYNTAX INTEGER { version2 (2) }
      MAX-ACCESS read-only
      STATUS
                 current
```

```
DESCRIPTION
       "The current version number of the OSPF protocol is 2."
    REFERENCE
       "OSPF Version 2, Title"
    ::= { ospfGeneralGroup 3 }
ospfAreaBdrRtrStatus OBJECT-TYPE
    SYNTAX TruthValue
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "A flag to note whether this router is an Area
       Border Router."
    REFERENCE
       "OSPF Version 2, Section 3 Splitting the AS into
       Areas"
    ::= { ospfGeneralGroup 4 }
ospfASBdrRtrStatus OBJECT-TYPE
    SYNTAX TruthValue
    MAX-ACCESS read-write
    STATUS current
    DESCRIPTION
       "A flag to note whether this router is configured as
        an Autonomous System Border Router.
        This object is persistent and when written the
        entity SHOULD save the change to non-volatile storage."
    REFERENCE
       "OSPF Version 2, Section 3.3 Classification of
       routers"
    ::= { ospfGeneralGroup 5 }
ospfExternLsaCount OBJECT-TYPE
     SYNTAX Gauge32
     MAX-ACCESS read-only
     STATUS
                current
     DESCRIPTION
        "The number of external (LS type-5) link state
        advertisements in the link state database."
     REFERENCE
        "OSPF Version 2, Appendix A.4.5 AS external link
        advertisements"
      ::= { ospfGeneralGroup 6 }
ospfExternLsaCksumSum OBJECT-TYPE
     SYNTAX Integer32
     MAX-ACCESS read-only
```

```
STATUS
                 current
     DESCRIPTION
        "The 32-bit sum of the LS checksums of
        the external link state advertisements
        contained in the link state database. This sum
        can be used to determine if there has been a
        change in a router's link state database and
        to compare the link state database of two
        routers. The value should be treated as unsigned
        when comparing two sums of checksums."
      ::= { ospfGeneralGroup 7 }
ospfTOSSupport OBJECT-TYPE
    SYNTAX TruthValue
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
       "The router's support for type-of-service routing.
        This object is persistent and when written
        the entity SHOULD save the change to non-volatile
        storage."
    REFERENCE
       "OSPF Version 2, Appendix F.1.2 Optional TOS
       support"
     ::= { ospfGeneralGroup 8 }
ospfOriginateNewLsas OBJECT-TYPE
    SYNTAX Counter32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "The number of new link state advertisements
       that have been originated. This number is
       incremented each time the router originates a new
       LSA.
       Discontinuities in the value of this counter can
       occur at re-initialization of the management system,
       and at other times as indicated by the value of
       ospfDiscontinuityTime."
      ::= { ospfGeneralGroup 9 }
ospfRxNewLsas OBJECT-TYPE
    SYNTAX Counter32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
```

```
"The number of link state advertisements received
       that are determined to be new instantiations.
       This number does not include newer instantiations
       of self-originated link state advertisements.
       Discontinuities in the value of this counter can
       occur at re-initialization of the management system,
       and at other times as indicated by the value of
       ospfDiscontinuityTime."
     ::= { ospfGeneralGroup 10 }
ospfExtLsdbLimit OBJECT-TYPE
                Integer32 (-1..'7FFFFFFF'h)
    SYNTAX
    MAX-ACCESS read-write
    STATUS
                 current
    DESCRIPTION
        "The maximum number of non-default
       AS-external LSAs entries that can be stored in the
       link state database. If the value is -1, then
       there is no limit.
       When the number of non-default AS-external LSAs
       in a router's link state database reaches
       ospfExtLsdbLimit, the router enters
       overflow state. The router never holds more than
       ospfExtLsdbLimit non-default AS-external LSAs
       in its database. OspfExtLsdbLimit MUST be set
       identically in all routers attached to the OSPF
       backbone and/or any regular OSPF area (i.e.,
       OSPF stub areas and NSSAs are excluded).
       This object is persistent and when written
       the entity SHOULD save the change to non-volatile
       storage."
     DEFVAL \{-1\}
      ::= { ospfGeneralGroup 11 }
ospfMulticastExtensions OBJECT-TYPE
    SYNTAX Integer32
    MAX-ACCESS read-write
    STATUS
                current
    DESCRIPTION
        "A bit mask indicating whether the router is
       forwarding IP multicast (Class D) datagrams
       based on the algorithms defined in the
       multicast extensions to OSPF.
       Bit 0, if set, indicates that the router can
```

forward IP multicast datagrams in the router's directly attached areas (called intra-area multicast routing).

Bit 1, if set, indicates that the router can forward IP multicast datagrams between OSPF areas (called inter-area multicast routing).

Bit 2, if set, indicates that the router can forward IP multicast datagrams between Autonomous Systems (called inter-AS multicast routing).

Only certain combinations of bit settings are allowed, namely: 0 (no multicast forwarding is enabled), 1 (intra-area multicasting only), 3 (intra-area and inter-area multicasting), 5 (intra-area and inter-AS multicasting), and 7 (multicasting everywhere). By default, no multicast forwarding is enabled.

This object is persistent and when written the entity SHOULD save the change to non-volatile storage."

DEFVAL { 0 }

::= { ospfGeneralGroup 12 }

ospfExitOverflowInterval OBJECT-TYPE

SYNTAX PositiveInteger MAX-ACCESS read-write

MAX-ACCESS read-write STATUS current

DESCRIPTION

"The number of seconds that, after entering OverflowState, a router will attempt to leave OverflowState. This allows the router to again originate non-default AS-external LSAs. When set to 0, the router will not leave overflow state until restarted.

This object is persistent and when written the entity SHOULD save the change to non-volatile storage."

DEFVAL { 0 }

::= { ospfGeneralGroup 13 }

ospfDemandExtensions OBJECT-TYPE SYNTAX TruthValue

MAX-ACCESS read-write

```
STATUS
                 current
     DESCRIPTION
        "The router's support for demand routing.
         This object is persistent and when written
         the entity SHOULD save the change to non-volatile
         storage."
     REFERENCE
        "Extending OSPF to Support Demand Circuits"
      ::= { ospfGeneralGroup 14 }
ospfRFC1583Compatibility OBJECT-TYPE
     SYNTAX
             TruthValue
     MAX-ACCESS read-write
     STATUS
                 current
     DESCRIPTION
        "Indicates metrics used to choose among multiple
        AS-external LSAs. When RFC1583Compatibility is set to
        enabled, only cost will be used when choosing among
        multiple AS-external LSAs advertising the same
        destination. When RFC1583Compatibility is set to
        disabled, preference will be driven first by type of
        path using cost only to break ties.
        This object is persistent and when written
        the entity SHOULD save the change to non-volatile
        storage."
      REFERENCE
         "OSPF Version 2, Section 16.4.1 External path
          preferences"
       ::= { ospfGeneralGroup 15 }
ospfOpaqueLsaSupport OBJECT-TYPE
     SYNTAX TruthValue
     MAX-ACCESS read-only
     STATUS
                 current
     DESCRIPTION
        "The router's support for Opaque LSA types."
        "The OSPF Opaque LSA Option"
      ::= { ospfGeneralGroup 16 }
ospfReferenceBandwidth OBJECT-TYPE
     SYNTAX Unsigned32
     UNITS
                 "kilobits per second"
     MAX-ACCESS read-write
     STATUS current
     DESCRIPTION
        "Reference bandwidth in kilobits/second for
```

[Page 17]

```
calculating default interface metrics. The
       default value is 100,000 KBPS (100 MBPS).
       This object is persistent and when written
       the entity SHOULD save the change to non-volatile
        storage."
     ::= { ospfGeneralGroup 17 }
ospfRestartSupport OBJECT-TYPE
     SYNTAX
                 INTEGER { none (1),
                           plannedOnly (2),
                           plannedAndUnplanned (3)
    MAX-ACCESS
                 read-write
     STATUS
                 current
     DESCRIPTION
        "The router's support for OSPF graceful restart.
       Options include: no restart support, only planned
       restarts, or both planned and unplanned restarts.
       This object is persistent and when written
       the entity SHOULD save the change to non-volatile
        storage."
     ::= { ospfGeneralGroup 18 }
ospfRestartInterval OBJECT-TYPE
     SYNTAX Integer32 (1..1800)
    UNITS
                 "seconds"
    MAX-ACCESS read-write
     STATUS
                current
    DESCRIPTION
        "Configured OSPF graceful restart timeout interval.
        This object is persistent and when written
        the entity SHOULD save the change to non-volatile
        storage."
     ::= { ospfGeneralGroup 19 }
ospfRestartStrictLsaChecking OBJECT-TYPE
     SYNTAX TruthValue
    MAX-ACCESS
                read-write
     STATUS
                 current
    DESCRIPTION
        "Indicates if strict LSA checking is enabled for
        graceful restart.
        This object is persistent and when written
        the entity SHOULD save the change to non-volatile
```

```
storage."
    ::= { ospfGeneralGroup 20 }
ospfRestartStatus OBJECT-TYPE
    SYNTAX
                 INTEGER { notRestarting (1),
                           plannedRestart (2),
                           unplannedRestart (3)
    MAX-ACCESS
                 read-only
    STATUS current
    DESCRIPTION
       "Current status of OSPF graceful restart."
    ::= { ospfGeneralGroup 21 }
ospfRestartAge OBJECT-TYPE
    SYNTAX Unsigned32 UNITS "seconds"
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "Remaining time in current OSPF graceful restart
       interval."
     ::= { ospfGeneralGroup 22 }
ospfRestartExitReason OBJECT-TYPE
                 INTEGER { none (1),
                                              -- none attempted
    SYNTAX
                           inProgress (2),
                                              -- restart in
                                              -- progress
                           completed (3),
                                              -- successfully
                                              -- completed
                                              -- timed out
                           timedOut (4),
                           topologyChanged (5) -- aborted due to
                                              -- topology change.
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
       "Describes the outcome of the last attempt at a
       graceful restart. If the value is 'none', no restart
       has yet been attempted. If the value is 'inProgress',
       a restart attempt is currently underway."
     ::= { ospfGeneralGroup 23 }
ospfAsLsaCount OBJECT-TYPE
    SYNTAX Gauge32
    MAX-ACCESS read-only
    STATUS
               current
```

```
DESCRIPTION
        "The number of AS-scope link state
        advertisements in the AS-scope link state database."
     ::= { ospfGeneralGroup 24 }
ospfAsLsaCksumSum OBJECT-TYPE
    SYNTAX Unsigned32 MAX-ACCESS read-only
     STATUS current
    DESCRIPTION
        "The 32-bit unsigned sum of the LS checksums of
        the AS link state advertisements contained in the AS-scope
        link state database. This sum can be used to determine
        if there has been a change in a router's AS-scope link
        state database, and to compare the AS-scope link state
        database of two routers."
     ::= { ospfGeneralGroup 25 }
 ospfStubRouterSupport OBJECT-TYPE
     SYNTAX TruthValue
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
        "The router's support for stub router functionality."
    REFERENCE
        "OSPF Stub Router Advertisement"
     ::= { ospfGeneralGroup 26 }
 ospfStubRouterAdvertisement OBJECT-TYPE
            INTEGER {
    SYNTAX
                       doNotAdvertise (1),
                       advertise(2)
    MAX-ACCESS read-write
     STATUS
                 current
    DESCRIPTION
        "This object controls the advertisement of
        stub router LSAs by the router. The value
        doNotAdvertise will result in the advertisement
        of a standard router LSA and is the default value.
        This object is persistent and when written
        the entity SHOULD save the change to non-volatile
        storage."
     ::= { ospfGeneralGroup 27 }
ospfDiscontinuityTime OBJECT-TYPE
   SYNTAX TimeStamp
```

```
MAX-ACCESS read-only
     STATUS current
     DESCRIPTION
         "The value of sysUpTime on the most recent occasion
         at which any one of this MIB's counters suffered
         a discontinuity.
         If no such discontinuities have occurred since the last
         re-initialization of the local management subsystem,
         then this object contains a zero value."
      ::= { ospfGeneralGroup 28 }
-- OSPF Area Table
      The OSPF Area Table contains information
      regarding the various areas.
 ospfAreaTable OBJECT-TYPE
      SYNTAX SEQUENCE OF OspfAreaEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
         "Information describing the configured parameters and
         cumulative statistics of the router's attached areas.
         The interfaces and virtual links are configured
         as part of these areas. Area 0.0.0.0, by definition,
         is the backbone area."
      REFERENCE
         "OSPF Version 2, Section 6 The Area Data Structure"
      ::= { ospf 2 }
 ospfAreaEntry OBJECT-TYPE
      SYNTAX OspfAreaEntry
      MAX-ACCESS not-accessible
      STATUS
                  current
      DESCRIPTION
         "Information describing the configured parameters and
         cumulative statistics of one of the router's attached areas.
         The interfaces and virtual links are configured as part of
         these areas. Area 0.0.0.0, by definition, is the backbone
         area.
         Information in this table is persistent and when this object
         is written the entity SHOULD save the change to non-volatile
         storage."
      INDEX { ospfAreaId }
       ::= { ospfAreaTable 1 }
```

```
OspfAreaEntry ::=
      SEQUENCE {
         ospfAreaId
            AreaID,
         ospfAuthType
            OspfAuthenticationType,
         ospfImportAsExtern
            INTEGER,
         ospfSpfRuns
            Counter32,
         ospfAreaBdrRtrCount
            Gauge32,
         ospfAsBdrRtrCount
            Gauge32,
         ospfAreaLsaCount
            Gauge32,
         ospfAreaLsaCksumSum
            Integer32,
         ospfAreaSummary
            INTEGER,
         ospfAreaStatus
           RowStatus,
         ospfAreaNssaTranslatorRole
            INTEGER,
         ospfAreaNssaTranslatorState
            INTEGER,
         {\tt ospfAreaNssaTranslatorStabilityInterval}
            PositiveInteger,
         ospfAreaNssaTranslatorEvents
            Counter32
         }
ospfAreaId OBJECT-TYPE
             AreaID
     {\tt MAX-ACCESS} \qquad {\tt read-only} \ {\tt --} \ {\tt read-only} \ {\tt since} \ {\tt originally}
                            -- an SMIv1 index
     STATUS
                 current
     DESCRIPTION
        "A 32-bit integer uniquely identifying an area.
        Area ID 0.0.0.0 is used for the OSPF backbone."
     REFERENCE
        "OSPF Version 2, Appendix C.2 Area parameters"
     ::= { ospfAreaEntry 1 }
ospfAuthType OBJECT-TYPE
     SYNTAX OspfAuthenticationType
     MAX-ACCESS read-create
     STATUS
                 obsolete
```

```
DESCRIPTION
       "The authentication type specified for an area."
    REFERENCE
       "OSPF Version 2, Appendix D Authentication"
    DEFVAL { none } -- no authentication, by default
    ::= { ospfAreaEntry 2 }
ospfImportAsExtern OBJECT-TYPE
    SYNTAX INTEGER {
                  importExternal (1),
                   importNoExternal (2),
                   importNssa (3)
    MAX-ACCESS
               read-create
    STATUS
                 current
    DESCRIPTION
       "Indicates if an area is a stub area, NSSA, or standard
       area. Type-5 AS-external LSAs and type-11 Opaque LSAs are
       not imported into stub areas or NSSAs. NSSAs import
       AS-external data as type-7 LSAs"
       "OSPF Version 2, Appendix C.2 Area parameters"
    DEFVAL { importExternal }
    ::= { ospfAreaEntry 3 }
ospfSpfRuns OBJECT-TYPE
    SYNTAX Counter32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "The number of times that the intra-area route
       table has been calculated using this area's
       link state database. This is typically done
       using Dijkstra's algorithm.
       Discontinuities in the value of this counter can occur
       at re-initialization of the management system, and at other
       times as indicated by the value of ospfDiscontinuityTime."
     ::= { ospfAreaEntry 4 }
ospfAreaBdrRtrCount OBJECT-TYPE
    SYNTAX Gauge32
               read-only
    MAX-ACCESS
    STATUS current
    DESCRIPTION
       "The total number of Area Border Routers reachable
       within this area. This is initially zero and is
       calculated in each Shortest Path First (SPF) pass."
```

```
::= { ospfAreaEntry 5 }
ospfAsBdrRtrCount OBJECT-TYPE
    SYNTAX Gauge32
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
       "The total number of Autonomous System Border
       Routers reachable within this area. This is
       initially zero and is calculated in each SPF
       pass."
     ::= { ospfAreaEntry 6 }
ospfAreaLsaCount OBJECT-TYPE
    SYNTAX
                Gauge32
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
       "The total number of link state advertisements
       in this area's link state database, excluding
       AS-external LSAs."
     ::= { ospfAreaEntry 7 }
ospfAreaLsaCksumSum OBJECT-TYPE
    SYNTAX Integer32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "The 32-bit sum of the link state
       advertisements' LS checksums contained in this
       area's link state database. This sum excludes
       external (LS type-5) link state advertisements.
       The sum can be used to determine if there has
       been a change in a router's link state
       database, and to compare the link state database of
       two routers. The value should be treated as unsigned
       when comparing two sums of checksums."
    DEFVAL { 0 }
     ::= { ospfAreaEntry 8 }
ospfAreaSummary OBJECT-TYPE
                 INTEGER {
    SYNTAX
                    noAreaSummary (1),
                    sendAreaSummary (2)
    MAX-ACCESS
               read-create
    STATUS
                 current
    DESCRIPTION
```

```
"The variable ospfAreaSummary controls the
        import of summary LSAs into stub and NSSA areas.
       It has no effect on other areas.
       If it is noAreaSummary, the router will not
       originate summary LSAs into the stub or NSSA area.
       It will rely entirely on its default route.
       If it is sendAreaSummary, the router will both
       summarize and propagate summary LSAs."
    DEFVAL { noAreaSummary }
     ::= { ospfAreaEntry 9 }
ospfAreaStatus OBJECT-TYPE
    SYNTAX RowStatus
    MAX-ACCESS read-create
    STATUS
                 current
    DESCRIPTION
       "This object permits management of the table by
       facilitating actions such as row creation,
       construction, and destruction.
       The value of this object has no effect on
       whether other objects in this conceptual row can be
       modified."
     ::= { ospfAreaEntry 10 }
ospfAreaNssaTranslatorRole OBJECT-TYPE
    SYNTAX INTEGER { always (1), candidate (2) }
    MAX-ACCESS read-create
    STATUS
                current
    DESCRIPTION
       "Indicates an NSSA border router's ability to
       perform NSSA translation of type-7 LSAs into
       type-5 LSAs."
    DEFVAL { candidate }
     ::= { ospfAreaEntry 11 }
ospfAreaNssaTranslatorState OBJECT-TYPE
                 INTEGER { enabled (1),
    SYNTAX
                    elected (2),
                    disabled (3)
                read-only
    MAX-ACCESS
    STATUS current
    DESCRIPTION
        "Indicates if and how an NSSA border router is
       performing NSSA translation of type-7 LSAs into type-5
```

```
LSAs. When this object is set to enabled, the NSSA Border
         router's OspfAreaNssaExtTranslatorRole has been set to
         always. When this object is set to elected, a candidate
         NSSA Border router is Translating type-7 LSAs into type-5.
         When this object is set to disabled, a candidate NSSA
         border router is NOT translating type-7 LSAs into type-5."
      ::= { ospfAreaEntry 12 }
 ospfAreaNssaTranslatorStabilityInterval OBJECT-TYPE
      SYNTAX PositiveInteger
      UNITS
                  "seconds"
      MAX-ACCESS read-create
                  current
      STATUS
      DESCRIPTION
         "The number of seconds after an elected translator
         determines its services are no longer required, that
         it should continue to perform its translation duties."
      DEFVAL { 40 }
      ::= { ospfAreaEntry 13 }
 ospfAreaNssaTranslatorEvents OBJECT-TYPE
      SYNTAX Counter32
      MAX-ACCESS read-only
      STATUS
                  current
      DESCRIPTION
         "Indicates the number of translator state changes
         that have occurred since the last boot-up.
         Discontinuities in the value of this counter can occur
         at re-initialization of the management system, and at other
         times as indicated by the value of ospfDiscontinuityTime."
      ::= { ospfAreaEntry 14 }
-- OSPF Area Default Metric Table
 ospfStubAreaTable OBJECT-TYPE
      SYNTAX SEQUENCE OF OspfStubAreaEntry
      MAX-ACCESS not-accessible
      STATUS
              current
      DESCRIPTION
         "The set of metrics that will be advertised
         by a default Area Border Router into a stub area."
      REFERENCE
         "OSPF Version 2, Appendix C.2, Area Parameters"
      ::= { ospf 3 }
 ospfStubAreaEntry OBJECT-TYPE
      SYNTAX OspfStubAreaEntry
```

```
MAX-ACCESS not-accessible
    STATUS current
    DESCRIPTION
        "The metric for a given Type of Service that
       will be advertised by a default Area Border
       Router into a stub area.
       Information in this table is persistent and when this object
       is written the entity SHOULD save the change to non-volatile
       storage."
    REFERENCE
       "OSPF Version 2, Appendix C.2, Area Parameters"
    INDEX { ospfStubAreaId, ospfStubTOS }
     ::= { ospfStubAreaTable 1 }
OspfStubAreaEntry ::=
    SEQUENCE {
       ospfStubAreaId
          AreaID,
       ospfStubTOS
          TOSType,
       ospfStubMetric
         BigMetric,
       ospfStubStatus
          RowStatus,
       ospfStubMetricType
          INTEGER
        }
ospfStubAreaId OBJECT-TYPE
    SYNTAX AreaID
    MAX-ACCESS read-only -- read-only since originally an
                          -- SMIv1 index
    STATUS
                current
    DESCRIPTION
       "The 32-bit identifier for the stub area. On
       creation, this can be derived from the
       instance."
     ::= { ospfStubAreaEntry 1 }
ospfStubTOS OBJECT-TYPE
    SYNTAX TOSType
    MAX-ACCESS read-only -- read-only since originally an
                          -- SMIv1 index
    STATUS current
    DESCRIPTION
       "The Type of Service associated with the
       metric. On creation, this can be derived from
```

```
the instance."
      ::= { ospfStubAreaEntry 2 }
 ospfStubMetric OBJECT-TYPE
      SYNTAX BigMetric
      MAX-ACCESS read-create
      STATUS
                  current
      DESCRIPTION
         "The metric value applied at the indicated Type
         of Service. By default, this equals the least
         metric at the Type of Service among the
         interfaces to other areas."
      ::= { ospfStubAreaEntry 3 }
 ospfStubStatus OBJECT-TYPE
      SYNTAX RowStatus
      MAX-ACCESS read-create
                  current
      STATUS
      DESCRIPTION
         "This object permits management of the table by
         facilitating actions such as row creation,
         construction, and destruction.
         The value of this object has no effect on
         whether other objects in this conceptual row can be
         modified."
      ::= { ospfStubAreaEntry 4 }
 ospfStubMetricType OBJECT-TYPE
                INTEGER {
      SYNTAX
                      ospfMetric (1), -- OSPF Metric
                      comparableCost (2), -- external type 1
                      nonComparable (3) -- external type 2
      MAX-ACCESS read-create
      STATUS
                   current
      DESCRIPTION
         "This variable displays the type of metric
         advertised as a default route."
      DEFVAL { ospfMetric }
      ::= { ospfStubAreaEntry 5 }
-- OSPF Link State Database
 ospfLsdbTable OBJECT-TYPE
      SYNTAX SEQUENCE OF OspfLsdbEntry
      MAX-ACCESS not-accessible
      STATUS
                 current
```

```
DESCRIPTION
        "The OSPF Process's link state database (LSDB).
         The LSDB contains the link state advertisements
         from throughout the areas that the device is attached to."
     REFERENCE
        "OSPF Version 2, Section 12 Link State Advertisements"
     ::= { ospf 4 }
ospfLsdbEntry OBJECT-TYPE
     SYNTAX OspfLsdbEntry
     MAX-ACCESS not-accessible
     STATUS current
     DESCRIPTION
        "A single link state advertisement."
     INDEX { ospfLsdbAreaId, ospfLsdbType,
             ospfLsdbLsid, ospfLsdbRouterId }
     ::= { ospfLsdbTable 1 }
OspfLsdbEntry ::=
     SEQUENCE {
        ospfLsdbAreaId
          AreaID,
        ospfLsdbType
           INTEGER,
        ospfLsdbLsid
           IpAddress,
        ospfLsdbRouterId
          RouterID,
        ospfLsdbSequence
          Integer32,
        ospfLsdbAge
           Integer32,
        ospfLsdbChecksum
           Integer32,
        ospfLsdbAdvertisement
           OCTET STRING
        }
ospfLsdbAreaId OBJECT-TYPE
     SYNTAX AreaID
     {\tt MAX-ACCESS} \qquad {\tt read-only} \ {\tt --} \ {\tt read-only} \ {\tt since} \ {\tt originally} \ {\tt an}
                            -- SMIv1 index
     STATUS current
     DESCRIPTION
        "The 32-bit identifier of the area from which
        the LSA was received."
     REFERENCE
        "OSPF Version 2, Appendix C.2 Area parameters"
```

```
::= { ospfLsdbEntry 1 }
ospfLsdbType OBJECT-TYPE
    SYNTAX
                 INTEGER {
                    routerLink (1),
                    networkLink (2),
                     summaryLink (3),
                    asSummaryLink (4),
                    asExternalLink (5), -- but see ospfAsLsdbTable
                    multicastLink (6),
                    nssaExternalLink (7),
                    areaOpaqueLink (10)
    MAX-ACCESS read-only -- read-only since originally an
                          -- SMIv1 index
    STATUS
                 current
    DESCRIPTION
        "The type of the link state advertisement.
       Each link state type has a separate advertisement
       format.
       Note: External link state advertisements are permitted
       for backward compatibility, but should be displayed
       in the ospfAsLsdbTable rather than here."
    REFERENCE
        "OSPF Version 2, Appendix A.4.1 The Link State
       Advertisement header"
     ::= { ospfLsdbEntry 2 }
ospfLsdbLsid OBJECT-TYPE
    SYNTAX IpAddress
    {\tt MAX-ACCESS} \quad {\tt read-only -- read-only since originally an} \\
                           -- SMIv1 index
    STATUS
                 current
    DESCRIPTION
        "The Link State ID is an LS Type Specific field
       containing either a Router ID or an IP address;
       it identifies the piece of the routing domain
       that is being described by the advertisement."
    REFERENCE
        "OSPF Version 2, Section 12.1.4 Link State ID"
     ::= { ospfLsdbEntry 3 }
ospfLsdbRouterId OBJECT-TYPE
    SYNTAX RouterID
    MAX-ACCESS read-only -- read-only since originally an
                          -- SMIv1 index
    STATUS current
```

```
DESCRIPTION
       "The 32-bit number that uniquely identifies the
       originating router in the Autonomous System."
       "OSPF Version 2, Appendix C.1 Global parameters"
     ::= { ospfLsdbEntry 4 }
ospfLsdbSequence OBJECT-TYPE
    SYNTAX Integer32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "The sequence number field is a signed 32-bit
       integer. It starts with the value '80000001'h,
       or -'7FFFFFFF'h, and increments until '7FFFFFFF'h.
       Thus, a typical sequence number will be very negative.
       It is used to detect old and duplicate Link State
       Advertisements. The space of sequence numbers is linearly
       ordered. The larger the sequence number, the more recent
       the advertisement."
    REFERENCE
       "OSPF Version 2, Section 12.1.6 LS sequence
       number"
     ::= { ospfLsdbEntry 5 }
ospfLsdbAge OBJECT-TYPE
    SYNTAX Integer32 -- Should be 0..MaxAge, except when
                   -- doNotAge bit is set
    UNITS
                "seconds"
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
       "This field is the age of the link state advertisement
       in seconds."
    REFERENCE
       "OSPF Version 2, Section 12.1.1 LS age"
     ::= { ospfLsdbEntry 6 }
ospfLsdbChecksum OBJECT-TYPE
    SYNTAX Integer32
               read-only
    MAX-ACCESS
    STATUS
                current
    DESCRIPTION
       "This field is the checksum of the complete contents of
       the advertisement, excepting the age field. The age field
       is excepted so that an advertisement's age can be
       incremented without updating the checksum. The checksum
       used is the same that is used for ISO connectionless
```

```
datagrams; it is commonly referred to as the
         Fletcher checksum."
       REFERENCE
          "OSPF Version 2, Section 12.1.7 LS checksum"
       ::= { ospfLsdbEntry 7 }
 ospfLsdbAdvertisement OBJECT-TYPE
      SYNTAX OCTET STRING (SIZE (1..65535))
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
         "The entire link state advertisement, including
         its header.
         Note that for variable length LSAs, SNMP agents
         may not be able to return the largest string size."
      REFERENCE
         "OSPF Version 2, Section 12 Link State Advertisements"
      ::= { ospfLsdbEntry 8 }
-- Address Range Table
 ospfAreaRangeTable OBJECT-TYPE
      SYNTAX SEQUENCE OF OspfAreaRangeEntry
                 not-accessible
      MAX-ACCESS
      STATUS obsolete
      DESCRIPTION
         "The Address Range Table acts as an adjunct to the Area
          Table. It describes those Address Range Summaries that
          are configured to be propagated from an Area to reduce
          the amount of information about it that is known beyond
          its borders. It contains a set of IP address ranges
          specified by an IP address/IP network mask pair.
          For example, class B address range of X.X.X.X
          with a network mask of 255.255.0.0 includes all IP
          addresses from X.X.O.O to X.X.255.255.
          Note that this table is obsoleted and is replaced
          by the Area Aggregate Table."
      REFERENCE
         "OSPF Version 2, Appendix C.2 Area parameters"
      ::= { ospf 5 }
 ospfAreaRangeEntry OBJECT-TYPE
      SYNTAX OspfAreaRangeEntry
      MAX-ACCESS not-accessible
      STATUS obsolete
      DESCRIPTION
```

```
"A single area address range.
       Information in this table is persistent and when this object
       is written the entity SHOULD save the change to non-volatile
       storage."
    REFERENCE
       "OSPF Version 2, Appendix C.2 Area parameters"
    INDEX { ospfAreaRangeAreaId, ospfAreaRangeNet }
     ::= { ospfAreaRangeTable 1 }
OspfAreaRangeEntry ::=
    SEQUENCE {
       ospfAreaRangeAreaId
          AreaID,
       ospfAreaRangeNet
          IpAddress,
       ospfAreaRangeMask
          IpAddress,
       ospfAreaRangeStatus
          RowStatus,
       ospfAreaRangeEffect
          INTEGER
ospfAreaRangeAreaId OBJECT-TYPE
    SYNTAX AreaID
    MAX-ACCESS read-only -- read-only since originally an
                          -- SMIv1 index
             obsolete
    STATUS
    DESCRIPTION
       "The area that the address range is to be found
       within."
    REFERENCE
       "OSPF Version 2, Appendix C.2 Area parameters"
     ::= { ospfAreaRangeEntry 1 }
ospfAreaRangeNet OBJECT-TYPE
    SYNTAX IpAddress
    MAX-ACCESS read-only -- read-only since originally an
                           -- SMIv1 index
    STATUS
             obsolete
    DESCRIPTION
        "The IP address of the net or subnet indicated
       by the range."
    REFERENCE
       "OSPF Version 2, Appendix C.2 Area parameters"
    ::= { ospfAreaRangeEntry 2 }
```

```
ospfAreaRangeMask OBJECT-TYPE
      SYNTAX IpAddress
      MAX-ACCESS read-create
      STATUS obsolete
      DESCRIPTION
         "The subnet mask that pertains to the net or
         subnet."
      REFERENCE
         "OSPF Version 2, Appendix C.2 Area parameters"
      ::= { ospfAreaRangeEntry 3 }
 ospfAreaRangeStatus OBJECT-TYPE
      SYNTAX
               RowStatus
      MAX-ACCESS read-create
      STATUS
                  obsolete
      DESCRIPTION
         "This object permits management of the table by
         facilitating actions such as row creation,
         construction, and destruction.
         The value of this object has no effect on
         whether other objects in this conceptual row can be
         modified."
       ::= { ospfAreaRangeEntry 4 }
 ospfAreaRangeEffect OBJECT-TYPE
      SYNTAX
                   INTEGER {
                     advertiseMatching (1),
                      doNotAdvertiseMatching (2)
                 read-create
      MAX-ACCESS
      STATUS
                   obsolete
      DESCRIPTION
         "Subnets subsumed by ranges either trigger the
         advertisement of the indicated summary
        (advertiseMatching) or result in the subnet's not
         being advertised at all outside the area."
      DEFVAL { advertiseMatching }
       ::= { ospfAreaRangeEntry 5 }
-- OSPF Host Table
 ospfHostTable OBJECT-TYPE
      SYNTAX SEQUENCE OF OspfHostEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
         "The Host/Metric Table indicates what hosts are directly
```

```
attached to the router, what metrics and types
       of service should be advertised for them,
       and what areas they are found within."
    REFERENCE
       "OSPF Version 2, Appendix C.7 Host route
       parameters"
     ::= { ospf 6 }
ospfHostEntry OBJECT-TYPE
    SYNTAX OspfHostEntry
    MAX-ACCESS not-accessible
    STATUS current
    DESCRIPTION
        "A metric to be advertised, for a given type of
        service, when a given host is reachable.
        Information in this table is persistent and when this object
       is written the entity SHOULD save the change to non-volatile
        storage."
     INDEX { ospfHostIpAddress, ospfHostTOS }
     ::= { ospfHostTable 1 }
OspfHostEntry ::=
    SEQUENCE {
       ospfHostIpAddress
          IpAddress,
       ospfHostTOS
          TOSType,
        ospfHostMetric
          Metric,
        ospfHostStatus
          RowStatus,
        ospfHostAreaID
          AreaID,
       ospfHostCfgAreaID
          AreaID
        }
ospfHostIpAddress OBJECT-TYPE
    SYNTAX IpAddress
    {\tt MAX-ACCESS} \quad {\tt read-only -- read-only since originally an} \\
                            -- SMIv1 index
    STATUS current
    DESCRIPTION
       "The IP address of the host."
    REFERENCE
        "OSPF Version 2, Appendix C.7 Host route parameters"
     ::= { ospfHostEntry 1 }
```

```
ospfHostTOS OBJECT-TYPE
    SYNTAX TOSType
    MAX-ACCESS read-only -- read-only since originally an
                         -- SMIv1 index
    STATUS current
    DESCRIPTION
       "The Type of Service of the route being configured."
       "OSPF Version 2, Appendix C.7 Host route parameters"
    ::= { ospfHostEntry 2 }
ospfHostMetric OBJECT-TYPE
    SYNTAX Metric
    MAX-ACCESS read-create
                current
    STATUS
    DESCRIPTION
       "The metric to be advertised."
    REFERENCE
       "OSPF Version 2, Appendix C.7 Host route parameters"
    ::= { ospfHostEntry 3 }
ospfHostStatus OBJECT-TYPE
    SYNTAX RowStatus
    MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
       "This object permits management of the table by
       facilitating actions such as row creation,
       construction, and destruction.
       The value of this object has no effect on
       whether other objects in this conceptual row can be
       modified."
     ::= { ospfHostEntry 4 }
ospfHostAreaID OBJECT-TYPE
    SYNTAX AreaID
    MAX-ACCESS read-only
    STATUS
            deprecated
    DESCRIPTION
       "The OSPF area to which the host belongs.
       Deprecated by ospfHostCfgAreaID."
    REFERENCE
       "OSPF Version 2, Appendix C.7 Host parameters"
    ::= { ospfHostEntry 5 }
ospfHostCfgAreaID OBJECT-TYPE
    SYNTAX AreaID
```

```
MAX-ACCESS read-create
                  current
      STATUS
      DESCRIPTION
         "To configure the OSPF area to which the host belongs."
      REFERENCE
         "OSPF Version 2, Appendix C.7 Host parameters"
       ::= { ospfHostEntry 6 }
-- OSPF Interface Table
 ospfIfTable OBJECT-TYPE
      SYNTAX SEQUENCE OF Ospfifentry
      MAX-ACCESS not-accessible
                  current
      STATUS
      DESCRIPTION
         "The OSPF Interface Table describes the interfaces
         from the viewpoint of OSPF.
         It augments the ipAddrTable with OSPF specific information."
      REFERENCE
         "OSPF Version 2, Appendix C.3 Router interface
         parameters"
       ::= { ospf 7 }
 ospfIfEntry OBJECT-TYPE
      SYNTAX OspfIfEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
         "The OSPF interface entry describes one interface
         from the viewpoint of OSPF.
         Information in this table is persistent and when this object
         is written the entity SHOULD save the change to non-volatile
         storage."
      INDEX { ospfIfIpAddress, ospfAddressLessIf }
      ::= { ospfIfTable 1 }
 OspfIfEntry ::=
      SEQUENCE {
         ospfIfIpAddress
            IpAddress,
         ospfAddressLessIf
            InterfaceIndexOrZero,
         ospfIfAreaId
            AreaID,
         ospfIfType
            INTEGER,
         ospfIfAdminStat
```

Status,

```
ospfIfRtrPriority
          DesignatedRouterPriority,
        ospfIfTransitDelay
          UpToMaxAge,
        ospfIfRetransInterval
          UpToMaxAge,
        ospfIfHelloInterval
          HelloRange,
        ospfIfRtrDeadInterval
          PositiveInteger,
        ospfIfPollInterval
          PositiveInteger,
        ospfIfState
          INTEGER,
        ospfIfDesignatedRouter
          IpAddress,
        ospfIfBackupDesignatedRouter
          IpAddress,
        ospfIfEvents
          Counter32,
        ospfIfAuthKey
          OCTET STRING,
        ospfIfStatus
          RowStatus,
        ospfIfMulticastForwarding
           INTEGER,
        ospfIfDemand
          TruthValue,
        ospfIfAuthType
          OspfAuthenticationType,
        ospfIfLsaCount
          Gauge32,
       ospfIfLsaCksumSum
          Unsigned32,
        ospfIfDesignatedRouterId
          RouterID,
        ospfIfBackupDesignatedRouterId
          RouterID
ospfIfIpAddress OBJECT-TYPE
     SYNTAX IpAddress
    MAX-ACCESS read-only -- read-only since originally an
                           -- SMIv1 index
     STATUS
                 current
    DESCRIPTION
        "The IP address of this OSPF interface."
```

```
::= { ospfIfEntry 1 }
ospfAddressLessIf OBJECT-TYPE
     SYNTAX InterfaceIndexOrZero
    {\tt MAX-ACCESS} \quad {\tt read-only -- read-only since originally an} \\
                           -- SMIv1 index
     STATUS current
     DESCRIPTION
        "For the purpose of easing the instancing of
       addressed and addressless interfaces; this
       variable takes the value 0 on interfaces with
       IP addresses and the corresponding value of
       ifIndex for interfaces having no IP address."
     ::= { ospfIfEntry 2 }
ospfIfAreaId OBJECT-TYPE
     SYNTAX AreaID
    MAX-ACCESS read-create
                 current
    STATUS
    DESCRIPTION
        "A 32-bit integer uniquely identifying the area
       to which the interface connects. Area ID
       0.0.0.0 is used for the OSPF backbone."
    DEFVAL { '00000000'H } -- 0.0.0.0
     ::= { ospfIfEntry 3 }
ospfIfType OBJECT-TYPE
    SYNTAX INTEGER {
                    broadcast (1),
                    nbma (2),
                    pointToPoint (3),
                    pointToMultipoint (5)
    MAX-ACCESS read-create
     STATUS
                 current
    DESCRIPTION
       "The OSPF interface type.
       By way of a default, this field may be intuited
       from the corresponding value of ifType.
       Broadcast LANs, such as Ethernet and IEEE 802.5,
       take the value 'broadcast', X.25 and similar
       technologies take the value 'nbma', and links
       that are definitively point to point take the
       value 'pointToPoint'."
      ::= { ospfIfEntry 4 }
ospfIfAdminStat OBJECT-TYPE
    SYNTAX Status
```

```
MAX-ACCESS read-create
    STATUS
               current
    DESCRIPTION
       "The OSPF interface's administrative status.
       The value formed on the interface, and the interface
       will be advertised as an internal route to some area.
       The value 'disabled' denotes that the interface is
       external to OSPF."
    DEFVAL { enabled }
    ::= { ospfIfEntry 5 }
ospfIfRtrPriority OBJECT-TYPE
    SYNTAX DesignatedRouterPriority
    MAX-ACCESS read-create
    STATUS
                current
    DESCRIPTION
       "The priority of this interface. Used in
       multi-access networks, this field is used in
       the designated router election algorithm. The
       value 0 signifies that the router is not eligible
       to become the designated router on this particular
       network. In the event of a tie in this value,
       routers will use their Router ID as a tie breaker."
     DEFVAL { 1 }
     ::= { ospfIfEntry 6 }
ospfIfTransitDelay OBJECT-TYPE
     SYNTAX UpToMaxAge
     UNITS
                "seconds"
     MAX-ACCESS read-create
     STATUS current
     DESCRIPTION
        "The estimated number of seconds it takes to
        transmit a link state update packet over this
        interface. Note that the minimal value SHOULD be
        1 second."
     DEFVAL { 1 }
     ::= { ospfIfEntry 7 }
ospfIfRetransInterval OBJECT-TYPE
    SYNTAX UpToMaxAge
               "seconds"
    UNITS
    MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
       "The number of seconds between link state advertisement
       retransmissions, for adjacencies belonging to this
       interface. This value is also used when retransmitting
```

```
database description and Link State request packets.
       Note that minimal value SHOULD be 1 second."
    DEFVAL { 5 }
    ::= { ospfIfEntry 8 }
ospfIfHelloInterval OBJECT-TYPE
    SYNTAX HelloRange UNITS "seconds"
    MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
       "The length of time, in seconds, between the Hello packets
       that the router sends on the interface. This value must be
       the same for all routers attached to a common network."
    DEFVAL { 10 }
    ::= { ospfIfEntry 9 }
ospfIfRtrDeadInterval OBJECT-TYPE
    SYNTAX PositiveInteger
    UNITS
                "seconds"
    MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
       "The number of seconds that a router's Hello packets have
       not been seen before its neighbors declare the router down.
       This should be some multiple of the Hello interval. This
       value must be the same for all routers attached to a common
       network."
     DEFVAL { 40 }
     ::= { ospfIfEntry 10 }
ospfIfPollInterval OBJECT-TYPE
    SYNTAX PositiveInteger
    UNITS
                 "seconds"
    MAX-ACCESS read-create
    STATUS
                 current
    DESCRIPTION
       "The larger time interval, in seconds, between the Hello
       packets sent to an inactive non-broadcast multi-access
       neighbor."
    DEFVAL { 120 }
    ::= { ospfIfEntry 11 }
ospfIfState OBJECT-TYPE
    SYNTAX
                 INTEGER {
                    down (1),
                    loopback (2),
                    waiting (3),
```

```
pointToPoint (4),
                    designatedRouter (5),
                    backupDesignatedRouter (6),
                    otherDesignatedRouter (7)
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
        "The OSPF Interface State."
    DEFVAL { down }
     ::= { ospfIfEntry 12 }
ospfIfDesignatedRouter OBJECT-TYPE
    SYNTAX IpAddress
    MAX-ACCESS read-only
STATUS current
    DESCRIPTION
       "The IP address of the designated router."
    DEFVAL { '00000000'H } -- 0.0.0.0
     ::= { ospfIfEntry 13 }
ospfIfBackupDesignatedRouter OBJECT-TYPE
    SYNTAX IpAddress
               read-only
    MAX-ACCESS
    STATUS current
    DESCRIPTION
       "The IP address of the backup designated
       router."
    DEFVAL { '00000000'H } -- 0.0.0.0
    ::= { ospfIfEntry 14 }
ospfIfEvents OBJECT-TYPE
    SYNTAX Counter32
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
       "The number of times this OSPF interface has
       changed its state or an error has occurred.
       Discontinuities in the value of this counter can occur
       at re-initialization of the management system, and at other
       times as indicated by the value of ospfDiscontinuityTime."
     ::= { ospfIfEntry 15 }
ospfIfAuthKey OBJECT-TYPE
    SYNTAX OCTET STRING (SIZE (0..256))
    MAX-ACCESS read-create
    STATUS
               current
```

DESCRIPTION

"The cleartext password used as an OSPF authentication key when simplePassword security is enabled. This object does not access any OSPF cryptogaphic (e.g., MD5) authentication key under any circumstance.

If the key length is shorter than 8 octets, the agent will left adjust and zero fill to 8 octets.

Unauthenticated interfaces need no authentication key, and simple password authentication cannot use a key of more than 8 octets.

Note that the use of simplePassword authentication is NOT recommended when there is concern regarding attack upon the OSPF system. SimplePassword authentication is only sufficient to protect against accidental misconfigurations because it re-uses cleartext passwords [RFC1704].

When read, ospfIfAuthKey always returns an octet string of length zero."

```
REFERENCE
```

"OSPF Version 2, Section 9 The Interface Data
Structure"
DEFVAL { '00000000000000000'H } -- 0.0.0.0.0.0.0.0
::= { ospfIfEntry 16 }

ospfIfStatus OBJECT-TYPE

SYNTAX RowStatus
MAX-ACCESS read-create
STATUS current

DESCRIPTION

"This object permits management of the table by facilitating actions such as row creation, construction, and destruction.

The value of this object has no effect on whether other objects in this conceptual row can be modified."

::= { ospfIfEntry 17 }

ospfIfMulticastForwarding OBJECT-TYPE
 SYNTAX INTEGER {

blocked (1), -- no multicast forwarding multicast (2), -- using multicast address unicast (3) -- to each OSPF neighbor

```
MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
       "The way multicasts should be forwarded on this
       interface: not forwarded, forwarded as data
       link multicasts, or forwarded as data link
       unicasts. Data link multicasting is not
       meaningful on point-to-point and NBMA interfaces,
       and setting ospfMulticastForwarding to 0 effectively
       disables all multicast forwarding."
    DEFVAL { blocked }
    ::= { ospfIfEntry 18 }
ospfIfDemand OBJECT-TYPE
    SYNTAX TruthValue
    MAX-ACCESS read-create
                current
    STATUS
    DESCRIPTION
       "Indicates whether Demand OSPF procedures (hello
       suppression to FULL neighbors and setting the
       DoNotAge flag on propagated LSAs) should be
       performed on this interface."
    DEFVAL { false }
    ::= { ospfIfEntry 19 }
ospfIfAuthType OBJECT-TYPE
    SYNTAX OspfAuthenticationType
    MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
       "The authentication type specified for an interface.
       Note that this object can be used to engage
       in significant attacks against an OSPF router."
    REFERENCE
       "OSPF Version 2, Appendix D Authentication"
    DEFVAL { none } -- no authentication, by default
     ::= { ospfIfEntry 20 }
ospfIfLsaCount OBJECT-TYPE
    SYNTAX Gauge32
               read-only
    MAX-ACCESS
    STATUS current
    DESCRIPTION
       "The total number of link-local link state advertisements
       in this interface's link-local link state database."
     ::= { ospfIfEntry 21 }
```

```
ospfIfLsaCksumSum OBJECT-TYPE
      SYNTAX Unsigned32
      MAX-ACCESS read-only
      STATUS
                  current
      DESCRIPTION
         "The 32-bit unsigned sum of the Link State
         Advertisements' LS checksums contained in this
         interface's link-local link state database.
         The sum can be used to determine if there has
         been a change in the interface's link state
         database and to compare the interface link state
         database of routers attached to the same subnet."
      ::= { ospfIfEntry 22 }
 ospfIfDesignatedRouterId OBJECT-TYPE
      SYNTAX RouterID
      MAX-ACCESS read-only
                  current
      STATUS
      DESCRIPTION
         "The Router ID of the designated router."
      ::= { ospfIfEntry 23 }
 ospfIfBackupDesignatedRouterId OBJECT-TYPE
      SYNTAX RouterID
                 read-only
      MAX-ACCESS
      STATUS current
      DESCRIPTION
         "The Router ID of the backup designated router."
      ::= { ospfIfEntry 24 }
-- OSPF Interface Metric Table
 ospfIfMetricTable OBJECT-TYPE
      SYNTAX SEQUENCE OF OspfIfMetricEntry
      MAX-ACCESS not-accessible
                  current
      STATUS
      DESCRIPTION
         "The Metric Table describes the metrics to be advertised
         for a specified interface at the various types of service.
         As such, this table is an adjunct of the OSPF Interface
         Table.
         Types of service, as defined by RFC 791, have the ability
         to request low delay, high bandwidth, or reliable linkage.
         For the purposes of this specification, the measure of
         bandwidth:
```

Metric = referenceBandwidth / ifSpeed

```
is the default value.
       The default reference bandwidth is 10^8.
       For multiple link interfaces, note that if Speed is the sum
       of the individual link speeds. This yields a number having
       the following typical values:
       Network Type/bit rate Metric
       >= 100 MBPS
                                   1
       Ethernet/802.3
                                  10
       E1
                                  48
       T1 (ESF)
                                  65
       64 KBPS
                                  1562
       56 KBPS
                                  1785
       19.2 KBPS
                                  5208
       9.6 KBPS
                                  10416
       Routes that are not specified use the default
       (TOS 0) metric.
       Note that the default reference bandwidth can be configured
       using the general group object ospfReferenceBandwidth."
       "OSPF Version 2, Appendix C.3 Router interface
       parameters"
     ::= { ospf 8 }
ospfIfMetricEntry OBJECT-TYPE
    SYNTAX OspfIfMetricEntry
    MAX-ACCESS not-accessible
    STATUS current
    DESCRIPTION
       "A particular TOS metric for a non-virtual interface
       identified by the interface index.
       Information in this table is persistent and when this object
       is written the entity SHOULD save the change to non-volatile
       storage."
    REFERENCE
       "OSPF Version 2, Appendix C.3 Router interface
       parameters"
    INDEX { ospfIfMetricIpAddress,
       ospfIfMetricAddressLessIf,
       ospfIfMetricTOS }
     ::= { ospfIfMetricTable 1 }
```

```
OspfIfMetricEntry ::=
    SEQUENCE {
       ospfIfMetricIpAddress
          IpAddress,
       ospfIfMetricAddressLessIf
          InterfaceIndexOrZero,
        ospfIfMetricTOS
          TOSType,
       ospfIfMetricValue
          Metric,
       ospfIfMetricStatus
          RowStatus
ospfIfMetricIpAddress OBJECT-TYPE
     SYNTAX IpAddress
    {\tt MAX-ACCESS} \quad {\tt read-only -- read-only since originally an} \\
                           -- SMIv1 index
    STATUS
                 current
    DESCRIPTION
        "The IP address of this OSPF interface. On row
       creation, this can be derived from the instance."
     ::= { ospfIfMetricEntry 1 }
ospfIfMetricAddressLessIf OBJECT-TYPE
     SYNTAX InterfaceIndexOrZero
    MAX-ACCESS read-only -- read-only since originally an
                           -- SMIv1 index
             current
    STATUS
    DESCRIPTION
        "For the purpose of easing the instancing of
       addressed and addressless interfaces; this
        variable takes the value 0 on interfaces with
        IP addresses and the value of ifIndex for
       interfaces having no IP address. On row
       creation, this can be derived from the instance."
      ::= { ospfIfMetricEntry 2 }
ospfIfMetricTOS OBJECT-TYPE
     SYNTAX TOSType
    MAX-ACCESS read-only -- read-only since originally an
                           -- SMIv1 index
     STATUS current
    DESCRIPTION
       "The Type of Service metric being referenced.
       On row creation, this can be derived from the
       instance."
     ::= { ospfIfMetricEntry 3 }
```

```
ospfIfMetricValue OBJECT-TYPE
      SYNTAX Metric
      MAX-ACCESS read-create
      STATUS current
      DESCRIPTION
         "The metric of using this Type of Service on
         this interface. The default value of the TOS 0
         metric is 10^8 / ifSpeed."
      ::= { ospfIfMetricEntry 4 }
 ospfIfMetricStatus OBJECT-TYPE
      SYNTAX RowStatus
      MAX-ACCESS read-create
      STATUS
                 current
      DESCRIPTION
         "This object permits management of the table by
         facilitating actions such as row creation,
         construction, and destruction.
         The value of this object has no effect on
         whether other objects in this conceptual row can be
         modified."
      ::= { ospfIfMetricEntry 5 }
-- OSPF Virtual Interface Table
 ospfVirtIfTable OBJECT-TYPE
      SYNTAX SEQUENCE OF OspfVirtIfEntry
      MAX-ACCESS not-accessible
      STATUS
                  current
      DESCRIPTION
         "Information about this router's virtual interfaces
         that the OSPF Process is configured to carry on."
      REFERENCE
         "OSPF Version 2, Appendix C.4 Virtual link
         parameters"
      ::= { ospf 9 }
 ospfVirtIfEntry OBJECT-TYPE
      SYNTAX OspfVirtIfEntry
                 not-accessible
      MAX-ACCESS
      STATUS
                  current
      DESCRIPTION
         "Information about a single virtual interface.
         Information in this table is persistent and when this object
         is written the entity SHOULD save the change to non-volatile
         storage."
```

```
INDEX { ospfVirtIfAreaId, ospfVirtIfNeighbor }
    ::= { ospfVirtIfTable 1 }
OspfVirtIfEntry ::=
    SEQUENCE {
       ospfVirtIfAreaId
          AreaID,
       ospfVirtIfNeighbor
          RouterID,
       ospfVirtIfTransitDelay
         UpToMaxAge,
       ospfVirtIfRetransInterval
          UpToMaxAge,
       ospfVirtIfHelloInterval
          HelloRange,
       ospfVirtIfRtrDeadInterval
          PositiveInteger,
       ospfVirtIfState
          INTEGER,
       ospfVirtIfEvents
          Counter32,
       ospfVirtIfAuthKey
         OCTET STRING,
       ospfVirtIfStatus
          RowStatus,
       ospfVirtIfAuthType
          OspfAuthenticationType,
       ospfVirtIfLsaCount
         Gauge32,
       ospfVirtIfLsaCksumSum
          Unsigned32
ospfVirtIfAreaId OBJECT-TYPE
    SYNTAX AreaID
    MAX-ACCESS read-only -- read-only since originally an
                   -- SMIv1 index
                current
    DESCRIPTION
       "The transit area that the virtual link
       traverses. By definition, this is not 0.0.0.0."
     ::= { ospfVirtIfEntry 1 }
ospfVirtIfNeighbor OBJECT-TYPE
    SYNTAX RouterID
    MAX-ACCESS read-only -- read-only since originally an
                         -- SMIv1 index
    STATUS current
```

[Page 49]

```
DESCRIPTION
       "The Router ID of the virtual neighbor."
     ::= { ospfVirtIfEntry 2 }
ospfVirtIfTransitDelay OBJECT-TYPE
    SYNTAX UpToMaxAge
                "seconds"
    UNITS
    MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
       "The estimated number of seconds it takes to
       transmit a Link State update packet over this
       interface. Note that the minimal value SHOULD be
       1 second."
    DEFVAL { 1 }
     ::= { ospfVirtIfEntry 3 }
ospfVirtIfRetransInterval OBJECT-TYPE
    SYNTAX UpToMaxAge
    UNITS
                "seconds"
    MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
       "The number of seconds between link state
       avertisement retransmissions, for adjacencies
       belonging to this interface. This value is
       also used when retransmitting database
       description and Link State request packets. This
       value should be well over the expected
       round-trip time. Note that the minimal value SHOULD be
       1 second."
    DEFVAL { 5 }
     ::= { ospfVirtIfEntry 4 }
ospfVirtIfHelloInterval OBJECT-TYPE
    SYNTAX HelloRange
    UNITS
                "seconds"
    MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
       "The length of time, in seconds, between the
       Hello packets that the router sends on the
       interface. This value must be the same for the
       virtual neighbor."
    DEFVAL { 10 }
     ::= { ospfVirtIfEntry 5 }
ospfVirtIfRtrDeadInterval OBJECT-TYPE
```

```
SYNTAX PositiveInteger UNITS "seconds"
    MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
       "The number of seconds that a router's Hello
       packets have not been seen before its
       neighbors declare the router down. This should be
       some multiple of the Hello interval. This
       value must be the same for the virtual neighbor."
    DEFVAL { 60 }
    ::= { ospfVirtIfEntry 6 }
ospfVirtIfState OBJECT-TYPE
    SYNTAX
                INTEGER {
                    down (1), -- these use the same encoding
                    pointToPoint (4) -- as the ospfIfTable
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
       "OSPF virtual interface states."
    DEFVAL { down }
    ::= { ospfVirtIfEntry 7 }
ospfVirtIfEvents OBJECT-TYPE
    SYNTAX Counter32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "The number of state changes or error events on
       this virtual link.
       Discontinuities in the value of this counter can occur
       at re-initialization of the management system, and at other
       times as indicated by the value of ospfDiscontinuityTime."
     ::= { ospfVirtIfEntry 8 }
ospfVirtIfAuthKey OBJECT-TYPE
    SYNTAX OCTET STRING (SIZE(0..256))
                read-create
    MAX-ACCESS
    STATUS
                current
    DESCRIPTION
       "The cleartext password used as an OSPF
       authentication key when simplePassword security
       is enabled. This object does not access any OSPF
       cryptogaphic (e.g., MD5) authentication key under
       any circumstance.
```

If the key length is shorter than 8 octets, the agent will left adjust and zero fill to 8 octets. Unauthenticated interfaces need no authentication key, and simple password authentication cannot use a key of more than 8 octets. Note that the use of simplePassword authentication is NOT recommended when there is concern regarding attack upon the OSPF system. SimplePassword authentication is only sufficient to protect against accidental misconfigurations because it re-uses cleartext passwords. [RFC1704] When read, ospfIfAuthKey always returns an octet string of length zero." REFERENCE "OSPF Version 2, Section 9 The Interface Data Structure" DEFVAL { '000000000000000'H } -- 0.0.0.0.0.0.0 ::= { ospfVirtIfEntry 9 } ospfVirtIfStatus OBJECT-TYPE SYNTAX RowStatus read-create MAX-ACCESS STATUS current DESCRIPTION "This object permits management of the table by facilitating actions such as row creation, construction, and destruction. The value of this object has no effect on whether other objects in this conceptual row can be modified." ::= { ospfVirtIfEntry 10 } ospfVirtIfAuthType OBJECT-TYPE SYNTAX OspfAuthenticationType MAX-ACCESS read-create STATUS current DESCRIPTION "The authentication type specified for a virtual interface. Note that this object can be used to engage in significant attacks against an OSPF router." "OSPF Version 2, Appendix E Authentication"

DEFVAL { none } -- no authentication, by default

```
::= { ospfVirtIfEntry 11 }
 ospfVirtIfLsaCount OBJECT-TYPE
      SYNTAX Gauge32
      MAX-ACCESS read-only
      STATUS
                  current
      DESCRIPTION
         "The total number of link-local link state advertisements
         in this virtual interface's link-local link state database."
      ::= { ospfVirtIfEntry 12 }
 ospfVirtIfLsaCksumSum OBJECT-TYPE
      SYNTAX Unsigned32
      MAX-ACCESS read-only
                  current
      STATUS
      DESCRIPTION
         "The 32-bit unsigned sum of the link state
         advertisements' LS checksums contained in this
         virtual interface's link-local link state database.
         The sum can be used to determine if there has
         been a change in the virtual interface's link state
         database, and to compare the virtual interface
         link state database of the virtual neighbors."
       ::= { ospfVirtIfEntry 13 }
-- OSPF Neighbor Table
 ospfNbrTable OBJECT-TYPE
      SYNTAX SEQUENCE OF OspfNbrEntry
      MAX-ACCESS not-accessible
      STATUS
                  current
      DESCRIPTION
         "A table describing all non-virtual neighbors
         in the locality of the OSPF router."
      REFERENCE
         "OSPF Version 2, Section 10 The Neighbor Data
         Structure"
      ::= { ospf 10 }
 ospfNbrEntry OBJECT-TYPE
      SYNTAX OspfNbrEntry
                 not-accessible
      MAX-ACCESS
      STATUS
              current
      DESCRIPTION
         "The information regarding a single neighbor.
         Information in this table is persistent and when this object
         is written the entity SHOULD save the change to non-volatile
```

```
storage."
    REFERENCE
       "OSPF Version 2, Section 10 The Neighbor Data
       Structure"
    INDEX { ospfNbrIpAddr, ospfNbrAddressLessIndex }
     ::= { ospfNbrTable 1 }
OspfNbrEntry ::=
    SEQUENCE {
       ospfNbrIpAddr
          IpAddress,
        ospfNbrAddressLessIndex
          InterfaceIndexOrZero,
       ospfNbrRtrId
          RouterID,
        ospfNbrOptions
          Integer32,
        ospfNbrPriority
          DesignatedRouterPriority,
        ospfNbrState
          INTEGER,
       ospfNbrEvents
          Counter32,
        ospfNbrLsRetransQLen
          Gauge32,
       ospfNbmaNbrStatus
          RowStatus,
        ospfNbmaNbrPermanence
          INTEGER,
        ospfNbrHelloSuppressed
          TruthValue,
        ospfNbrRestartHelperStatus
          INTEGER,
        ospfNbrRestartHelperAge
          Unsigned32,
        ospfNbrRestartHelperExitReason
          INTEGER
        }
ospfNbrIpAddr OBJECT-TYPE
    SYNTAX IpAddress
                read-only -- read-only since originally an
    MAX-ACCESS
                           -- SMIv1 index
    STATUS
                current
    DESCRIPTION
        "The IP address this neighbor is using in its
       IP source address. Note that, on addressless
       links, this will not be 0.0.0.0 but the
```

```
address of another of the neighbor's interfaces."
     ::= { ospfNbrEntry 1 }
 ospfNbrAddressLessIndex OBJECT-TYPE
     SYNTAX InterfaceIndexOrZero
    {\tt MAX-ACCESS} \quad {\tt read-only} \,\, {\tt --} \,\, {\tt read-only} \,\, {\tt since} \,\, {\tt originally} \,\, {\tt an}
                            -- SMIv1 index
     STATUS current
    DESCRIPTION
        "On an interface having an IP address, zero.
        On addressless interfaces, the corresponding
        value of ifIndex in the Internet Standard MIB.
        On row creation, this can be derived from the
        instance."
      ::= { ospfNbrEntry 2 }
ospfNbrRtrId OBJECT-TYPE
    SYNTAX RouterID
    MAX-ACCESS read-only
     STATUS
                current
     DESCRIPTION
        "A 32-bit integer (represented as a type
        IpAddress) uniquely identifying the neighboring
        router in the Autonomous System."
     DEFVAL { '00000000'H } -- 0.0.0.0
     ::= { ospfNbrEntry 3 }
ospfNbrOptions OBJECT-TYPE
    SYNTAX Integer32
    MAX-ACCESS read-only
     STATUS current
    DESCRIPTION
        "A bit mask corresponding to the neighbor's
        options field.
        Bit 0, if set, indicates that the system will
        operate on Type of Service metrics other than
        TOS 0. If zero, the neighbor will ignore all
        metrics except the TOS 0 metric.
        Bit 1, if set, indicates that the associated
        area accepts and operates on external
        information; if zero, it is a stub area.
        Bit 2, if set, indicates that the system is
        capable of routing IP multicast datagrams, that is
        that it implements the multicast extensions to
        OSPF.
```

```
Bit 3, if set, indicates that the associated
       area is an NSSA. These areas are capable of
       carrying type-7 external advertisements, which
       are translated into type-5 external advertisements
       at NSSA borders."
    REFERENCE
        "OSPF Version 2, Section 12.1.2 Options"
    DEFVAL { 0 }
    ::= { ospfNbrEntry 4 }
ospfNbrPriority OBJECT-TYPE
    SYNTAX DesignatedRouterPriority
    MAX-ACCESS read-create
    STATUS
                current
    DESCRIPTION
       "The priority of this neighbor in the designated
       router election algorithm. The value 0 signifies
       that the neighbor is not eligible to become
       the designated router on this particular network."
    DEFVAL { 1 }
    ::= { ospfNbrEntry 5 }
ospfNbrState OBJECT-TYPE
     SYNTAX
                  INTEGER {
                      down (1),
                      attempt (2),
                      init (3),
                      twoWay (4),
                      exchangeStart (5),
                      exchange (6),
                      loading (7),
                      full (8)
      MAX-ACCESS read-only
      STATUS
                  current
      DESCRIPTION
         "The state of the relationship with this neighbor."
      REFERENCE
         "OSPF Version 2, Section 10.1 Neighbor States"
      DEFVAL { down }
      ::= { ospfNbrEntry 6 }
ospfNbrEvents OBJECT-TYPE
    SYNTAX Counter32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
```

```
"The number of times this neighbor relationship
       has changed state or an error has occurred.
       Discontinuities in the value of this counter can occur
       at re-initialization of the management system, and at other
       times as indicated by the value of ospfDiscontinuityTime."
     ::= { ospfNbrEntry 7 }
ospfNbrLsRetransQLen OBJECT-TYPE
    SYNTAX Gauge32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "The current length of the retransmission
       queue."
     ::= { ospfNbrEntry 8 }
ospfNbmaNbrStatus OBJECT-TYPE
    SYNTAX RowStatus
    MAX-ACCESS read-create
    STATUS
           current
    DESCRIPTION
       "This object permits management of the table by
       facilitating actions such as row creation,
       construction, and destruction.
       The value of this object has no effect on
       whether other objects in this conceptual row can be
       modified."
     ::= { ospfNbrEntry 9 }
ospfNbmaNbrPermanence OBJECT-TYPE
    SYNTAX INTEGER {
                    dynamic (1), -- learned through protocol
                    permanent (2) -- configured address
    MAX-ACCESS
               read-only
                 current
    DESCRIPTION
       "This variable displays the status of the entry;
       'dynamic' and 'permanent' refer to how the neighbor
       became known."
    DEFVAL { permanent }
    ::= { ospfNbrEntry 10 }
ospfNbrHelloSuppressed OBJECT-TYPE
    SYNTAX TruthValue
    MAX-ACCESS read-only
```

```
STATUS
                  current
      DESCRIPTION
         "Indicates whether Hellos are being suppressed
         to the neighbor."
      ::= { ospfNbrEntry 11 }
 ospfNbrRestartHelperStatus OBJECT-TYPE
                   INTEGER { notHelping (1),
                            helping (2)
      MAX-ACCESS read-only
      STATUS
                  current
      DESCRIPTION
         "Indicates whether the router is acting
         as a graceful restart helper for the neighbor."
         ::= { ospfNbrEntry 12 }
 ospfNbrRestartHelperAge OBJECT-TYPE
      SYNTAX Unsigned32
      UNITS
                  "seconds"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
         "Remaining time in current OSPF graceful restart
         interval, if the router is acting as a restart
         helper for the neighbor."
      ::= { ospfNbrEntry 13 }
 ospfNbrRestartHelperExitReason OBJECT-TYPE
                  INTEGER \{ none (1),
                                                -- not attempted
      SYNTAX
                                                -- restart in
                             inProgress (2),
                                                -- progress
                             completed (3),
                                                -- successfully
                                                -- completed
                             timedOut (4),
                                                -- timed out
                             topologyChanged (5) -- aborted due to
                                                -- topology
                                                -- change.
      MAX-ACCESS read-only
      STATUS
                  current
      DESCRIPTION
         "Describes the outcome of the last attempt at acting
          as a graceful restart helper for the neighbor."
      ::= { ospfNbrEntry 14 }
-- OSPF Virtual Neighbor Table
```

```
ospfVirtNbrTable OBJECT-TYPE
    SYNTAX SEQUENCE OF OspfVirtNbrEntry
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        "This table describes all virtual neighbors.
       Since virtual links are configured
       in the Virtual Interface Table, this table is read-only."
    REFERENCE
        "OSPF Version 2, Section 15 Virtual Links"
     ::= { ospf 11 }
ospfVirtNbrEntry OBJECT-TYPE
    SYNTAX OspfVirtNbrEntry
    MAX-ACCESS not-accessible
     STATUS
                 current
    DESCRIPTION
       "Virtual neighbor information."
     INDEX { ospfVirtNbrArea, ospfVirtNbrRtrId }
     ::= { ospfVirtNbrTable 1 }
OspfVirtNbrEntry ::=
     SEQUENCE {
       ospfVirtNbrArea
          AreaID,
       ospfVirtNbrRtrId
          RouterID,
        ospfVirtNbrIpAddr
          IpAddress,
        ospfVirtNbrOptions
          Integer32,
        ospfVirtNbrState
          INTEGER,
       ospfVirtNbrEvents
          Counter32,
        ospfVirtNbrLsRetransQLen
          Gauge32,
        ospfVirtNbrHelloSuppressed
          TruthValue,
        ospfVirtNbrRestartHelperStatus
          INTEGER,
        ospfVirtNbrRestartHelperAge
          Unsigned32,
        ospfVirtNbrRestartHelperExitReason
          INTEGER
        }
ospfVirtNbrArea OBJECT-TYPE
```

```
SYNTAX
               AreaID
    MAX-ACCESS read-only -- read-only since originally an
                          -- SMIv1 index
             current
    DESCRIPTION
       "The Transit Area Identifier."
     ::= { ospfVirtNbrEntry 1 }
ospfVirtNbrRtrId OBJECT-TYPE
    SYNTAX RouterID
    MAX-ACCESS read-only -- read-only since originally an
                         -- SMIv1 index
    STATUS current
    DESCRIPTION
       "A 32-bit integer uniquely identifying the
       neighboring router in the Autonomous System."
     ::= { ospfVirtNbrEntry 2 }
ospfVirtNbrIpAddr OBJECT-TYPE
    SYNTAX IpAddress
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "The IP address this virtual neighbor is using."
     ::= { ospfVirtNbrEntry 3 }
ospfVirtNbrOptions OBJECT-TYPE
    SYNTAX Integer32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "A bit mask corresponding to the neighbor's
       options field.
       Bit 1, if set, indicates that the system will
       operate on Type of Service metrics other than
       TOS 0. If zero, the neighbor will ignore all
       metrics except the TOS 0 metric.
       Bit 2, if set, indicates that the system is
       network multicast capable, i.e., that it
       implements OSPF multicast routing."
     ::= { ospfVirtNbrEntry 4 }
 ospfVirtNbrState OBJECT-TYPE
                INTEGER {
                    down (1),
                    attempt (2),
```

```
init (3),
                    twoWay (4),
                    exchangeStart (5),
                    exchange (6),
                    loading (7),
                    full (8)
    MAX-ACCESS
               read-only
    STATUS current
    DESCRIPTION
       "The state of the virtual neighbor relationship."
     ::= { ospfVirtNbrEntry 5 }
ospfVirtNbrEvents OBJECT-TYPE
    SYNTAX Counter32
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
       "The number of times this virtual link has
       changed its state or an error has occurred.
       Discontinuities in the value of this counter can occur
       at re-initialization of the management system, and at other
       times as indicated by the value of ospfDiscontinuityTime."
     ::= { ospfVirtNbrEntry 6 }
ospfVirtNbrLsRetransQLen OBJECT-TYPE
    SYNTAX Gauge32
    MAX-ACCESS read-only
    STATUS
            current
    DESCRIPTION
       "The current length of the retransmission
       queue."
     ::= { ospfVirtNbrEntry 7 }
ospfVirtNbrHelloSuppressed OBJECT-TYPE
    SYNTAX TruthValue
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "Indicates whether Hellos are being suppressed
       to the neighbor."
     ::= { ospfVirtNbrEntry 8 }
ospfVirtNbrRestartHelperStatus OBJECT-TYPE
                 INTEGER { notHelping (1),
                          helping (2)
                         }
```

```
MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
         "Indicates whether the router is acting
         as a graceful restart helper for the neighbor."
      ::= { ospfVirtNbrEntry 9 }
 ospfVirtNbrRestartHelperAge OBJECT-TYPE
      SYNTAX Unsigned32
      UNITS
                  "seconds"
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
         "Remaining time in current OSPF graceful restart
         interval, if the router is acting as a restart
         helper for the neighbor."
       ::= { ospfVirtNbrEntry 10 }
 ospfVirtNbrRestartHelperExitReason OBJECT-TYPE
      SYNTAX INTEGER { none (1), -- not attempted inProgress (2), -- restart in
                                                -- progress
                             completed (3), -- successfully
                                                -- completed
                             timedOut (4), -- timed out
                             topologyChanged (5) -- aborted due to
                                                -- topology
                                                -- change.
      MAX-ACCESS read-only
      STATUS
                   current
      DESCRIPTION
         "Describes the outcome of the last attempt at acting
          as a graceful restart helper for the neighbor."
       ::= { ospfVirtNbrEntry 11 }
-- OSPF Link State Database, External
 ospfExtLsdbTable OBJECT-TYPE
      SYNTAX SEQUENCE OF OspfextLsdbEntry
                 not-accessible
      MAX-ACCESS
      STATUS deprecated
      DESCRIPTION
         "The OSPF Process's external LSA link state database.
         This table is identical to the OSPF LSDB Table
         in format, but contains only external link state
         advertisements. The purpose is to allow external
```

```
LSAs to be displayed once for the router rather
       than once in each non-stub area.
       Note that external LSAs are also in the AS-scope link state
       database."
    REFERENCE
       "OSPF Version 2, Section 12 Link State Advertisements"
     ::= { ospf 12 }
ospfExtLsdbEntry OBJECT-TYPE
    SYNTAX OspfExtLsdbEntry
    MAX-ACCESS not-accessible
    STATUS deprecated
    DESCRIPTION
       "A single link state advertisement."
    INDEX { ospfExtLsdbType, ospfExtLsdbLsid, ospfExtLsdbRouterId }
     ::= { ospfExtLsdbTable 1 }
OspfExtLsdbEntry ::=
    SEQUENCE {
       ospfExtLsdbType
          INTEGER,
       ospfExtLsdbLsid
          IpAddress,
       ospfExtLsdbRouterId
          RouterID,
       ospfExtLsdbSequence
          Integer32,
       ospfExtLsdbAge
          Integer32,
        ospfExtLsdbChecksum
          Integer32,
        ospfExtLsdbAdvertisement
          OCTET STRING
        }
ospfExtLsdbType OBJECT-TYPE
    SYNTAX
               INTEGER {
                   asExternalLink (5)
                   }
    {\tt MAX-ACCESS} \quad {\tt read-only -- read-only since originally an} \\
                           -- SMIv1 index
    STATUS
            deprecated
    DESCRIPTION
        "The type of the link state advertisement.
       Each link state type has a separate advertisement
       format."
    REFERENCE
```

```
"OSPF Version 2, Appendix A.4.1 The Link State
       Advertisement header"
     ::= { ospfExtLsdbEntry 1 }
ospfExtLsdbLsid OBJECT-TYPE
    SYNTAX IpAddress
               read-only -- read-only since originally an
    MAX-ACCESS
                       -- SMIv1 index
    STATUS
                 deprecated
    DESCRIPTION
       "The Link State ID is an LS Type Specific field
       containing either a Router ID or an IP address;
       it identifies the piece of the routing domain
       that is being described by the advertisement."
    REFERENCE
       "OSPF Version 2, Section 12.1.4 Link State ID"
     ::= { ospfExtLsdbEntry 2 }
ospfExtLsdbRouterId OBJECT-TYPE
    SYNTAX RouterID
    MAX-ACCESS read-only -- read-only since originally an
                      -- SMIv1 index
    STATUS deprecated
    DESCRIPTION
       "The 32-bit number that uniquely identifies the
       originating router in the Autonomous System."
    REFERENCE
       "OSPF Version 2, Appendix C.1 Global parameters"
    ::= { ospfExtLsdbEntry 3 }
ospfExtLsdbSequence OBJECT-TYPE
    SYNTAX Integer32
    MAX-ACCESS read-only
    STATUS
                deprecated
    DESCRIPTION
       "The sequence number field is a signed 32-bit
       integer. It starts with the value '80000001'h,
       or -'7FFFFFFF'h, and increments until '7FFFFFFF'h.
       Thus, a typical sequence number will be very negative.
       It is used to detect old and duplicate link state
       advertisements. The space of sequence numbers is linearly
       ordered. The larger the sequence number, the more recent
       the advertisement."
    REFERENCE
       "OSPF Version 2, Section 12.1.6 LS sequence
     ::= { ospfExtLsdbEntry 4 }
```

```
ospfExtLsdbAge OBJECT-TYPE
      SYNTAX Integer32 -- Should be 0..MaxAge, except when
                            -- doNotAge bit is set
                  "seconds"
      UNITS
      MAX-ACCESS read-only
      STATUS
                  deprecated
      DESCRIPTION
         "This field is the age of the link state
         advertisement in seconds."
      REFERENCE
         "OSPF Version 2, Section 12.1.1 LS age"
      ::= { ospfExtLsdbEntry 5 }
 ospfExtLsdbChecksum OBJECT-TYPE
      SYNTAX Integer32
      MAX-ACCESS read-only
      STATUS
                  deprecated
      DESCRIPTION
         "This field is the checksum of the complete
         contents of the advertisement, excepting the
         age field. The age field is excepted so that
         an advertisement's age can be incremented
         without updating the checksum. The checksum
         used is the same that is used for ISO
         connectionless datagrams; it is commonly referred
         to as the Fletcher checksum."
      REFERENCE
         "OSPF Version 2, Section 12.1.7 LS checksum"
      ::= { ospfExtLsdbEntry 6 }
 ospfExtLsdbAdvertisement OBJECT-TYPE
      SYNTAX OCTET STRING (SIZE(36))
      MAX-ACCESS read-only
                  deprecated
      DESCRIPTION
         "The entire link state advertisement, including
         its header."
      REFERENCE
         "OSPF Version 2, Section 12 Link State
         Advertisements"
      ::= { ospfExtLsdbEntry 7 }
-- OSPF Use of the CIDR Route Table
 ospfRouteGroup OBJECT IDENTIFIER ::= { ospf 13 }
      The IP Forwarding Table defines a number of objects for use by
      the routing protocol to externalize its information. Most of
```

```
the variables (ipForwardDest, ipForwardMask, ipForwardPolicy,
      ipForwardNextHop, ipForwardIfIndex, ipForwardType,
      ipForwardProto, ipForwardAge, and ipForwardNextHopAS) are
      defined there.
      Those that leave some discretion are defined here.
      ipCidrRouteProto is, of course, ospf (13).
      ipCidrRouteAge is the time since the route was first
___
      calculated, as opposed to the time since the last SPF run.
      ipCidrRouteInfo is an OBJECT IDENTIFIER for use by the routing
      protocol. The following values shall be found there depending
      on the way the route was calculated.
 ospfIntraArea OBJECT IDENTIFIER ::= { ospfRouteGroup 1 } ospfInterArea OBJECT IDENTIFIER ::= { ospfRouteGroup 2 }
 ospfExternalType1 OBJECT IDENTIFIER ::= { ospfRouteGroup 3 }
 ospfExternalType2 OBJECT IDENTIFIER ::= { ospfRouteGroup 4 }
      ipCidrRouteMetric1 is, by definition, the primary routing
      metric. Therefore, it should be the metric that route
      selection is based on. For intra-area and inter-area routes,
      it is an OSPF metric. For External Type 1 (comparable value)
      routes, it is an OSPF metric plus the External Metric. For
      external Type 2 (non-comparable value) routes, it is the
--
      external metric.
      ipCidrRouteMetric2 is, by definition, a secondary routing
      metric. Therefore, it should be the metric that breaks a tie
___
      among routes having equal metric1 values and the same
      calculation rule. For intra-area, inter-area routes, and
      External Type 1 (comparable value) routes, it is unused. For
      External Type 2 (non-comparable value) routes, it is the metric
      to the AS border router.
      ipCidrRouteMetric3, ipCidrRouteMetric4, and ipCidrRouteMetric5
      are unused.
-- The OSPF Area Aggregate Table
      This table replaces the OSPF Area Summary Table, being an
      extension of that for CIDR routers.
  ospfAreaAggregateTable OBJECT-TYPE
      SYNTAX SEQUENCE OF OspfAreaAggregateEntry
      MAX-ACCESS not-accessible
      STATUS
                  current
```

DESCRIPTION

```
"The Area Aggregate Table acts as an adjunct
        to the Area Table. It describes those address aggregates
        that are configured to be propagated from an area.
        Its purpose is to reduce the amount of information
        that is known beyond an Area's borders.
        It contains a set of IP address ranges
        specified by an IP address/IP network mask pair.
        For example, a class B address range of X.X.X.X
        with a network mask of 255.255.0.0 includes all IP
        addresses from X.X.O.O to X.X.255.255.
        Note that if ranges are configured such that one range
        subsumes another range (e.g., 10.0.0.0 mask 255.0.0.0
        and 10.1.0.0 mask 255.255.0.0),
        the most specific match is the preferred one."
    REFERENCE
        "OSPF Version 2, Appendix C.2 Area parameters"
     ::= { ospf 14 }
ospfAreaAggregateEntry OBJECT-TYPE
    SYNTAX OspfAreaAggregateEntry
    MAX-ACCESS not-accessible
    STATUS current
    DESCRIPTION
        "A single area aggregate entry.
        Information in this table is persistent and when this object
       is written the entity SHOULD save the change to non-volatile
       storage."
    REFERENCE
        "OSPF Version 2, Appendix C.2 Area parameters"
     INDEX { ospfAreaAggregateAreaID, ospfAreaAggregateLsdbType,
       ospfAreaAggregateNet, ospfAreaAggregateMask }
     ::= { ospfAreaAggregateTable 1 }
OspfAreaAggregateEntry ::=
    SEQUENCE {
       ospfAreaAggregateAreaID
          AreaID,
        ospfAreaAggregateLsdbType
          INTEGER,
        ospfAreaAggregateNet
          IpAddress,
        ospfAreaAggregateMask
          IpAddress,
        ospfAreaAggregateStatus
```

```
RowStatus,
       ospfAreaAggregateEffect
          INTEGER,
       ospfAreaAggregateExtRouteTag
          Unsigned32
ospfAreaAggregateAreaID OBJECT-TYPE
            AreaID
    SYNTAX
    MAX-ACCESS read-only -- read-only since originally an
                          -- SMIv1 index
              current
    STATUS
    DESCRIPTION
       "The area within which the address aggregate is to be
       found."
    REFERENCE
        "OSPF Version 2, Appendix C.2 Area parameters"
     ::= { ospfAreaAggregateEntry 1 }
ospfAreaAggregateLsdbType OBJECT-TYPE
    SYNTAX
                 INTEGER {
                    summaryLink (3),
                    nssaExternalLink (7)
    MAX-ACCESS
                read-only -- read-only since originally an
                          -- SMIv1 index
             current
    STATUS
    DESCRIPTION
       "The type of the address aggregate. This field
       specifies the Lsdb type that this address
       aggregate applies to."
    REFERENCE
       "OSPF Version 2, Appendix A.4.1 The Link State
       Advertisement header"
     ::= { ospfAreaAggregateEntry 2 }
ospfAreaAggregateNet OBJECT-TYPE
    SYNTAX IpAddress
    MAX-ACCESS read-only -- read-only since originally an
                           -- SMIv1 index
    STATUS current
    DESCRIPTION
        "The IP address of the net or subnet indicated
       by the range."
    REFERENCE
       "OSPF Version 2, Appendix C.2 Area parameters"
     ::= { ospfAreaAggregateEntry 3 }
```

```
ospfAreaAggregateMask OBJECT-TYPE
    SYNTAX IpAddress
    MAX-ACCESS read-only -- read-only since originally an
                          -- SMIv1 index
    STATUS current
    DESCRIPTION
        "The subnet mask that pertains to the net or
       subnet."
    REFERENCE
       "OSPF Version 2, Appendix C.2 Area parameters"
     ::= { ospfAreaAggregateEntry 4 }
ospfAreaAggregateStatus OBJECT-TYPE
    SYNTAX RowStatus
    MAX-ACCESS read-create
    STATUS
                 current
    DESCRIPTION
       "This object permits management of the table by
       facilitating actions such as row creation,
       construction, and destruction.
       The value of this object has no effect on
       whether other objects in this conceptual row can be
       modified."
     ::= { ospfAreaAggregateEntry 5 }
ospfAreaAggregateEffect OBJECT-TYPE
    SYNTAX INTEGER {
                    advertiseMatching (1),
                    doNotAdvertiseMatching (2)
    MAX-ACCESS read-create
    STATUS
                 current
    DESCRIPTION
       "Subnets subsumed by ranges either trigger the
       advertisement of the indicated aggregate
       (advertiseMatching) or result in the subnet's not
       being advertised at all outside the area."
    DEFVAL { advertiseMatching }
     ::= { ospfAreaAggregateEntry 6 }
ospfAreaAggregateExtRouteTag OBJECT-TYPE
    SYNTAX
            Unsigned32
    MAX-ACCESS read-create
    STATUS current
    DESCRIPTION
        "External route tag to be included in NSSA (type-7)
        LSAs."
```

```
DEFVAL { 0 }
      ::= { ospfAreaAggregateEntry 7 }
-- OSPF Link State Database, link-local for non-virtual links
 ospfLocalLsdbTable OBJECT-TYPE
      SYNTAX
                  SEQUENCE OF OspfLocalLsdbEntry
                 not-accessible
      MAX-ACCESS
      STATUS current
      DESCRIPTION
         "The OSPF Process's link-local link state database
         for non-virtual links.
         This table is identical to the OSPF LSDB Table
         in format, but contains only link-local Link State
         Advertisements for non-virtual links. The purpose is
         to allow link-local LSAs to be displayed for each
         non-virtual interface. This table is implemented to
         support type-9 LSAs that are defined
         in 'The OSPF Opaque LSA Option'."
      REFERENCE
         "OSPF Version 2, Section 12 Link State Advertisements
         and The OSPF Opaque LSA Option"
       ::= { ospf 17 }
 ospfLocalLsdbEntry OBJECT-TYPE
      SYNTAX OspfLocalLsdbEntry
      MAX-ACCESS not-accessible
      STATUS current
      DESCRIPTION
         "A single link state advertisement."
      INDEX { ospfLocalLsdbIpAddress, ospfLocalLsdbAddressLessIf,
         ospfLocalLsdbType, ospfLocalLsdbLsid, ospfLocalLsdbRouterId
       ::= { ospfLocalLsdbTable 1 }
 OspfLocalLsdbEntry ::=
      SEQUENCE {
         ospfLocalLsdbIpAddress
            IpAddress,
         ospfLocalLsdbAddressLessIf
            InterfaceIndexOrZero,
         ospfLocalLsdbType
            INTEGER,
         ospfLocalLsdbLsid
            IpAddress,
         ospfLocalLsdbRouterId
            RouterID,
```

```
ospfLocalLsdbSequence
          Integer32,
        ospfLocalLsdbAge
          Integer32,
        ospfLocalLsdbChecksum
          Integer32,
        ospfLocalLsdbAdvertisement
          OCTET STRING
ospfLocalLsdbIpAddress OBJECT-TYPE
     SYNTAX
             IpAddress
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        "The IP address of the interface from
       which the LSA was received if the interface is
       numbered."
    REFERENCE
       "OSPF Version 2, Appendix C.3 Interface parameters"
     ::= { ospfLocalLsdbEntry 1 }
ospfLocalLsdbAddressLessIf OBJECT-TYPE
     SYNTAX InterfaceIndexOrZero
                not-accessible
    MAX-ACCESS
     STATUS current
    DESCRIPTION
        "The interface index of the interface from
       which the LSA was received if the interface is
       unnumbered."
    REFERENCE
        "OSPF Version 2, Appendix C.3 Interface parameters"
     ::= { ospfLocalLsdbEntry 2 }
ospfLocalLsdbType OBJECT-TYPE
    SYNTAX INTEGER { localOpaqueLink (9) }
    MAX-ACCESS not-accessible
     STATUS
                 current
    DESCRIPTION
        "The type of the link state advertisement.
       Each link state type has a separate
       advertisement format."
    REFERENCE
        "OSPF Version 2, Appendix A.4.1 The Link State
       Advertisement header"
     ::= { ospfLocalLsdbEntry 3 }
ospfLocalLsdbLsid OBJECT-TYPE
```

```
IpAddress
    SYNTAX
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
       "The Link State ID is an LS Type Specific field
       containing a 32-bit identifier in IP address format;
       it identifies the piece of the routing domain
       that is being described by the advertisement."
    REFERENCE
      "OSPF Version 2, Section 12.1.4 Link State ID"
    ::= { ospfLocalLsdbEntry 4 }
ospfLocalLsdbRouterId OBJECT-TYPE
    SYNTAX RouterID
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
       "The 32-bit number that uniquely identifies the
       originating router in the Autonomous System."
    REFERENCE
       "OSPF Version 2, Appendix C.1 Global parameters"
     ::= { ospfLocalLsdbEntry 5 }
ospfLocalLsdbSequence OBJECT-TYPE
    SYNTAX Integer32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "The sequence number field is a signed 32-bit
       integer. It starts with the value '80000001'h,
       or -'7FFFFFFF'h, and increments until '7FFFFFFF'h.
       Thus, a typical sequence number will be very negative.
       It is used to detect old and duplicate link state
       advertisements. The space of sequence numbers is linearly
       ordered. The larger the sequence number, the more recent
       the advertisement."
    REFERENCE
       "OSPF Version 2, Section 12.1.6 LS sequence
       number"
     ::= { ospfLocalLsdbEntry 6 }
ospfLocalLsdbAge OBJECT-TYPE
    SYNTAX Integer32 -- Should be 0..MaxAge, except when
                          -- doNotAge bit is set
    UNITS
                "seconds"
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
```

```
"This field is the age of the link state
         advertisement in seconds."
      REFERENCE
         "OSPF Version 2, Section 12.1.1 LS age"
       ::= { ospfLocalLsdbEntry 7 }
 ospfLocalLsdbChecksum OBJECT-TYPE
              Integer32
      SYNTAX
                 read-only
      MAX-ACCESS
      STATUS current
      DESCRIPTION
         "This field is the checksum of the complete
         contents of the advertisement, excepting the
         age field. The age field is excepted so that
         an advertisement's age can be incremented
         without updating the checksum. The checksum
         used is the same that is used for ISO
         connectionless datagrams; it is commonly referred
         to as the Fletcher checksum."
      REFERENCE
         "OSPF Version 2, Section 12.1.7 LS checksum"
       ::= { ospfLocalLsdbEntry 8 }
 ospfLocalLsdbAdvertisement OBJECT-TYPE
      SYNTAX OCTET STRING (SIZE (1..65535))
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
         "The entire link state advertisement, including
         its header.
         Note that for variable length LSAs, SNMP agents
         may not be able to return the largest string size."
      REFERENCE
         "OSPF Version 2, Section 12 Link State
         Advertisements"
       ::= { ospfLocalLsdbEntry 9 }
-- OSPF Link State Database, link-local for virtual Links
 ospfVirtLocalLsdbTable OBJECT-TYPE
      SYNTAX SEQUENCE OF OspfVirtLocalLsdbEntry
                 not-accessible
      MAX-ACCESS
      STATUS current
      DESCRIPTION
         "The OSPF Process's link-local link state database
         for virtual links.
```

```
This table is identical to the OSPF LSDB Table
        in format, but contains only link-local Link State
       Advertisements for virtual links. The purpose is to
        allow link-local LSAs to be displayed for each virtual
        interface. This table is implemented to support type-9 LSAs
        that are defined in 'The OSPF Opaque LSA Option'."
     REFERENCE
        "OSPF Version 2, Section 12 Link State
        Advertisements and The OSPF Opaque LSA Option"
     ::= { ospf 18 }
ospfVirtLocalLsdbEntry OBJECT-TYPE
     SYNTAX OspfVirtLocalLsdbEntry
    MAX-ACCESS not-accessible
     STATUS
                 current
    DESCRIPTION
        "A single link state advertisement."
     INDEX { ospfVirtLocalLsdbTransitArea,
       ospfVirtLocalLsdbNeighbor,
        ospfVirtLocalLsdbType,
        ospfVirtLocalLsdbLsid,
       ospfVirtLocalLsdbRouterId
     ::= { ospfVirtLocalLsdbTable 1 }
OspfVirtLocalLsdbEntry ::=
     SEQUENCE {
        ospfVirtLocalLsdbTransitArea
          AreaID,
        ospfVirtLocalLsdbNeighbor
          RouterID,
        ospfVirtLocalLsdbType
          INTEGER,
        ospfVirtLocalLsdbLsid
          IpAddress,
        ospfVirtLocalLsdbRouterId
          RouterID,
        ospfVirtLocalLsdbSequence
          Integer32,
        ospfVirtLocalLsdbAge
           Integer32,
        ospfVirtLocalLsdbChecksum
          Integer32,
        ospfVirtLocalLsdbAdvertisement
          OCTET STRING
ospfVirtLocalLsdbTransitArea OBJECT-TYPE
```

```
SYNTAX
                AreaID
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        "The transit area that the virtual link
       traverses. By definition, this is not 0.0.0.0."
    REFERENCE
        "OSPF Version 2, Appendix C.3 Interface parameters"
     ::= { ospfVirtLocalLsdbEntry 1 }
ospfVirtLocalLsdbNeighbor OBJECT-TYPE
    SYNTAX RouterID
    MAX-ACCESS not-accessible
                current
    STATUS
    DESCRIPTION
       "The Router ID of the virtual neighbor."
    REFERENCE
       "OSPF Version 2, Appendix C.3 Interface parameters"
     ::= { ospfVirtLocalLsdbEntry 2 }
ospfVirtLocalLsdbType OBJECT-TYPE
    SYNTAX INTEGER { localOpaqueLink (9) }
    MAX-ACCESS not-accessible
    STATUS
                 current
    DESCRIPTION
        "The type of the link state advertisement.
       Each link state type has a separate
       advertisement format."
    REFERENCE
       "OSPF Version 2, Appendix A.4.1 The Link State
       Advertisement header"
     ::= { ospfVirtLocalLsdbEntry 3 }
ospfVirtLocalLsdbLsid OBJECT-TYPE
    SYNTAX IpAddress
    MAX-ACCESS not-accessible
    STATUS
                current
    DESCRIPTION
        "The Link State ID is an LS Type Specific field
       containing a 32-bit identifier in IP address format;
       it identifies the piece of the routing domain
       that is being described by the advertisement."
    REFERENCE
        "OSPF Version 2, Section 12.1.4 Link State ID"
     ::= { ospfVirtLocalLsdbEntry 4 }
ospfVirtLocalLsdbRouterId OBJECT-TYPE
    SYNTAX RouterID
```

```
MAX-ACCESS not-accessible
    STATUS current
    DESCRIPTION
       "The 32-bit number that uniquely identifies the
       originating router in the Autonomous System."
       "OSPF Version 2, Appendix C.1 Global parameters"
     ::= { ospfVirtLocalLsdbEntry 5 }
ospfVirtLocalLsdbSequence OBJECT-TYPE
    SYNTAX Integer32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "The sequence number field is a signed 32-bit
       integer. It starts with the value '80000001'h,
       or -'7FFFFFFF'h, and increments until '7FFFFFFF'h.
       Thus, a typical sequence number will be very negative.
       It is used to detect old and duplicate link state
       advertisements. The space of sequence numbers is linearly
       ordered. The larger the sequence number, the more recent
       the advertisement."
    REFERENCE
       "OSPF Version 2, Section 12.1.6 LS sequence
     ::= { ospfVirtLocalLsdbEntry 6 }
ospfVirtLocalLsdbAge OBJECT-TYPE
    SYNTAX Integer32 -- Should be 0..MaxAge, except when
                          -- doNotAge bit is set
    UNITS
                "seconds"
    MAX-ACCESS read-only
    STATUS
                 current
    DESCRIPTION
       "This field is the age of the link state
       advertisement in seconds."
    REFERENCE
       "OSPF Version 2, Section 12.1.1 LS age"
     ::= { ospfVirtLocalLsdbEntry 7 }
ospfVirtLocalLsdbChecksum OBJECT-TYPE
    SYNTAX Integer32
    MAX-ACCESS read-only
    STATUS current
    DESCRIPTION
       "This field is the checksum of the complete
       contents of the advertisement, excepting the
       age field. The age field is excepted so that
```

```
an advertisement's age can be incremented
         without updating the checksum. The checksum
         used is the same that is used for ISO
         connectionless datagrams; it is commonly
         referred to as the Fletcher checksum."
      REFERENCE
         "OSPF Version 2, Section 12.1.7 LS checksum"
       ::= { ospfVirtLocalLsdbEntry 8 }
 ospfVirtLocalLsdbAdvertisement OBJECT-TYPE
      SYNTAX OCTET STRING (SIZE (1..65535))
      MAX-ACCESS read-only
      STATUS
                  current
      DESCRIPTION
         "The entire link state advertisement, including
         its header."
      REFERENCE
         "OSPF Version 2, Section 12 Link State
         Advertisements.
         Note that for variable length LSAs, SNMP agents
         may not be able to return the largest string size."
       ::= { ospfVirtLocalLsdbEntry 9 }
-- OSPF Link State Database, AS-scope
 ospfAsLsdbTable OBJECT-TYPE
      SYNTAX SEQUENCE OF OspfAsLsdbEntry
      MAX-ACCESS not-accessible
      STATUS
                  current
      DESCRIPTION
         "The OSPF Process's AS-scope LSA link state database.
          The database contains the AS-scope Link State
          Advertisements from throughout the areas that
          the device is attached to.
          This table is identical to the OSPF LSDB Table
          in format, but contains only AS-scope Link State
          Advertisements. The purpose is to allow AS-scope
          LSAs to be displayed once for the router rather
          than once in each non-stub area."
      REFERENCE
         "OSPF Version 2, Section 12 Link State
         Advertisements"
      ::= { ospf 19 }
 ospfAsLsdbEntry OBJECT-TYPE
      SYNTAX OspfAsLsdbEntry
```

```
MAX-ACCESS not-accessible
    STATUS current
    DESCRIPTION
        "A single link state advertisement."
    INDEX { ospfAsLsdbType, ospfAsLsdbLsid, ospfAsLsdbRouterId }
    ::= { ospfAsLsdbTable 1 }
OspfAsLsdbEntry ::=
    SEQUENCE {
       ospfAsLsdbType
          INTEGER,
       ospfAsLsdbLsid
          IpAddress,
       ospfAsLsdbRouterId
          RouterID,
       ospfAsLsdbSequence
          Integer32,
       ospfAsLsdbAge
          Integer32,
       ospfAsLsdbChecksum
          Integer32,
       ospfAsLsdbAdvertisement
          OCTET STRING
ospfAsLsdbType OBJECT-TYPE
    SYNTAX
                INTEGER {
                  asExternalLink (5),
                   asOpaqueLink (11)
    MAX-ACCESS not-accessible
    STATUS
                 current
    DESCRIPTION
        "The type of the link state advertisement.
       Each link state type has a separate
       advertisement format."
    REFERENCE
       "OSPF Version 2, Appendix A.4.1 The Link State
       Advertisement header"
     ::= { ospfAsLsdbEntry 1 }
ospfAsLsdbLsid OBJECT-TYPE
    SYNTAX IpAddress
    MAX-ACCESS not-accessible
    STATUS current
    DESCRIPTION
        "The Link State ID is an LS Type Specific field
       containing either a Router ID or an IP address;
```

```
it identifies the piece of the routing domain
       that is being described by the advertisement."
    REFERENCE
       "OSPF Version 2, Section 12.1.4 Link State ID"
     ::= { ospfAsLsdbEntry 2 }
ospfAsLsdbRouterId OBJECT-TYPE
    SYNTAX RouterID
               not-accessible
    MAX-ACCESS
    STATUS current
    DESCRIPTION
       "The 32-bit number that uniquely identifies the
       originating router in the Autonomous System."
    REFERENCE
       "OSPF Version 2, Appendix C.1 Global parameters"
     ::= { ospfAsLsdbEntry 3 }
ospfAsLsdbSequence OBJECT-TYPE
    SYNTAX Integer32
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
       "The sequence number field is a signed 32-bit
       integer. It starts with the value '80000001'h,
       or -'7FFFFFFF'h, and increments until '7FFFFFFF'h.
       Thus, a typical sequence number will be very negative.
       It is used to detect old and duplicate link state
       advertisements. The space of sequence numbers is linearly
       ordered. The larger the sequence number, the more recent
       the advertisement."
    REFERENCE
       "OSPF Version 2, Section 12.1.6 LS sequence
       number"
     ::= { ospfAsLsdbEntry 4 }
ospfAsLsdbAge OBJECT-TYPE
    SYNTAX Integer32 -- Should be 0..MaxAge, except when
                           -- doNotAge bit is set
                "seconds"
    MAX-ACCESS read-only
    STATUS
                current
    DESCRIPTION
        "This field is the age of the link state
       advertisement in seconds."
    REFERENCE
       "OSPF Version 2, Section 12.1.1 LS age"
    ::= { ospfAsLsdbEntry 5 }
```

```
ospfAsLsdbChecksum OBJECT-TYPE
     SYNTAX Integer32
     MAX-ACCESS read-only
     STATUS
                current
     DESCRIPTION
        "This field is the checksum of the complete
        contents of the advertisement, excepting the
        age field. The age field is excepted so that
        an advertisement's age can be incremented
        without updating the checksum. The checksum
        used is the same that is used for ISO
        connectionless datagrams; it is commonly referred
        to as the Fletcher checksum."
     REFERENCE
        "OSPF Version 2, Section 12.1.7 LS checksum"
     ::= { ospfAsLsdbEntry 6 }
ospfAsLsdbAdvertisement OBJECT-TYPE
     SYNTAX OCTET STRING (SIZE (1..65535))
     MAX-ACCESS read-only
     STATUS current
     DESCRIPTION
        "The entire link state advertisement, including
        its header."
        "OSPF Version 2, Section 12 Link State
        Advertisements.
        Note that for variable length LSAs, SNMP agents
        may not be able to return the largest string size."
     ::= { ospfAsLsdbEntry 7 }
-- OSPF Area LSA Counter Table
    ospfAreaLsaCountTable OBJECT-TYPE
        SYNTAX SEQUENCE OF OspfAreaLsaCountEntry
        MAX-ACCESS not-accessible
                   current
        DESCRIPTION
           "This table maintains per-area, per-LSA-type counters"
        ::= { ospf 20 }
    ospfAreaLsaCountEntry OBJECT-TYPE
        SYNTAX OspfAreaLsaCountEntry
        MAX-ACCESS not-accessible
        STATUS current
        DESCRIPTION
           "An entry with a number of link advertisements
```

```
of a given type for a given area."
         INDEX { ospfAreaLsaCountAreaId, ospfAreaLsaCountLsaType }
          ::= { ospfAreaLsaCountTable 1 }
     OspfAreaLsaCountEntry ::=
          SEQUENCE {
             ospfAreaLsaCountAreaId
                AreaID,
             ospfAreaLsaCountLsaType
                INTEGER,
             ospfAreaLsaCountNumber
                Gauge32
          }
     ospfAreaLsaCountAreaId OBJECT-TYPE
         SYNTAX AreaID
         MAX-ACCESS not-accessible
         STATUS
                    current
         DESCRIPTION
            "This entry Area ID."
         ::= { ospfAreaLsaCountEntry 1 }
     ospfAreaLsaCountLsaType OBJECT-TYPE
         SYNTAX INTEGER {
                         routerLink (1),
                         networkLink (2),
                         summaryLink (3),
                         asSummaryLink (4),
                         multicastLink (6),
                         nssaExternalLink (7),
                         areaOpaqueLink (10)
         MAX-ACCESS not-accessible
         STATUS
                      current
         DESCRIPTION
            "This entry LSA type."
         ::= { ospfAreaLsaCountEntry 2 }
     ospfAreaLsaCountNumber OBJECT-TYPE
         SYNTAX Gauge32
                    read-only
         MAX-ACCESS
         STATUS current
         DESCRIPTION
            "Number of LSAs of a given type for a given area."
         ::= { ospfAreaLsaCountEntry 3 }
-- conformance information
```

Galecki, et al.

Standards Track

```
ospfConformance OBJECT IDENTIFIER ::= { ospf 15 }
ospfGroups OBJECT IDENTIFIER ::= { ospfConformance 1 }
ospfCompliances OBJECT IDENTIFIER ::= { ospfConformance 2 }
-- compliance statements
  ospfCompliance MODULE-COMPLIANCE
       STATUS
              deprecated
      DESCRIPTION
          "The compliance statement for OSPF systems
         conforming to RFC 1850."
      MODULE -- this module
      MANDATORY-GROUPS {
          ospfBasicGroup,
          ospfAreaGroup,
          ospfStubAreaGroup,
          ospfIfGroup,
          ospfIfMetricGroup,
          ospfVirtIfGroup,
          ospfNbrGroup,
          ospfVirtNbrGroup,
          ospfAreaAggregateGroup
       GROUP ospfHostGroup
         DESCRIPTION
            "This group is mandatory for OSPF systems that support
            attached hosts."
       GROUP ospfLsdbGroup
         DESCRIPTION
             "This group is mandatory for OSPF systems that display
            their per-area link state database."
       GROUP ospfExtLsdbGroup
         DESCRIPTION
             "This group is mandatory for OSPF systems that display
            their external link state database."
       ::= { ospfCompliances 1 }
  ospfCompliance2 MODULE-COMPLIANCE
       STATUS
               current
       DESCRIPTION
          "The compliance statement."
              -- this module
      MODULE
      MANDATORY-GROUPS {
         ospfBasicGroup2,
         ospfAreaGroup2,
         ospfStubAreaGroup,
         ospfIfGroup2,
```

```
ospfIfMetricGroup,
       ospfVirtIfGroup2,
       ospfNbrGroup2,
       ospfVirtNbrGroup2,
       ospfAreaAggregateGroup2
    GROUP ospfHostGroup2
       DESCRIPTION
           "This group is mandatory for OSPF systems that support
          attached hosts."
    GROUP ospfLsdbGroup
        DESCRIPTION
           "This group is mandatory for OSPF systems that display
          their per-area link state database."
    GROUP ospfAsLsdbGroup
        DESCRIPTION
           "This group is mandatory for OSPF systems that display
          their AS-scope link state database."
    GROUP ospfLocalLsdbGroup
        DESCRIPTION
           "This group is mandatory for OSPF systems that display
          their per-link link state database for non-virtual
          links."
    GROUP ospfVirtLocalLsdbGroup
        DESCRIPTION
           "This group is mandatory for OSPF systems that display
          their per-link link state database for virtual links."
    GROUP ospfAreaLsaCountGroup
        DESCRIPTION
           "This group is mandatory for OSPF systems that display
          per-area, per-LSA-type counters."
     ::= { ospfCompliances 2 }
ospfComplianceObsolete MODULE-COMPLIANCE
    STATUS
                obsolete
    DESCRIPTION
       "Contains obsolete object groups."
                -- this module
    GROUP ospfAreaRangeGroup
       DESCRIPTION
           "This group is obsolete, and it is mandatory only
          for non-Classless Inter-Domain Routing (CIDR) OSPF
          systems that support multiple areas."
    GROUP ospfObsoleteGroup
       DESCRIPTION
           "This group contains obsolete objects,
          which are no longer required for OSPF systems."
     ::= { ospfCompliances 3 }
```

```
-- units of conformance
                 OBJECT-GROUP
 ospfBasicGroup
       OBJECTS {
         ospfRouterId,
         ospfAdminStat,
          ospfVersionNumber,
          ospfAreaBdrRtrStatus,
         ospfASBdrRtrStatus,
         ospfExternLsaCount,
         ospfExternLsaCksumSum,
         ospfTOSSupport,
         ospfOriginateNewLsas,
         ospfRxNewLsas,
         ospfExtLsdbLimit,
          ospfMulticastExtensions,
         ospfExitOverflowInterval,
         ospfDemandExtensions
       STATUS
                 deprecated
       DESCRIPTION
          "These objects are used to monitor/manage
         global OSPF parameters. This object group
         conforms to RFC 1850."
       ::= { ospfGroups 1 }
  ospfAreaGroup
                  OBJECT-GROUP
      OBJECTS {
         ospfAreaId,
         ospfImportAsExtern,
         ospfSpfRuns,
         ospfAreaBdrRtrCount,
          ospfAsBdrRtrCount,
         ospfAreaLsaCount,
         ospfAreaLsaCksumSum,
         ospfAreaSummary,
         ospfAreaStatus
       STATUS
                deprecated
      DESCRIPTION
          "These objects are used for OSPF systems
          supporting areas per RFC 1850."
       ::= { ospfGroups 2 }
  ospfStubAreaGroup OBJECT-GROUP
      OBJECTS {
         ospfStubAreaId,
         ospfStubTOS,
```

```
ospfStubMetric,
        ospfStubStatus,
        ospfStubMetricType
     STATUS
                 current
     DESCRIPTION
        "These objects are used for OSPF systems
        supporting stub areas."
     ::= { ospfGroups 3 }
 ospfLsdbGroup
                OBJECT-GROUP
     OBJECTS {
       ospfLsdbAreaId,
        ospfLsdbType,
        ospfLsdbLsid,
        ospfLsdbRouterId,
        ospfLsdbSequence,
        ospfLsdbAge,
        ospfLsdbChecksum,
        ospfLsdbAdvertisement
     STATUS
                  current
     DESCRIPTION
        "These objects are used for OSPF systems
        that display their link state database."
     ::= { ospfGroups 4 }
 ospfAreaRangeGroup OBJECT-GROUP
     OBJECTS {
       ospfAreaRangeAreaId,
        ospfAreaRangeNet,
        ospfAreaRangeMask,
        ospfAreaRangeStatus,
        ospfAreaRangeEffect
     STATUS obsolete
     DESCRIPTION
        "These objects are used for non-CIDR OSPF
        systems that support multiple areas. This
        object group is obsolete."
     ::= { ospfGroups 5 }
ospfHostGroup
                 OBJECT-GROUP
     OBJECTS {
       ospfHostIpAddress,
        ospfHostTOS,
        ospfHostMetric,
        ospfHostStatus,
```

```
ospfHostAreaID
        }
     STATUS
                  deprecated
     DESCRIPTION
        "These objects are used for OSPF systems
        that support attached hosts."
     ::= { ospfGroups 6 }
ospfIfGroup
             OBJECT-GROUP
     OBJECTS {
       ospfIfIpAddress,
        ospfAddressLessIf,
        ospfIfAreaId,
        ospfIfType,
        ospfIfAdminStat,
        ospfIfRtrPriority,
        ospfIfTransitDelay,
        ospfIfRetransInterval,
        ospfIfHelloInterval,
        ospfIfRtrDeadInterval,
        ospfIfPollInterval,
        ospfIfState,
        ospfIfDesignatedRouter,
        ospfIfBackupDesignatedRouter,
        ospfIfEvents,
        ospfIfAuthType,
        ospfIfAuthKey,
        ospfIfStatus,
        ospfIfMulticastForwarding,
        ospfIfDemand
     STATUS
                 deprecated
     DESCRIPTION
        "These objects are used to monitor/manage OSPF
        interfaces. This object group conforms to RFC 1850."
     ::= { ospfGroups 7 }
ospfIfMetricGroup OBJECT-GROUP
     OBJECTS {
        ospfIfMetricIpAddress,
        ospfIfMetricAddressLessIf,
        ospfIfMetricTOS,
        ospfIfMetricValue,
        ospfIfMetricStatus
        }
     STATUS
                 current
     DESCRIPTION
        "These objects are used for OSPF systems for supporting
```

```
interface metrics."
     ::= { ospfGroups 8 }
ospfVirtIfGroup
                OBJECT-GROUP
     OBJECTS {
        ospfVirtIfAreaId,
        ospfVirtIfNeighbor,
        ospfVirtIfTransitDelay,
        ospfVirtIfRetransInterval,
        ospfVirtIfHelloInterval,
        ospfVirtIfRtrDeadInterval,
        ospfVirtIfState,
        ospfVirtIfEvents,
        ospfVirtIfAuthType,
        ospfVirtIfAuthKey,
        ospfVirtIfStatus
      STATUS
                  deprecated
      DESCRIPTION
        "These objects are used for OSPF systems for supporting
       virtual interfaces. This object group conforms
       to RFC 1850."
      ::= { ospfGroups 9 }
ospfNbrGroup
               OBJECT-GROUP
     OBJECTS {
       ospfNbrIpAddr,
        ospfNbrAddressLessIndex,
        ospfNbrRtrId,
        ospfNbrOptions,
        ospfNbrPriority,
        ospfNbrState,
        ospfNbrEvents,
        ospfNbrLsRetransQLen,
        ospfNbmaNbrStatus,
        ospfNbmaNbrPermanence,
        ospfNbrHelloSuppressed
     STATUS
                 deprecated
     DESCRIPTION
        "These objects are used to monitor/manage OSPF neighbors.
        This object group conforms to RFC 1850."
     ::= { ospfGroups 10 }
ospfVirtNbrGroup
                 OBJECT-GROUP
     OBJECTS {
       ospfVirtNbrArea,
        ospfVirtNbrRtrId,
```

```
ospfVirtNbrIpAddr,
       ospfVirtNbrOptions,
       ospfVirtNbrState,
       ospfVirtNbrEvents,
       ospfVirtNbrLsRetransQLen,
        ospfVirtNbrHelloSuppressed
     STATUS
                 deprecated
    DESCRIPTION
        "These objects are used to monitor/manage OSPF virtual
       neighbors. This object group conforms to RFC 1850."
     ::= { ospfGroups 11 }
ospfExtLsdbGroup OBJECT-GROUP
    OBJECTS {
       ospfExtLsdbType,
       ospfExtLsdbLsid,
       ospfExtLsdbRouterId,
        ospfExtLsdbSequence,
       ospfExtLsdbAge,
        ospfExtLsdbChecksum,
       ospfExtLsdbAdvertisement
        }
    STATUS
                 deprecated
    DESCRIPTION
        "These objects are used for OSPF systems that display
        their link state database. This object group
        conforms to RFC 1850.
       This object group is replaced by the ospfAsLsdbGroup
        in order to support any AS-scope LSA type in a single
        table."
     ::= { ospfGroups 12 }
ospfAreaAggregateGroup OBJECT-GROUP
    OBJECTS {
       ospfAreaAggregateAreaID,
       ospfAreaAggregateLsdbType,
       ospfAreaAggregateNet,
       ospfAreaAggregateMask,
        ospfAreaAggregateStatus,
       ospfAreaAggregateEffect
        }
    STATUS
                deprecated
    DESCRIPTION
        "These objects are used for OSPF systems to support
       network prefix aggregation across areas."
```

```
::= { ospfGroups 13 }
ospfLocalLsdbGroup OBJECT-GROUP
     OBJECTS {
       ospfLocalLsdbSequence,
        ospfLocalLsdbAge,
        ospfLocalLsdbChecksum,
        ospfLocalLsdbAdvertisement
        }
     STATUS
               current
     DESCRIPTION
        "These objects are used for OSPF systems
        that display their link-local link state databases
        for non-virtual links."
      ::= { ospfGroups 14 }
ospfVirtLocalLsdbGroup OBJECT-GROUP
     OBJECTS {
       ospfVirtLocalLsdbSequence,
        ospfVirtLocalLsdbAge,
        ospfVirtLocalLsdbChecksum,
        ospfVirtLocalLsdbAdvertisement
      STATUS
                   current
      DESCRIPTION
         "These objects are used for OSPF systems
         that display their link-local link state databases
         for virtual links."
       ::= { ospfGroups 15 }
ospfAsLsdbGroup
                OBJECT-GROUP
     OBJECTS {
       ospfAsLsdbSequence,
        ospfAsLsdbAge,
        ospfAsLsdbChecksum,
        ospfAsLsdbAdvertisement
        }
      STATUS
                   current
      DESCRIPTION
         "These objects are used for OSPF systems
         that display their AS-scope link state database."
       ::= { ospfGroups 16 }
ospfBasicGroup2
                 OBJECT-GROUP
     OBJECTS {
       ospfRouterId,
        ospfAdminStat,
        {\tt ospfVersionNumber,}
```

```
ospfAreaBdrRtrStatus,
        ospfASBdrRtrStatus,
        ospfExternLsaCount,
        ospfExternLsaCksumSum,
        ospfTOSSupport,
        ospfOriginateNewLsas,
        ospfRxNewLsas,
        ospfExtLsdbLimit,
        ospfMulticastExtensions,
        ospfExitOverflowInterval,
        ospfDemandExtensions,
        ospfRFC1583Compatibility,
        ospfOpaqueLsaSupport,
        ospfReferenceBandwidth,
        ospfRestartSupport,
        ospfRestartInterval,
        ospfRestartStrictLsaChecking,
        ospfRestartStatus,
        ospfRestartAge,
        ospfRestartExitReason,
        ospfAsLsaCount,
        ospfAsLsaCksumSum,
        ospfStubRouterSupport,
        ospfStubRouterAdvertisement,
        ospfDiscontinuityTime
        }
     STATUS
                  current
    DESCRIPTION
        "These objects are used to monitor/manage OSPF global
       parameters."
     ::= { ospfGroups 17 }
ospfAreaGroup2
                 OBJECT-GROUP
    OBJECTS {
       ospfAreaId,
        ospfImportAsExtern,
        ospfSpfRuns,
        ospfAreaBdrRtrCount,
        ospfAsBdrRtrCount,
        ospfAreaLsaCount,
        ospfAreaLsaCksumSum,
        ospfAreaSummary,
        ospfAreaStatus,
        ospfAreaNssaTranslatorRole,
        ospfAreaNssaTranslatorState,
        ospfAreaNssaTranslatorStabilityInterval,
        ospfAreaNssaTranslatorEvents
        }
```

```
current
     STATUS
    DESCRIPTION
          "These objects are used by OSPF systems
          to support areas."
     ::= { ospfGroups 18 }
ospfIfGroup2
                OBJECT-GROUP
     OBJECTS {
        ospfIfIpAddress,
        ospfAddressLessIf,
        ospfIfAreald,
        ospfIfType,
        ospfIfAdminStat,
        ospfIfRtrPriority,
        ospfIfTransitDelay,
        ospfIfRetransInterval,
        ospfIfHelloInterval,
        ospfIfRtrDeadInterval,
        ospfIfPollInterval,
        ospfIfState,
        ospfIfDesignatedRouter,
        ospfIfBackupDesignatedRouter,
        ospfIfEvents,
        ospfIfAuthType,
        ospfIfAuthKey,
        ospfIfStatus,
        ospfIfMulticastForwarding,
        ospfIfDemand,
        ospfIfLsaCount,
        ospfIfLsaCksumSum
     STATUS
                 current
     DESCRIPTION
        "These objects are used to monitor/manage OSPF interfaces."
      ::= { ospfGroups 19 }
ospfVirtIfGroup2 OBJECT-GROUP
     OBJECTS {
        ospfVirtIfAreaId,
        ospfVirtIfNeighbor,
        ospfVirtIfTransitDelay,
        ospfVirtIfRetransInterval,
        ospfVirtIfHelloInterval,
        ospfVirtIfRtrDeadInterval,
        ospfVirtIfState,
        ospfVirtIfEvents,
        ospfVirtIfAuthType,
        ospfVirtIfAuthKey,
```

```
ospfVirtIfStatus,
        ospfVirtIfLsaCount,
        ospfVirtIfLsaCksumSum,
        ospfIfDesignatedRouterId,
        ospfIfBackupDesignatedRouterId
     STATUS
                  current
     DESCRIPTION
        "These objects are used to monitor/manage OSPF
        virtual interfaces."
     ::= { ospfGroups 20 }
ospfNbrGroup2
                OBJECT-GROUP
     OBJECTS {
        ospfNbrIpAddr,
        ospfNbrAddressLessIndex,
        ospfNbrRtrId,
        ospfNbrOptions,
        ospfNbrPriority,
        ospfNbrState,
        ospfNbrEvents,
        ospfNbrLsRetransQLen,
        ospfNbmaNbrStatus,
        ospfNbmaNbrPermanence,
        ospfNbrHelloSuppressed,
        ospfNbrRestartHelperStatus,
        ospfNbrRestartHelperAge,
        ospfNbrRestartHelperExitReason
        }
     STATUS
                 current
     DESCRIPTION
        "These objects are used to monitor/manage OSPF
        neighbors."
     ::= { ospfGroups 21 }
ospfVirtNbrGroup2 OBJECT-GROUP
     OBJECTS {
        ospfVirtNbrArea,
        ospfVirtNbrRtrId,
        ospfVirtNbrIpAddr,
        ospfVirtNbrOptions,
        ospfVirtNbrState,
        ospfVirtNbrEvents,
        ospfVirtNbrLsRetransQLen,
        ospfVirtNbrHelloSuppressed,
        ospfVirtNbrRestartHelperStatus,
        ospfVirtNbrRestartHelperAge,
        ospfVirtNbrRestartHelperExitReason
```

```
}
    STATUS
                current
    DESCRIPTION
       "These objects are used to monitor/manage OSPF
       virtual neighbors."
     ::= { ospfGroups 22 }
ospfAreaAggregateGroup2 OBJECT-GROUP
    OBJECTS {
       ospfAreaAggregateAreaID,
       ospfAreaAggregateLsdbType,
       ospfAreaAggregateNet,
       ospfAreaAggregateMask,
       ospfAreaAggregateStatus,
       ospfAreaAggregateEffect,
       ospfAreaAggregateExtRouteTag
    STATUS
                current
    DESCRIPTION
       "These objects are used for OSPF systems to support
       network prefix aggregation across areas."
     ::= { ospfGroups 23 }
ospfAreaLsaCountGroup OBJECT-GROUP
    OBJECTS {
       ospfAreaLsaCountNumber
       }
    STATUS
                current
    DESCRIPTION
       "These objects are used for OSPF systems that display
       per-area, per-LSA-type counters."
     ::= { ospfGroups 24 }
ospfHostGroup2
               OBJECT-GROUP
    OBJECTS {
       ospfHostIpAddress,
       ospfHostTOS,
       ospfHostMetric,
       ospfHostStatus,
       ospfHostCfgAreaID
       }
    STATUS
             current
    DESCRIPTION
        "These objects are used for OSPF systems
       that support attached hosts."
     ::= { ospfGroups 25 }
    This object group is included for SMI conformance. It is not a
```

Galecki, et al.

Standards Track

[Page 93]

-- mandatory group for compliance with this MIB

```
ospfObsoleteGroup OBJECT-GROUP
  OBJECTS {
    ospfAuthType
    }
  STATUS obsolete
  DESCRIPTION
    "These objects are obsolete and are no longer required for    OSPF systems. They are placed into this group for SMI    conformance."
  ::= { ospfGroups 26 }
```

END

4. OSPF Trap Overview

4.1. Introduction

OSPF is an event-driven routing protocol, where an event can be a change in an OSPF interface's link-level status, the expiration of an OSPF timer, or the reception of an OSPF protocol packet. Many of the actions that OSPF takes as a result of these events will result in a change of the routing topology.

As routing topologies become large and complex, it is often difficult to locate the source of a topology change or unpredicted routing path by polling a large number or routers. Because of the difficulty of polling a large number of devices, a more prudent approach is for devices to notify a network manager of potentially critical OSPF events using SNMP traps.

This section defines a set of traps, objects, and mechanisms to enhance the ability to manage IP internetworks that use OSPF as their Interior Gateway Protocol (IGP). It is an optional but very useful extension to the OSPF MIB.

Galecki, et al.

Standards Track

4.2. Approach

The mechanism for sending traps is straightforward. When an exception event occurs, the application notifies the local agent, who sends a trap to the appropriate SNMP management stations. The message includes the trap type and may include a list of trapspecific variables. Section 5 gives the trap definitions, which includes the variable lists. The Router ID of the originator of the trap is included in the variable list so that the network manager may easily determine the source of the trap.

To limit the frequency of OSPF traps, the following additional mechanisms are suggested.

4.3. Ignoring Initial Activity

The majority of critical events occur when OSPF is enabled on a router, at which time the designated router is elected and neighbor adjacencies are formed. During this initial period, a potential flood of traps is unnecessary since the events are expected. To avoid unnecessary traps, a router should not originate expected OSPF interface-related traps until two of that interface's dead timer intervals have elapsed. The expected OSPF interface traps are ospfIfStateChange, ospfVirtIfStateChange, ospfNbrStateChange, ospfVirtIfStateChange, ospfVirtIfTxRetransmit. Additionally, ospfMaxAgeLsa and ospfOriginateLsa traps should not be originated until two dead timer intervals have elapsed where the dead timer interval used should be the dead timer with the smallest value.

4.4. Throttling Traps

The mechanism for throttling the traps is similar to the mechanism explained in RFC 1224 [RFC1224]. The basic premise of the throttling mechanism is that of a sliding window, defined in seconds and an upper bound on the number of traps that may be generated within this window. Note that unlike RFC 1224, traps are not sent to inform the network manager that the throttling mechanism has kicked in.

A single window should be used to throttle all OSPF trap types except for the ospfLsdbOverflow and the ospfLsdbApproachingOverflow traps, which should not be throttled. For example, with a window time of 3, an upper bound of 3, and events to cause trap types 1, 3, 5, and 7 (4 traps within a 3-second period), the type-7 (the 4th) trap should not be generated.

Appropriate values are 7 traps with a window time of 10 seconds.

4.5. One Trap Per OSPF Event

Several of the traps defined in section 5 are generated as the result of finding an unusual condition while parsing an OSPF packet or a processing a timer event. There may be more than one unusual condition detected while handling the event. For example, a link state update packet may contain several retransmitted link state advertisements (LSAs), or a retransmitted database description packet may contain several database description entries. To limit the number of traps and variables, OSPF should generate at most one trap per OSPF event. Only the variables associated with the first unusual condition should be included with the trap. Similarly, if more than one type of unusual condition is encountered while parsing the packet, only the first event will generate a trap.

4.6. Polling Event Counters

Many of the tables in the OSPF MIB contain generalized event counters. By enabling the traps defined in this document, a network manager can obtain more specific information about these events. A network manager may want to poll these event counters and enable specific OSPF traps when a particular counter starts increasing abnormally.

The following table shows the relationship between the event counters defined in the OSPF MIB and the trap types.

Counter32	Trap Type
ospfOriginateNewLsas	ospf0riginateLsa
ospfIfEvents	ospfIfStateChange
	ospfConfigError
	ospfIfAuthFailure
	ospfRxBadPacket
	ospfTxRetransmit
ospfVirtIfEvents	${\tt ospfVirtIfStateChange}$
	${\tt ospfVirtIfConfigError}$
	${ t ospfVirtIfAuthFailure}$
	ospfVirtIfRxBadPacket
	${\tt ospfVirtIfTxRetransmit}$
ospfNbrEvents	ospfNbrStateChange
ospfVirtNbrEvents	ospfVirtNbrStateChange
ospfExternLSACount	ospfLsdbApproachingOverflo
ospfExternLSACount	ospfLsdbOverflow

4.7. Translating Notification Parameters

The definition of the OSPF notifications pre-dates the RFC 2578 [RFC2578] requirement of having a zero value for the penultimate sub-identifier for translating SNMPv2/SNMPv3 trap parameters to SNMPv1 trap parameters. RFC 3584 [RFC3584], section 3, defines the translation rules that can be implemented by intermediate proxyagents or multi-lingual agents to convert SNMPv2/SNMPv3 notifications to SNMPv1 notifications and vice versa. The conversion is not reversible, that is, a conversion to one SNMP version and then back again will result in an incorrectly formatted version of the notification.

According to the rules specified in RFC 3584, section 3.1, translation of OSPF notifications from SNMPv1 to SNMPv2/SNMPv3 would result in the SNMPv2/SNMPv3 snmpTrapOID being the concatenation of the SNMPv1 'enterprise' parameter and two additional sub-identifiers, '0' and the SNMPv1 'specific-trap' parameter.

According to the rules specified in RFC 3584, section 3.2, translation of OSPF notifications from SNMPv2/SNMPv3 to SNMPv1, as the notifications are defined in this MIB, would result in the SNMPv1 'enterprise' parameter being set to the SNMPv2/SNMPv3 snmpTrapOID parameter value with the last sub-identifier removed and the 'specific-trap' parameter being set to the last sub-identifier of the SNMPv2/SNMPv3 snmpTrapOID parameter.

Note that a notification originated from an SNMPv1 agent will not be converted into the same notification that would be originated from a native SNMPv2/SNMPv3 agent.

4.8. Historical Artifacts

The MIB modules that are updated by this document were originally written in SMIv1 for SNMPv1 when only traps were used. Since this version of the MIB module is written in SMIv2, it should be understood that all types of notifications, trap and inform PDUs, may be used by native SNMPv2 and SNMPv3 agents, although only traps are mentioned. Also, for backwards compatibility, the OSPF Trap module remains rooted at {ospf 16}.

Galecki, et al. Standards Track [Page 97]

5. OSPF Trap Definitions

OSPF-TRAP-MIB DEFINITIONS ::= BEGIN

IMPORTS

MODULE-IDENTITY, OBJECT-TYPE, NOTIFICATION-TYPE, IpAddress FROM SNMPv2-SMI

MODULE-COMPLIANCE, OBJECT-GROUP, NOTIFICATION-GROUP FROM SNMPv2-CONF

ospfRouterId, ospfIfIpAddress, ospfAddressLessIf, ospfIfState,
ospfVirtIfAreaId, ospfVirtIfNeighbor, ospfVirtIfState,
ospfNbrIpAddr, ospfNbrAddressLessIndex, ospfNbrRtrId,
ospfNbrState, ospfVirtNbrArea, ospfVirtNbrRtrId,
ospfVirtNbrState, ospfLsdbType, ospfLsdbLsid, ospfLsdbRouterId,
ospfLsdbAreaId, ospfExtLsdbLimit, ospf, ospfAreaId,
ospfAreaNssaTranslatorState, ospfRestartStatus,
ospfRestartInterval, ospfRestartExitReason,
ospfNbrRestartHelperStatus, ospfNbrRestartHelperAge,
ospfNbrRestartHelperExitReason, ospfVirtNbrRestartHelperExitReason
FROM OSPF-MIB;

ospfTrap MODULE-IDENTITY

LAST-UPDATED "200611100000Z" -- November 10, 2006 00:00:00 EST

ORGANIZATION "IETF OSPF Working Group"

CONTACT-INFO

"WG E-Mail: ospf@ietf.org

WG Chairs: acee@cisco.com

rohit@gmail.com

Editors: Dan Joyal

Nortel

600 Technology Park Drive Billerica, MA 01821 djoyal@nortel.com

Piotr Galecki

Airvana

19 Alpha Road

Chelmsford, MA 01824 pgalecki@airvana.com

Spencer Giacalone

CSFB

Eleven Madison Ave New York, NY 10010-3629 spencer.giacalone@gmail.com"

```
DESCRIPTION
          "The MIB module to describe traps for the OSPF
         Version 2 Protocol.
         Copyright (C) The IETF Trust (2006).
         This version of this MIB module is part of
         RFC 4750; see the RFC itself for full legal
         notices."
      REVISION "2006111000002" -- November 10, 2006 00:00:00 EST
      DESCRIPTION
          "Updated for latest changes to OSPFv2:
          -added graceful restart related traps
           -added new config error types
          -added ospfNssaTranslatorStatusChange trap.
          See Appendix B of RFC 4750 for more details.
         This version published as part of RFC 4750"
      REVISION "199501201225Z" -- Fri Jan 20 12:25:50 PST 1995
      DESCRIPTION
          "The initial SMIv2 revision of this MIB module, published
         in RFC 1850."
       ::= { ospf 16 }
-- Trap Support Objects
-- The following are support objects for the OSPF traps.
 ospfTrapControl OBJECT IDENTIFIER ::= { ospfTrap 1 }
 ospfTraps OBJECT IDENTIFIER ::= { ospfTrap 2 }
 ospfSetTrap OBJECT-TYPE
      SYNTAX OCTET STRING (SIZE(4))
      MAX-ACCESS read-write
      STATUS
              current
      DESCRIPTION
          "A 4-octet string serving as a bit map for
         the trap events defined by the OSPF traps. This
         object is used to enable and disable specific
         OSPF traps where a 1 in the bit field
         represents enabled. The right-most bit (least
         significant) represents trap 0.
         This object is persistent and when written
```

```
the entity SHOULD save the change to non-volatile
       storage."
      ::= { ospfTrapControl 1 }
ospfConfigErrorType OBJECT-TYPE
     SYNTAX
                 INTEGER {
                    badVersion (1),
                    areaMismatch (2),
                    unknownNbmaNbr (3), -- Router is DR eligible
                    unknownVirtualNbr (4),
                     authTypeMismatch(5),
                    authFailure (6),
                    netMaskMismatch (7),
                    helloIntervalMismatch (8),
                    deadIntervalMismatch (9),
                    optionMismatch (10),
                    mtuMismatch (11),
                    duplicateRouterId (12),
                    noError (13) }
    MAX-ACCESS read-only
     STATUS current
    DESCRIPTION
        "Potential types of configuration conflicts.
       Used by the ospfConfigError and
       ospfConfigVirtError\ traps. When the last value
       of a trap using this object is needed, but no
       traps of that type have been sent, this value
       pertaining to this object should be returned as
       noError."
     ::= { ospfTrapControl 2 }
ospfPacketType OBJECT-TYPE
                 INTEGER {
    SYNTAX
                    hello (1),
                    dbDescript (2),
                    lsReq(3),
                    lsUpdate (4),
                    lsAck (5),
                    nullPacket (6) }
    MAX-ACCESS read-only
     STATUS
                 current
     DESCRIPTION
        "OSPF packet types. When the last value of a trap
       using this object is needed, but no traps of
       that type have been sent, this value pertaining
       to this object should be returned as nullPacket."
     ::= { ospfTrapControl 3 }
```

```
ospfPacketSrc OBJECT-TYPE
      SYNTAX IpAddress
      MAX-ACCESS read-only
      STATUS current
      DESCRIPTION
          "The IP address of an inbound packet that cannot
         be identified by a neighbor instance. When
         the last value of a trap using this object is
         needed, but no traps of that type have been sent,
         this value pertaining to this object should
         be returned as 0.0.0.0."
       ::= { ospfTrapControl 4 }
-- Traps
 ospfVirtIfStateChange NOTIFICATION-TYPE
      OBJECTS { ospfRouterId, -- The originator of the trap
         ospfVirtIfAreaId,
         ospfVirtIfNeighbor,
         ospfVirtIfState -- The new state
      STATUS
                   current
      DESCRIPTION
         "An ospfVirtIfStateChange trap signifies that there
         has been a change in the state of an OSPF virtual
         interface.
         This trap should be generated when the interface
         state regresses (e.g., goes from Point-to-Point to Down)
         or progresses to a terminal state
         (i.e., Point-to-Point)."
       ::= { ospfTraps 1 }
 ospfNbrStateChange NOTIFICATION-TYPE
      OBJECTS { ospfRouterId, -- The originator of the trap
         ospfNbrIpAddr,
         ospfNbrAddressLessIndex,
         ospfNbrRtrId,
         ospfNbrState -- The new state
      STATUS
                   current
      DESCRIPTION
          "An ospfNbrStateChange trap signifies that
         there has been a change in the state of a
         non-virtual OSPF neighbor. This trap should be
         generated when the neighbor state regresses
         (e.g., goes from Attempt or Full to 1-Way or
         Down) or progresses to a terminal state (e.g.,
```

```
2-Way or Full). When an neighbor transitions
       from or to Full on non-broadcast multi-access
       and broadcast networks, the trap should be
       generated by the designated router. A designated
       router transitioning to Down will be noted by
       ospfIfStateChange."
     ::= { ospfTraps 2 }
ospfVirtNbrStateChange NOTIFICATION-TYPE
    OBJECTS { ospfRouterId, -- The originator of the trap
       ospfVirtNbrArea,
       ospfVirtNbrRtrId,
       ospfVirtNbrState -- The new state
    STATUS
                 current
    DESCRIPTION
        "An ospfVirtNbrStateChange trap signifies that there
       has been a change in the state of an OSPF virtual
       neighbor. This trap should be generated
       when the neighbor state regresses (e.g., goes
       from Attempt or Full to 1-Way or Down) or
       progresses to a terminal state (e.g., Full)."
     ::= { ospfTraps 3 }
ospfIfConfigError NOTIFICATION-TYPE
    OBJECTS { ospfRouterId, -- The originator of the trap
       ospfIfIpAddress,
       ospfAddressLessIf,
       ospfPacketSrc, -- The source IP address
       ospfConfigErrorType, -- Type of error
       ospfPacketType
     STATUS
                 current
    DESCRIPTION
        "An ospfIfConfigError trap signifies that a
       packet has been received on a non-virtual
       interface from a router whose configuration
       parameters conflict with this router's
       configuration parameters. Note that the event
       optionMismatch should cause a trap only if it
       prevents an adjacency from forming."
     ::= { ospfTraps 4 }
ospfVirtIfConfigError NOTIFICATION-TYPE
    OBJECTS { ospfRouterId, -- The originator of the trap
       ospfVirtIfAreaId,
       ospfVirtIfNeighbor,
       ospfConfigErrorType, -- Type of error
```

```
ospfPacketType
        }
     STATUS
                current
     DESCRIPTION
        "An ospfVirtIfConfigError trap signifies that a
        packet has been received on a virtual interface
        from a router whose configuration parameters
        conflict with this router's configuration
       parameters. Note that the event optionMismatch
        should cause a trap only if it prevents an
       adjacency from forming."
     ::= { ospfTraps 5 }
ospfIfAuthFailure NOTIFICATION-TYPE
     OBJECTS { ospfRouterId, -- The originator of the trap
        ospfIfIpAddress,
        ospfAddressLessIf,
        ospfPacketSrc, -- The source IP address
        ospfConfigErrorType, -- authTypeMismatch or
                            -- authFailure
        ospfPacketType
        }
     STATUS
                 current
    DESCRIPTION
        "An ospfIfAuthFailure trap signifies that a
       packet has been received on a non-virtual
       interface from a router whose authentication key
       or authentication type conflicts with this
        router's authentication key or authentication
        type."
     ::= { ospfTraps 6 }
ospfVirtIfAuthFailure NOTIFICATION-TYPE
     OBJECTS { ospfRouterId, -- The originator of the trap
       ospfVirtIfAreaId,
        ospfVirtIfNeighbor,
        ospfConfigErrorType, -- authTypeMismatch or
                            -- authFailure
        ospfPacketType
     STATUS
                 current
     DESCRIPTION
        "An ospfVirtIfAuthFailure trap signifies that a
        packet has been received on a virtual interface
        from a router whose authentication key or
        authentication type conflicts with this router's
        authentication key or authentication type."
```

```
::= { ospfTraps 7 }
ospfIfRxBadPacket NOTIFICATION-TYPE
     OBJECTS { ospfRouterId, -- The originator of the trap
       ospfIfIpAddress,
        ospfAddressLessIf,
        ospfPacketSrc, -- The source IP address
        ospfPacketType
        }
     STATUS
                  current
     DESCRIPTION
        "An ospfIfRxBadPacket trap signifies that an
        OSPF packet has been received on a non-virtual
        interface that cannot be parsed."
     ::= { ospfTraps 8 }
ospfVirtIfRxBadPacket NOTIFICATION-TYPE
     OBJECTS { ospfRouterId, -- The originator of the trap
       ospfVirtIfAreaId,
       ospfVirtIfNeighbor,
       ospfPacketType
       }
     STATUS
                  current
     DESCRIPTION
        "An ospfVirtIfRxBadPacket trap signifies that an OSPF
       packet has been received on a virtual interface
        that cannot be parsed."
     ::= { ospfTraps 9 }
ospfTxRetransmit NOTIFICATION-TYPE
     OBJECTS { ospfRouterId, -- The originator of the trap
        ospfIfIpAddress,
        ospfAddressLessIf,
        ospfNbrRtrId, -- Destination
        ospfPacketType,
        ospfLsdbType,
        ospfLsdbLsid,
        ospfLsdbRouterId
        }
      STATUS
                  current
      DESCRIPTION
         "An ospfTxRetransmit trap signifies than an
         OSPF packet has been retransmitted on a
         non-virtual interface. All packets that may be
         retransmitted are associated with an LSDB entry.
         The LS type, LS ID, and Router ID are used to
         identify the LSDB entry."
      ::= { ospfTraps 10 }
```

```
ospfVirtIfTxRetransmit NOTIFICATION-TYPE
    OBJECTS { ospfRouterId, -- The originator of the trap
       ospfVirtIfAreaId,
        ospfVirtIfNeighbor,
        ospfPacketType,
        ospfLsdbType,
        ospfLsdbLsid,
        ospfLsdbRouterId
        }
     STATUS
                 current
    DESCRIPTION
        "An ospfVirtIfTxRetransmit trap signifies than an
        OSPF packet has been retransmitted on a virtual
        interface. All packets that may be retransmitted
        are associated with an LSDB entry. The LS
        type, LS ID, and Router ID are used to identify
        the LSDB entry."
     ::= { ospfTraps 11 }
ospfOriginateLsa NOTIFICATION-TYPE
     OBJECTS { ospfRouterId, -- The originator of the trap
       ospfLsdbAreaId, -- 0.0.0.0 for AS Externals
        ospfLsdbType,
        ospfLsdbLsid,
        ospfLsdbRouterId
     STATUS
                  current
     DESCRIPTION
        "An ospfOriginateLsa trap signifies that a new
        LSA has been originated by this router. This
        trap should not be invoked for simple refreshes
        of LSAs (which happens every 30 minutes), but
        instead will only be invoked when an LSA is
        (re)originated due to a topology change.
        Additionally, this trap does not include LSAs that
        are being flushed because they have reached
        MaxAge."
     ::= { ospfTraps 12 }
ospfMaxAgeLsa NOTIFICATION-TYPE
     OBJECTS { ospfRouterId, -- The originator of the trap
        ospfLsdbAreaId, -- 0.0.0.0 for AS Externals
        ospfLsdbType,
        ospfLsdbLsid,
        ospfLsdbRouterId
        }
     STATUS
                current
     DESCRIPTION
```

```
"An ospfMaxAgeLsa trap signifies that one of
        the LSAs in the router's link state database has
        aged to MaxAge."
     ::= { ospfTraps 13 }
ospfLsdbOverflow NOTIFICATION-TYPE
     OBJECTS { ospfRouterId, -- The originator of the trap
        ospfExtLsdbLimit
     STATUS
                 current
     DESCRIPTION
        "An ospfLsdbOverflow trap signifies that the
        number of LSAs in the router's link state
        database has exceeded ospfExtLsdbLimit."
     ::= { ospfTraps 14 }
ospfLsdbApproachingOverflow NOTIFICATION-TYPE
     OBJECTS { ospfRouterId, -- The originator of the trap
       ospfExtLsdbLimit
     STATUS
                 current
     DESCRIPTION
        "An ospfLsdbApproachingOverflow trap signifies
        that the number of LSAs in the router's
        link state database has exceeded ninety percent of
        ospfExtLsdbLimit."
     ::= { ospfTraps 15 }
ospfIfStateChange NOTIFICATION-TYPE
     OBJECTS { ospfRouterId, -- The originator of the trap
        ospfIfIpAddress,
        ospfAddressLessIf,
        ospfIfState -- The new state
        }
     STATUS
                current
    DESCRIPTION
        "An ospfIfStateChange trap signifies that there
        has been a change in the state of a non-virtual
        OSPF interface. This trap should be generated
        when the interface state regresses (e.g., goes
        from Dr to Down) or progresses to a terminal
        state (i.e., Point-to-Point, DR Other, Dr, or
        Backup)."
     ::= { ospfTraps 16 }
ospfNssaTranslatorStatusChange NOTIFICATION-TYPE
    OBJECTS { ospfRouterId, -- The originator of the trap
```

```
ospfAreald,
        ospfAreaNssaTranslatorState -- The current translation
                                    -- status
     STATUS
                 current
     DESCRIPTION
        "An ospfNssaTranslatorStatusChange trap indicates that
        there has been a change in the router's ability to
        translate OSPF type-7 LSAs into OSPF type-5 LSAs.
        This trap should be generated when the translator
        status transitions from or to any defined status on
        a per-area basis."
     ::= { ospfTraps 17 }
ospfRestartStatusChange NOTIFICATION-TYPE
     OBJECTS { ospfRouterId, -- The originator of the trap
               ospfRestartStatus,
               ospfRestartInterval,
               ospfRestartExitReason
     STATUS
                  current
     DESCRIPTION
        "An ospfRestartStatusChange trap signifies that
        there has been a change in the graceful restart
        state for the router. This trap should be
        generated when the router restart status
        changes."
     ::= { ospfTraps 18 }
ospfNbrRestartHelperStatusChange NOTIFICATION-TYPE
     OBJECTS { ospfRouterId, -- The originator of the trap
               ospfNbrIpAddr,
               ospfNbrAddressLessIndex,
               ospfNbrRtrId,
               ospfNbrRestartHelperStatus,
               ospfNbrRestartHelperAge,
               ospfNbrRestartHelperExitReason
     STATUS
                current
     DESCRIPTION
        "An ospfNbrRestartHelperStatusChange trap signifies that
        there has been a change in the graceful restart
        helper state for the neighbor. This trap should be
        generated when the neighbor restart helper status
        transitions for a neighbor."
     ::= { ospfTraps 19 }
```

ospfVirtNbrRestartHelperStatusChange NOTIFICATION-TYPE

```
OBJECTS { ospfRouterId, -- The originator of the trap
               ospfVirtNbrArea,
               ospfVirtNbrRtrId,
               ospfVirtNbrRestartHelperStatus,
               ospfVirtNbrRestartHelperAge,
               ospfVirtNbrRestartHelperExitReason
      STATUS
                  current
      DESCRIPTION
         "An ospfVirtNbrRestartHelperStatusChange trap signifies
         that there has been a change in the graceful restart
         helper state for the virtual neighbor. This trap should
         be generated when the virtual neighbor restart helper
         status transitions for a virtual neighbor."
      ::= { ospfTraps 20 }
-- conformance information
ospfTrapConformance OBJECT IDENTIFIER ::= { ospfTrap 3 }
ospfTrapCompliances OBJECT IDENTIFIER ::= { ospfTrapConformance 2 }
-- compliance statements
ospfTrapCompliance MODULE-COMPLIANCE
    STATUS
           obsolete
    DESCRIPTION
       "The compliance statement."
    MODULE -- this module
    MANDATORY-GROUPS { ospfTrapControlGroup }
               ospfTrapControlGroup
    GROUP
    DESCRIPTION
       "This group is optional but recommended for all
       OSPF systems."
    ::= { ospfTrapCompliances 1 }
ospfTrapCompliance2 MODULE-COMPLIANCE
    STATUS current
    DESCRIPTION
       "The compliance statement."
    MODULE -- this module
    MANDATORY-GROUPS { ospfTrapControlGroup, ospfTrapEventGroup }
    OBJECT ospfConfigErrorType
    MIN-ACCESS accessible-for-notify
       "This object is only required to be supplied within
       notifications."
```

```
ospfPacketType
    OBJECT
    MIN-ACCESS accessible-for-notify
    DESCRIPTION
        "This object is only required to be supplied within
       notifications."
    OBJECT
                 ospfPacketSrc
    MIN-ACCESS accessible-for-notify
    DESCRIPTION
        "This object is only required to be supplied within
       notifications."
    ::= { ospfTrapCompliances 2 }
-- units of conformance
 ospfTrapControlGroup OBJECT-GROUP
      OBJECTS { ospfSetTrap,
                ospfConfigErrorType,
                ospfPacketType,
                ospfPacketSrc }
      STATUS
                   current
      DESCRIPTION
          "These objects are required to control traps
         from OSPF systems."
       ::= { ospfTrapGroups 1 }
 ospfTrapEventGroup
                         NOTIFICATION-GROUP
      NOTIFICATIONS {
         ospfVirtIfStateChange,
         ospfNbrStateChange,
         ospfVirtNbrStateChange,
         ospfIfConfigError,
         ospfVirtIfConfigError,
         ospfIfAuthFailure,
         ospfVirtIfAuthFailure,
         ospfIfRxBadPacket,
         ospfVirtIfRxBadPacket,
         ospfTxRetransmit,
         ospfVirtIfTxRetransmit,
         ospfOriginateLsa,
         ospfMaxAgeLsa,
         ospfLsdbOverflow,
         ospfLsdbApproachingOverflow,
         ospfIfStateChange,
         ospfNssaTranslatorStatusChange,
         ospfRestartStatusChange,
         ospfNbrRestartHelperStatusChange,
         ospfVirtNbrRestartHelperStatusChange
          }
```

END

6. Security Considerations

There are a number of management objects defined in this MIB that have a MAX-ACCESS clause of read-write and/or read-create. Such objects may be considered sensitive or vulnerable in some network environments. The support for SET operations in a non-secure environment without proper protection can have a negative effect on network operations.

It is recommended that attention be specifically given to implementing the MAX-ACCESS clause in a number of objects, including ospfIfAuthKey, ospfIfAuthType, ospfVirtIfAuthKey, and ospfVirtIfAuthType in scenarios that DO NOT use SNMPv3 strong security (i.e., authentication and encryption). Extreme caution must be used to minimize the risk of cascading security vulnerabilities when SNMPv3 strong security is not used. When SNMPv3 strong security is not used, these objects should have access of read-only, not read-create.

SNMPv1 by itself is not a secure environment. Even if the network itself is secure (for example by using IPsec), even then, there is no control as to who on the secure network is allowed to access and GET/SET (read/change/create/delete) the objects in this MIB.

It is recommended that the implementers consider the security features as provided by the SNMPv3 framework. Specifically, the use of the User-based Security Model RFC 3414 [RFC3414] and the View-based Access Control Model RFC 3415 [RFC3415] is recommended.

It is then a customer/user responsibility to ensure that the SNMP entity giving access to an instance of this MIB, is properly configured to give access to the objects only to those principals (users) that have legitimate rights to indeed GET or SET (change/create/delete) them.

Galecki, et al.

Standards Track

7. IANA Considerations

The MIB module in this document uses the following IANA-assigned OBJECT IDENTIFIER values recorded in the SMI Numbers registry:

Descriptor	OBJECT IDENTIFIER value
ospf	{ mib-2 14 }

8. Acknowledgements

This document was produced by the OSPF Working Group and is based on the MIB for OSPF version 2 by Rob Coltun and Fred Baker [RFC1850]. The editors would like to acknowledge John Moy, Rob Coltun, Randall Atkinson, David T. Perkins, Ken Chapman, Brian Field, Acee Lindem, Vishwas Manral, Roy Jose, Don Goodspeed, Vivek Dubey, Keith McCloghrie, Bill Fenner, and Dan Romascanu for their constructive comments.

9. References

9.1. Normative References

- [RFC2119] Bradner, S., "Key words for use in RFCs to Indicate Requirement Levels", BCP 14, RFC 2119, March 1997.

9.2 Informative References

- [RFC1224] Steinberg, L., "Techniques for managing asynchronously generated alerts", RFC 1224, May 1991.
- [RFC1704] Haller, N. and R. Atkinson, "On Internet Authentication", RFC 1704, October 1994.
- [RFC1765] Moy, J., "OSPF Database Overflow", RFC 1765, March 1995.

- [RFC1793] Moy, J., "Extending OSPF to Support Demand Circuits", RFC 1793, April 1995.
- [RFC1850] Baker, F. and R. Coltun, "OSPF Version 2 Management Information Base", RFC 1850, November 1995.
- [RFC2328] Moy, J., "OSPF Version 2", STD 54, RFC 2328, April 1998.
- [RFC2370] Coltun, R., "The OSPF Opaque LSA Option", RFC 2370, July 1998.
- [RFC3101] Murphy, P., "The OSPF Not-So-Stubby Area (NSSA) Option", RFC 3101, January 2003.
- [RFC3410] Case, J., Mundy, R., Partain, D., and B. Stewart,
 "Introduction and Applicability Statements for InternetStandard Management Framework", RFC 3410, December 2002.
- [RFC3414] Blumenthal, U. and B. Wijnen, "User-based Security Model (USM) for version 3 of the Simple Network Management Protocol (SNMPv3)", STD 62, RFC 3414, December 2002.
- [RFC3415] Wijnen, B., Presuhn, R., and K. McCloghrie, "View-based Access Control Model (VACM) for the Simple Network Management Protocol (SNMP)", STD 62, RFC 3415, December 2002.
- [RFC3623] Moy, J., Pillay-Esnault, P., and A. Lindem, "Graceful OSPF Restart", RFC 3623, November 2003.
- [RFC791] Postel, J., "Internet Protocol", STD 5, RFC 791, September 1981.
- [RFC3411] Harrington, D., Presuhn, R., and B. Wijnen, "An Architecture for Describing Simple Network Management Protocol (SNMP) Management Frameworks", STD 62, RFC 3411, December 2002.
- [RFC1583] Moy, J., "OSPF Version 2", RFC 1583, March 1994.

Appendix A. TOS Support

For backward compatibility with previous versions of the OSPF MIB specification, TOS-specific information has been retained in this document, though the TOS routing option has been deleted from OSPF [RFC2328].

Appendix B. Changes from RFC 1850

This section documents the differences between this memo and $\ensuremath{\mathsf{RFC}}$ 1850.

Appendix B.1. General Group Changes

Added object ospfRFC1583Compatibility to indicate support with "RFC 1583 Compatibility" [RFC1583]. This object has DEFVAL of "enabled".

Added object ospfReferenceBandwidth to allow configuration of a reference bandwidth for calculation of default interface metrics.

Added objects ospfRestartSupport, ospfRestartInterval, ospfRestartAge, ospfRestartStrictLsaChecking, and ospfRestartExitReason to support graceful restart.

Added objects ospfStubRouterSupport and ospfStubRouteAdvertisement to support stub routers.

Added object ospfDiscontinuityTime in order for a management entity to detect counter discontinuity events.

Appendix B.2. OSPF NSSA Enhancement Support

Added new objects to OspfAreaTable including the following:

- -ospfAreaNssaTranslatorRole to indicate the configured NSSA translation role.
- -ospfAreaNssaTranslatorState to indicate the current NSSA translation role.
- -ospfAreaNssaTranslatorStabilityInterval to indicate time to continue to perform at current translation status.
- -ospfAreaNssaTranslatorEvents to indicate the number of times OSPF translation state has changed.

Added new object ospfAreaAggregateExtRouteTag to ospfAreaAggregateTable.

Galecki, et al.

Standards Track

Added new object ospfNssaTranslatorStatusChange to ospfTraps in OSPF-TRAP-MIB DEFINITIONS.

Added ospfAreaId to IMPORTS in OSPF-TRAP-MIB DEFINITIONS to support ospfNssaTranslatorStatusChange.

Added ospfAreaExtNssaTranslatorStatus to IMPORTS in OSPF-TRAP-MIB DEFINITIONS to support ospfNssaTranslatorStatusChange.

Modified the DESCRIPTION clause of the ospfAreaSummary object in the ospfAreaTable to indicate support for NSSA.

Modified the DESCRIPTION clause of the ospfImportAsExtern object in the ospfAreaTable for clarity.

Appendix B.3. Opaque LSA Support

Added object ospfOpaqueLsaSupport to ospfGeneralGroup to indicate support of OSPF Opaque LSAs.

Created ospfLocalLsdbTable, for link-local (type-9) LSA support. This table is indexed by the following:

- -ospflocalLsdbIpAddress
- -ospfLocalLsdbAddressLessIf
- -ospfLocalLsdbType
- -ospfLocalLsdbLsid
- -ospfLocalLsdbRouterId

ospfLocalLsdbTable contains the following (columnar) objects:

- -ospfLocalLsdbSequence, to indicate LSA instance
- -ospfLocalLsdbAge
- -ospfLocalLsdbChecksum
- -ospfLocalLsdbAdvertisement, containing the entire LSA

Created ospfVirLocalLsdbTable, for link-local (type-9) LSA support on virtual links. This table is indexed by the following:

 $- {\tt ospfVirtLocalLsdbTransitArea}$

- -ospfVirtLocalLsdbNeighbor, to indicate the router ID of the virtual neighbor
- -ospfVirLocalLsdbType
- -ospfVirLocalLsdbLsid
- -ospfVirLocalLsdbRouterId
- ospfVirLocalLsdbTable contains the following (columnar) objects:
- -ospfVirLocalLsdbSequence, to indicate LSA instance
- -ospfVirLocalLsdbAge
- -ospfVirLocalLsdbChecksum
- -ospfVirLocalLsdbAdvertisement, containing the entire LSA

Added objects to ospfIfTable to support link-local (type-9) LSAs, including the following:

- -ospfIfLsaCount
- -ospfIfLsaCksumSum, to indicate the sum of the type-9 link state advertisement checksums on this interface

Added objects to ospfVirIfTable, to support link-local (type-9) LSAs on virtual links, including the following:

- -ospfVirIfLsaCount
- -ospfVirIfLsaCksumSum, to indicate the sum of the type-9 link state advertisement checksums on this link

To support area scope (type-10) LSAs, the enumeration areaOpaqueLink (10) was added to ospfLsdbType in the ospfLsdbTable.

Created ospfAsLsdbTable, for AS-scope LSA support. This table is indexed by the following:

- $-{\tt ospfAsLsdbType}$
- -ospfAsLsdbLsid
- -ospfAsLsdbRouterId

ospfAsLsdbTable contains the following (columnar) objects:

- -ospfAsLsdbSequence, to indicate LSA instance
- -ospfAsLsdbAge
- -ospfAsLsdbChecksum
- -ospfAsLsdbAdvertisement, containing the entire LSA

Appendix B.4. Graceful Restart Support

Added objects ospfRestartSupport, ospfRestartInterval, ospfRestartAge, ospfRestartStrictLsaChecking, and ospfRestartExitReason to general group.

Added objects ospfNbrRestartHelperStatus, ospfNbrRestartHelperAge, and ospfNbrRestartHelperExitReason to OspfNbrTable.

Added objects ospfVirtNbrRestartHelperStatus, ospfVirtNbrRestartHelperAge, and ospfVirtNbrRestartHelperExitReason to OspfVirtNbrTable.

Appendix B.5. OSPF Compliances

New compliance statements were added for new and for obsoleted conformance groups. These statements include the following:

- -ospfCompliance2
- -ospfComplianceObsolete

New conformance groups were created to support new objects added to the group. These groups include the following:

- -ospfBasicGroup2
- -ospfAreaGroup2
- -ospfIfGroup2
- -ospfVirtIfGroup2
- -ospfNbrGroup2
- -ospfVirtNbrGroup2
- -ospfAreaAggregateGroup2

Added completely new conformance groups, including the following:

Galecki, et al.

- -ospfLocalLsdbGroup, which specifies support for link-local (type-9) LSAs
- -ospfVirtLocalLsdbGroup, which specifies support for link-local (type-9) LSAs on virtual links
- -ospfObsoleteGroup, for obsolete objects and SMI compatibility

Appendix B.6. OSPF Authentication and Security

As there has been significant concern in the community regarding cascading security vulnerabilities, the following changes have been incorporated:

- -Modified the DESCRIPTION clause of ospfIfAuthKey due to security concerns and to increase clarity
- -Modified the DESCRIPTION clause of ospfVirtIfAuthKey due to security concerns and to increase clarity
- -Modified the DESCRIPTION clause of ospfIfAuthType due to security concerns and to increase clarity
- -Modified the DESCRIPTION clause of ospfVirtIfType due to security concerns and to increase clarity
- -Modified the OSPF MIB MODULE DESCRIPTION due to security concerns and to include a reference to the Security Considerations section in this document that will transcend compilation
- -Modified the Security Considerations section to provide detail

Appendix B.7. OSPF Trap MIB

Added ospfTrapEventGroup.

Added importation of NOTIFICATION-GROUP.

Changed the STATUS of the ospfTrapCompliance MODULE-COMPLIANCE construct to obsolete.

Added ospfTrapCompliance2 MODULE-COMPLIANCE construct, which replaces ospfTrapCompliance. OspfTrapCompliance includes an updated MANDATORY-GROUPS clause and new MIN-ACCESS specifications.

Added mtuMismatch enumeration to ospfConfigErrorType object in ospfTrapControl to imply MTU mismatch trap generation. in ospfIfConfigError.

Galecki, et al.

Standards Track

Added noError enumeration to ospfConfigErrorType object for situations when traps are requested but none have been sent. Updated the DESCRIPTION clause accordingly.

Added nullPacket enumeration to ospfPacketType object for situations when traps are requested but none have been sent. Updated the DESCRIPTION clause accordingly.

Updated the DESCRIPTION clause of ospfPacketSrc for situations when traps are requested, but none have been sent.

Added NOTIFICATION-TYPE for ospfRestartStatusChange.

Added NOTIFICATION-TYPE for ospfNbrRestartHelperStatusChange.

Added NOTIFICATION-TYPE for ospfVirtNbrRestartHelperStatusChange.

Appendix B.8. Miscellaneous

Various sections have been moved or modified for clarity. Most of these changes are semantic in nature and include, but are not limited to the following:

- -The OSPF overview section's format was revised. Unneeded information was removed. Removed information includes OSPF TOS default values.
- -The trap overview section's format and working were revised. Unneeded information was removed.
- -Modified the DESCRIPTION clause of "Status" "TEXTUAL-CONVENTION" for clarity.
- -The Updates section was moved from the overview to its own section.
- -Updated "REFERENCE" clauses in all objects, as needed.
- -Modified the SEQUENCE of the OspfIfTable to reflect the true order of the objects in the table.
- -Modified the DESCRIPTION clause of all row management objects for clarity.

Added ospfHostCfgAreaID to object to Host table with read-create access. Deprecated ospfHostAreaID.

Added importation of InterfaceIndexOrZero from IF-MIB. This TEXTUAL-CONVENTION will replace the InterfaceIndex TEXTUAL-CONVENTION.

Changed the SYNTAX clause of ospfNbrAddressLessIndex to use the semantically identical InterfaceIndexOrZero TEXTUAL-CONVENTION, as permitted by the SMI.

Changed the STATUS clause of the TEXTUAL-CONVENTION InterfaceIndex to obsolete and modified the DESCRIPTION accordingly.

Changed the SYNTAX clause of ospfAddressLessIf to use the semantically identical InterfaceIndexOrZero TEXTUAL-CONVENTION, as permitted by the SMI.

Changed the SYNTAX clause of ospfIfMetricAddressLessIf to use the semantically identical InterfaceIndexOrZero TEXTUAL-CONVENTION, as permitted by the SMI.

Changed importation of mib-2 from RFC1213-MIB to SNMPv2-SMI

Added Intellectual Property Rights section.

Updated REVISION DESCRIPTION clauses with description of major MIB modifications.

Moved all relevant MIB comments to objects' DESCRIPTION clauses.

Added reasoning for object deprecation.

Added persistence information for read-write, read-create objects.

Described conditions when columns can be modified in RowStatus managed rows as required by RFC 2579.

Defined OspfAuthenticationType TC and modified authentication type objects to use the new type.

Made index objects of new tables not accessible.

Added the UNITS clause to several objects.

Added the area LSA counter table.

Added IANA Considerations section.

Authors' Addresses

Dan Joyal (Editor) Nortel, Inc. 600 Technology Park Drive Billerica, MA 01821 USA

EMail: djoyal@nortel.com

Piotr Galecki (Editor) Airvana, Inc. 19 Alpha Road Chelmsford, MA 01824 USA

EMail: pgalecki@airvana.com

Spencer Giacalone (Editor) CSFB Eleven Madison Ave New York, NY 10010-3629 USA

EMail: spencer.giacalone@gmail.com

Fred Baker Cisco Systems 1121 Via Del Rey Santa Barbara, California 93117 USA

EMail: fred@cisco.com

Rob Coltun Touch Acoustra 3204 Brooklawn Terrace Chevy Chase, MD 20815 USA

EMail: undisclosed

Full Copyright Statement

Copyright (C) The IETF Trust (2006).

This document is subject to the rights, licenses and restrictions contained in BCP 78, and except as set forth therein, the authors retain all their rights.

This document and the information contained herein are provided on an "AS IS" basis and THE CONTRIBUTOR, THE ORGANIZATION HE/SHE REPRESENTS OR IS SPONSORED BY (IF ANY), THE INTERNET SOCIETY, THE IETF TRUST, AND THE INTERNET ENGINEERING TASK FORCE DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Intellectual Property

The IETF takes no position regarding the validity or scope of any Intellectual Property Rights or other rights that might be claimed to pertain to the implementation or use of the technology described in this document or the extent to which any license under such rights might or might not be available; nor does it represent that it has made any independent effort to identify any such rights. Information on the procedures with respect to rights in RFC documents can be found in BCP 78 and BCP 79.

Copies of IPR disclosures made to the IETF Secretariat and any assurances of licenses to be made available, or the result of an attempt made to obtain a general license or permission for the use of such proprietary rights by implementers or users of this specification can be obtained from the IETF on-line IPR repository at http://www.ietf.org/ipr.

The IETF invites any interested party to bring to its attention any copyrights, patents or patent applications, or other proprietary rights that may cover technology that may be required to implement this standard. Please address the information to the IETF at ietf-ipr@ietf.org.

Acknowledgement

Funding for the RFC Editor function is currently provided by the Internet Society.