Network Working Group Request for Comments: 2213 Category: Standards Track F. Baker
Cisco Systems
J. Krawczyk
ArrowPoint Communications
A. Sastry
Cisco Systems
September 1997

Integrated Services Management Information Base using SMIv2

Status of this Memo

This document specifies an Internet standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "Internet Official Protocol Standards" (STD 1) for the standardization state and status of this protocol. Distribution of this memo is unlimited.

Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in TCP/IP-based internets. In particular, it defines objects for managing the the interface attributes defined in the Integrated Services Model. Comments should be made to the Integrated Services Working Group, int-serv@isi.edu.

Table of Contents

1 The SNMPv2 Network Management Framework	2
1.1 Object Definitions	2
2 Overview	2
2.1 Textual Conventions	2
2.2 Structure of MIB	3
3 Definitions	3
3.2 Interface Attributes Database	6
3.3 Integrated Services Interface Flows Database	8
4 Security Considerations	19
5 Authors' Addresses	2 (
6 Acknowledgements	2 (
7 References	2 (

Baker, et. al. Standards Track [Page 1]

1. The SNMPv2 Network Management Framework

The SNMPv2 Network Management Framework consists of four major components. They are:

- o RFC 1441 which defines the SMI, the mechanisms used for describing and naming objects for the purpose of management.
- o STD 17, RFC 1213 defines MIB-II, the core set of managed objects for the Internet suite of protocols.
- o RFC 1445 which defines the administrative and other architectural aspects of the framework.
- o RFC 1448 which defines the protocol used for network access to managed objects.

The Framework permits new objects to be defined for the purpose of experimentation and evaluation.

1.1. Object Definitions

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. Objects in the MIB are defined using the subset of Abstract Syntax Notation One (ASN.1) defined in the SMI. In particular, each object type is named by an OBJECT IDENTIFIER, an administratively assigned name. The object type together with an object instance serves to uniquely identify a specific instantiation of the object. For human convenience, we often use a textual string, termed the descriptor, to refer to the object type.

2. Overview

2.1. Textual Conventions

Several new data types are introduced as a textual convention in this MIB document. These textual conventions enhance the readability of the specification and can ease comparison with other specifications if appropriate. It should be noted that the introduction of the these textual conventions has no effect on either the syntax nor the semantics of any managed objects. The use of these is merely an

artifact of the explanatory method used. Objects defined in terms of one of these methods are always encoded by means of the rules that define the primitive type. Hence, no changes to the SMI or the SNMP are necessary to accommodate these textual conventions which are adopted merely for the convenience of readers and writers in pursuit of the elusive goal of clear, concise, and unambiguous MIB documents.

2.2. Structure of MIB

The MIB is composed of the following sections:
 Integrated Services
 Interface Attributes Table
 Interface Flow Table

3. Definitions

INTEGRATED-SERVICES-MIB DEFINITIONS ::= BEGIN

IMPORTS

MODULE-IDENTITY, OBJECT-TYPE, Counter32,
Gauge32, Integer32, mib-2 FROM SNMPv2-SMI
TimeInterval, TEXTUAL-CONVENTION, RowStatus,
TruthValue FROM SNMPv2-TC
MODULE-COMPLIANCE, OBJECT-GROUP FROM SNMPv2-CONF
ifIndex, InterfaceIndex FROM IF-MIB;

-- This MIB module uses the extended OBJECT-TYPE macro as -- defined in [9].

intSrv MODULE-IDENTITY

LAST-UPDATED "9511030500Z" -- Thu Aug 28 09:04:13 PDT 1997 ORGANIZATION "IETF Integrated Services Working Group" CONTACT-INFO

" Fred Baker
Postal: Cisco Systems
519 Lado Drive

Santa Barbara, California 93111

Tel: +1 805 681 0115 E-Mail: fred@cisco.com

John Krawczyk

Postal: ArrowPoint Communications

235 Littleton Road

Westford, Massachusetts 01886

Tel: +1 508 692 5875 E-Mail: jjk@tiac.net"

DESCRIPTION

"The MIB module to describe the Integrated Services

```
Protocol"
    ::= { mib-2 52 }
                       OBJECT IDENTIFIER ::= { intSrv 1 }
intSrvObjects
intSrvObjects
OBJECT IDENTIFIER :- { IntSrv 1 }
intSrvGenObjects
OBJECT IDENTIFIER ::= { intSrv 2 }
intSrvNotifications
OBJECT IDENTIFIER ::= { intSrv 3 }
intSrvConformance
OBJECT IDENTIFIER ::= { intSrv 4 }
-- Textual Conventions
    SessionNumber ::= TEXTUAL-CONVENTION
        STATUS
                current
        DESCRIPTION
            "The Session Number convention is used for
            numbers identifying sessions or saved PATH or
           RESV information. It is a number in the range
           returned by a TestAndIncr variable, having no
           protocol meaning whatsoever but serving instead
           as simple identifier.
            The alternative was a very complex instance or
            instance object that became unwieldy."
       SYNTAX INTEGER (0..2147483647)
    Protocol ::= TEXTUAL-CONVENTION
        DISPLAY-HINT "d"
        STATUS current
        DESCRIPTION
            "The value of the IP Protocol field of an IP
            Datagram Header. This identifies the protocol
            layer above IP. For example, the value 6 is
            used for TCP and the value 17 is used for UDP.
            The values of this field are defined in the As-
            signed Numbers RFC."
       SYNTAX INTEGER (1..255)
    SessionType ::= TEXTUAL-CONVENTION
        STATUS current
        DESCRIPTION
            "The value of the C-Type field of a Session ob-
            ject, as defined in the RSVP specification.
            This value determines the lengths of octet
            strings and use of certain objects such as the
```

'port' variables. If the C-Type calls for an IP6 address, one would expect all source, des-

tination, and next/previous hop addresses to be 16 bytes long, and for the ports to be UDP/TCP port numbers, for example." SYNTAX INTEGER (1..255)

Port ::= TEXTUAL-CONVENTION

DISPLAY-HINT "d" STATUS current DESCRIPTION

> "The value of the UDP or TCP Source or Destination Port field, a virtual destination port or generalized port identifier used with the IPSEC Authentication Header or Encapsulating Security Payload, or other session discriminator. If it is not used, the value should be of length 0. This pair, when coupled with the IP Addresses of the source and destination system and the IP protocol field, uniquely identifies a data stream."

SYNTAX OCTET STRING (SIZE(2..4))

MessageSize ::= TEXTUAL-CONVENTION

DISPLAY-HINT "d" STATUS current

DESCRIPTION

"The size of a message in bytes. This is used to specify the minimum and maximum size of a message along an integrated services route."

SYNTAX INTEGER (0...'7FFFFFFF'h)

BitRate ::= TEXTUAL-CONVENTION

DISPLAY-HINT "d" STATUS current DESCRIPTION

> "The rate, in bits/second, that data may move in the context. Applicable contexts minimally include the speed of an interface or virtual circuit, the data rate of a (potentially aggregated) data flow, or the data rate to be allocated for use by a flow."

SYNTAX INTEGER (0...'7FFFFFFF'h)

BurstSize ::= TEXTUAL-CONVENTION

DISPLAY-HINT "d" STATUS current DESCRIPTION

```
"The number of octets of IP Data, including IP
          Headers, that a stream may send without concern
          for policing."
       SYNTAX INTEGER (0...'7FFFFFFF'h)
   QosService ::= TEXTUAL-CONVENTION
        STATUS current
        DESCRIPTION
          "The class of service in use by a flow."
       SYNTAX INTEGER {
                  bestEffort (1),
                                         -- Best Effort Service
                  guaranteedDelay (2), -- Guaranteed Delay
controlledLoad (5) -- Controlled Load
       The Integrated Services Interface Attributes Database contains
       information about resources allocated by resource reservation
       protocols, such as RSVP and ST-II.
   intSrvIfAttribTable OBJECT-TYPE
       SYNTAX SEQUENCE OF IntSrvIfAttribEntry
       MAX-ACCESS not-accessible
       STATUS current
       DESCRIPTION
          "The reservable attributes of the system's in-
          terfaces."
       ::= { intSrvObjects 1 }
   intSrvIfAttribEntry OBJECT-TYPE
       SYNTAX IntSrvIfAttribEntry
       MAX-ACCESS not-accessible
       STATUS
                   current
       DESCRIPTION
          "The reservable attributes of a given inter-
       INDEX { ifIndex }
       ::= { intSrvIfAttribTable 1 }
IntSrvIfAttribEntry ::=
   SEQUENCE {
       intSrvIfAttribAllocatedBits
                                     BitRate,
       intSrvIfAttribMaxAllocatedBits BitRate,
       intSrvIfAttribAllocatedBuffer BurstSize,
       intSrvIfAttribFlows
                                       Gauge32,
       intSrvIfAttribPropagationDelay Integer32,
```

```
intSrvIfAttribStatus
                                 RowStatus
}
intSrvIfAttribAllocatedBits OBJECT-TYPE
   SYNTAX BitRate
   UNITS
             "Bits per second"
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
      "The number of bits/second currently allocated
      to reserved sessions on the interface."
   ::= { intSrvIfAttribEntry 1 }
intSrvIfAttribMaxAllocatedBits OBJECT-TYPE
   SYNTAX BitRate
              "Bits per second"
   UNITS
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The maximum number of bits/second that may be
      allocated to reserved sessions on the inter-
      face."
   ::= { intSrvIfAttribEntry 2 }
intSrvIfAttribAllocatedBuffer OBJECT-TYPE
   SYNTAX BurstSize
   UNITS
              "Bytes"
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
      "The amount of buffer space required to hold
      the simultaneous burst of all reserved flows on
      the interface."
   ::= { intSrvIfAttribEntry 3 }
intSrvIfAttribFlows OBJECT-TYPE
   SYNTAX Gauge32
   MAX-ACCESS read-only
   STATUS
          current
   DESCRIPTION
      "The number of reserved flows currently active
      on this interface. A flow can be created ei-
      ther from a reservation protocol (such as RSVP
      or ST-II) or via configuration information."
   ::= { intSrvIfAttribEntry 4 }
```

```
intSrvIfAttribPropagationDelay OBJECT-TYPE
   SYNTAX Integer32
   UNITS
              "microseconds"
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The amount of propagation delay that this in-
      terface introduces in addition to that intro-
      diced by bit propagation delays."
  DEFVAL { 0 }-- by default, interfaces are presumed to add
              -- no extra delays
  ::= { intSrvIfAttribEntry 5 }
intSrvIfAttribStatus OBJECT-TYPE
   SYNTAX RowStatus
   MAX-ACCESS read-create
              current
   STATUS
   DESCRIPTION
      "'active' on interfaces that are configured for
   ::= { intSrvIfAttribEntry 6 }
   The Integrated Services Active Flows Database
   lists all flows active on an outgoing interface, including
   relevant attributes.
intSrvFlowTable OBJECT-TYPE
   SYNTAX SEQUENCE OF IntSrvFlowEntry
   MAX-ACCESS not-accessible
   STATUS
              current
   DESCRIPTION
      "Information describing the reserved flows us-
      ing the system's interfaces."
   ::= { intSrvObjects 2 }
intSrvFlowEntry OBJECT-TYPE
   SYNTAX IntSrvFlowEntry
   MAX-ACCESS not-accessible
   STATUS
           current
   DESCRIPTION
      "Information describing the use of a given in-
      terface by a given flow. The counter
      intSrvFlowPoliced starts counting at the in-
      stallation of the flow."
```

```
INDEX { intSrvFlowNumber }
  ::= { intSrvFlowTable 1 }
IntSrvFlowEntry ::=
   SEQUENCE {
       intSrvFlowNumber
                                      SessionNumber,
       intSrvFlowType
                                      SessionType,
       intSrvFlowOwner
                                      INTEGER,
       intSrvFlowDestAddr
                                     OCTET STRING,
       intSrvFlowSenderAddr
                                     OCTET STRING,
       intSrvFlowDestAddrLength
                                     INTEGER,
       intSrvFlowSenderAddrLength
                                     INTEGER,
       intSrvFlowProtocol
                                     Protocol,
       intSrvFlowDestPort
                                      Port,
       intSrvFlowPort
                                      Port,
       intSrvFlowFlowId
                                      INTEGER,
       intSrvFlowInterface
                                     InterfaceIndex,
       intSrvFlowIfAddr
                                     OCTET STRING,
       intSrvFlowRate
                                     BitRate,
       intSrvFlowBurst
                                     BurstSize,
       intSrvFlowWeight
                                     Integer32,
       intSrvFlowQueue
                                     Integer32,
                                     MessageSize,
       intSrvFlowMinTU
       intSrvFlowMaxTU
                                     MessageSize,
       intSrvFlowBestEffort
                                     Counter32,
       intSrvFlowPoliced
                                      Counter32,
       intSrvFlowDiscard
                                     TruthValue,
       intSrvFlowService
                                     QosService,
       intSrvFlowOrder
                                      INTEGER,
       intSrvFlowStatus
                                     RowStatus
   }
intSrvFlowNumber OBJECT-TYPE
   SYNTAX SessionNumber
   MAX-ACCESS not-accessible
   STATUS current
   DESCRIPTION
      "The number of this flow. This is for SNMP In-
      dexing purposes only and has no relation to any
      protocol value."
   ::= { intSrvFlowEntry 1 }
intSrvFlowType OBJECT-TYPE
   SYNTAX SessionType
   MAX-ACCESS read-create
```

```
STATUS current
   DESCRIPTION
      "The type of session (IP4, IP6, IP6 with flow
      information, etc)."
   ::= { intSrvFlowEntry 2 }
intSrvFlowOwner OBJECT-TYPE
   SYNTAX INTEGER {
                  other(1),
                   rsvp(2),
                   management(3)
               }
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The process that installed this flow in the
     queue policy database."
   ::= { intSrvFlowEntry 3 }
intSrvFlowDestAddr OBJECT-TYPE
   SYNTAX OCTET STRING (SIZE(4..16))
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The destination address used by all senders in
      this session. This object may not be changed
      when the value of the RowStatus object is 'ac-
      tive'."
   ::= { intSrvFlowEntry 4 }
intSrvFlowSenderAddr OBJECT-TYPE
   SYNTAX OCTET STRING (SIZE(4..16))
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The source address of the sender selected by
      this reservation. The value of all zeroes in-
      dicates 'all senders'. This object may not be
      changed when the value of the RowStatus object
      is 'active'."
   ::= { intSrvFlowEntry 5 }
intSrvFlowDestAddrLength OBJECT-TYPE
   SYNTAX INTEGER(0..128)
```

```
MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The length of the destination address in bits.
      This is the CIDR Prefix Length, which for IP4
      hosts and multicast addresses is 32 bits. This
      object may not be changed when the value of the
      RowStatus object is 'active'."
   ::= { intSrvFlowEntry 6 }
intSrvFlowSenderAddrLength OBJECT-TYPE
   SYNTAX INTEGER(0..128)
   MAX-ACCESS read-create
   STATUS
              current
   DESCRIPTION
      "The length of the sender's address in bits.
      This is the CIDR Prefix Length, which for IP4
      hosts and multicast addresses is 32 bits. This
      object may not be changed when the value of the
      RowStatus object is 'active'."
          ::= { intSrvFlowEntry 7 }
intSrvFlowProtocol OBJECT-TYPE
   SYNTAX Protocol
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The IP Protocol used by a session. This ob-
      ject may not be changed when the value of the
      RowStatus object is 'active'."
   ::= { intSrvFlowEntry 8 }
intSrvFlowDestPort OBJECT-TYPE
   SYNTAX Port
   MAX-ACCESS read-create
   STATUS
           current
   DESCRIPTION
      "The UDP or TCP port number used as a destina-
      tion port for all senders in this session. If
      the IP protocol in use, specified by
      intSrvResvFwdProtocol, is 50 (ESP) or 51 (AH),
      this represents a virtual destination port
      number. A value of zero indicates that the IP
      protocol in use does not have ports. This ob-
      ject may not be changed when the value of the
```

```
RowStatus object is 'active'."
  ::= { intSrvFlowEntry 9 }
intSrvFlowPort OBJECT-TYPE
   SYNTAX
              Port
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The UDP or TCP port number used as a source
      port for this sender in this session. If the
      IP protocol in use, specified by
      intSrvResvFwdProtocol is 50 (ESP) or 51 (AH),
      this represents a generalized port identifier
      (GPI). A value of zero indicates that the IP
      protocol in use does not have ports. This ob-
      ject may not be changed when the value of the
      RowStatus object is 'active'."
  ::= { intSrvFlowEntry 10 }
intSrvFlowFlowId OBJECT-TYPE
   SYNTAX INTEGER (0..16777215)
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
      "The flow ID that this sender is using, if
      this is an IPv6 session."
  ::= { intSrvFlowEntry 11 }
intSrvFlowInterface OBJECT-TYPE
   SYNTAX InterfaceIndex
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The ifIndex value of the interface on which
      this reservation exists."
  ::= { intSrvFlowEntry 12 }
intSrvFlowIfAddr OBJECT-TYPE
   SYNTAX OCTET STRING (SIZE(4..16))
   MAX-ACCESS read-create
   STATUS current
      "The IP Address on the if Entry on which this
      reservation exists. This is present primarily
```

```
to support those interfaces which layer multi-
      ple IP Addresses on the interface."
   ::= { intSrvFlowEntry 13 }
intSrvFlowRate OBJECT-TYPE
   SYNTAX BitRate
UNITS "bits per second"
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The Reserved Rate of the sender's data stream.
      If this is a Controlled Load service flow, this
      rate is derived from the Tspec rate parameter
      (r). If this is a Guaranteed service flow,
      this rate is derived from the Rspec clearing
      rate parameter (R)."
   ::= { intSrvFlowEntry 14 }
intSrvFlowBurst OBJECT-TYPE
   SYNTAX BurstSize
   UNITS "bytes"
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The size of the largest burst expected from
      the sender at a time.
      If this is less than the sender's advertised
      burst size, the receiver is asking the network
      to provide flow pacing beyond what would be
      provided under normal circumstances. Such pac-
      ing is at the network's option."
   ::= { intSrvFlowEntry 15 }
intSrvFlowWeight OBJECT-TYPE
   SYNTAX Integer32
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The weight used to prioritize the traffic.
      Note that the interpretation of this object is
      implementation-specific, as implementations
      vary in their use of weighting procedures."
   ::= { intSrvFlowEntry 16 }
```

```
intSrvFlowQueue OBJECT-TYPE
   SYNTAX Integer32
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The number of the queue used by this traffic.
      Note that the interpretation of this object is
      implementation-specific, as implementations
      vary in their use of queue identifiers."
   ::= { intSrvFlowEntry 17 }
intSrvFlowMinTU OBJECT-TYPE
   SYNTAX MessageSize
   MAX-ACCESS read-create
   STATUS
              current
   DESCRIPTION
      "The minimum message size for this flow. The
      policing algorithm will treat smaller messages
      as though they are this size."
   ::= { intSrvFlowEntry 18 }
intSrvFlowMaxTU OBJECT-TYPE
   SYNTAX MessageSize
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "The maximum datagram size for this flow that
      will conform to the traffic specification. This
      value cannot exceed the MTU of the interface."
   ::= { intSrvFlowEntry 19 }
intSrvFlowBestEffort OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
          current
   DESCRIPTION
      "The number of packets that were remanded to
      best effort service."
   ::= { intSrvFlowEntry 20 }
intSrvFlowPoliced OBJECT-TYPE
   SYNTAX Counter32
   MAX-ACCESS read-only
   STATUS
             current
```

```
DESCRIPTION
      "The number of packets policed since the incep-
      tion of the flow's service."
   ::= { intSrvFlowEntry 21 }
intSrvFlowDiscard OBJECT-TYPE
   SYNTAX
           TruthValue
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "If 'true', the flow is to incur loss when
      traffic is policed. If 'false', policed traff-
      ic is treated as best effort traffic."
  DEFVAL { false } -- traffic is, by default, treated as best
                   -- effort
   ::= { intSrvFlowEntry 22 }
intSrvFlowService OBJECT-TYPE
   SYNTAX QosService
   MAX-ACCESS read-only
   STATUS current
   DESCRIPTION
      "The QoS service being applied to this flow."
   ::= { intSrvFlowEntry 23 }
intSrvFlowOrder OBJECT-TYPE
   SYNTAX INTEGER (0..65535)
   MAX-ACCESS read-create
   STATUS
              current
   DESCRIPTION
      "In the event of ambiguity, the order in which
      the classifier should make its comparisons.
      The row with intSrvFlowOrder=0 is tried first,
      and comparisons proceed in the order of in-
      creasing value. Non-serial implementations of
      the classifier should emulate this behavior."
   ::= { intSrvFlowEntry 24 }
intSrvFlowStatus OBJECT-TYPE
   SYNTAX RowStatus
   MAX-ACCESS read-create
   STATUS current
   DESCRIPTION
      "'active' for all active flows. This object
```

[Page 16]

```
may be used to install static classifier infor-
          mation, delete classifier information, or au-
          thorize such."
       ::= { intSrvFlowEntry 25 }
   intSrvFlowNewIndex OBJECT-TYPE
       SYNTAX
               TestAndIncr
       MAX-ACCESS read-write
       STATUS current
       DESCRIPTION
          "This object is used to assign values to
          intSrvFlowNumber as described in 'Textual Con-
          ventions for SNMPv2'. The network manager
          reads the object, and then writes the value
          back in the SET that creates a new instance of
          intSrvFlowEntry. If the SET fails with the
          code 'inconsistentValue', then the process must
          be repeated; If the SET succeeds, then the ob-
          ject is incremented, and the new instance is
          created according to the manager's directions."
       ::= { intSrvGenObjects 1 }
-- conformance information
intSrvGroups      OBJECT IDENTIFIER ::= { intSrvConformance 1 }
intSrvCompliances OBJECT IDENTIFIER ::= { intSrvConformance 2 }
-- compliance statements
   intSrvCompliance MODULE-COMPLIANCE
       STATUS current
       DESCRIPTION
          "The compliance statement "
      MODULE -- this module
      MANDATORY-GROUPS { intSrvIfAttribGroup, intSrvFlowsGroup }
      OBJECT
                 intSrvFlowType
        MIN-ACCESS read-only
        DESCRIPTION
         "read-create access is not required. This may be
         read-only."
                intSrvFlowOwner
     OBJECT
       MIN-ACCESS read-only
```

DESCRIPTION

"read-create access is not required. This may be read-only."

intSrvFlowDestAddr

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

OBJECT intSrvFlowSenderAddr

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

OBJECT intSrvFlowDestAddrLength

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

intSrvFlowSenderAddrLength

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

OBJECT intSrvFlowProtocol

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

intSrvFlowDestPort OBJECT

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

OBJECT intSrvFlowPort

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

intSrvFlowFlowId MIN-ACCESS not-accessible

DESCRIPTION

"This object is needed only in a system that implements IPv6."

intSrvFlowInterface

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

OBJECT intSrvFlowRate

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

OBJECT intSrvFlowBurst

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

OBJECT intSrvFlowWeight

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

OBJECT intSrvFlowQueue

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

intSrvFlowMinTU OBJECT

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

OBJECT intSrvFlowMaxTU

MIN-ACCESS read-only

DESCRIPTION

"read-create access is not required. This may be read-only."

OBJECT intSrvFlowStatus

MIN-ACCESS read-only

```
DESCRIPTION
  "read-create access is not required. This may be
  read-only."
::= { intSrvCompliances 1 }
intSrvIfAttribGroup OBJECT-GROUP
    OBJECTS {
       intSrvIfAttribAllocatedBits, intSrvIfAttribMaxAllocatedBits,
        intSrvIfAttribAllocatedBuffer, intSrvIfAttribFlows,
       intSrvIfAttribPropagationDelay, intSrvIfAttribStatus
   STATUS current
   DESCRIPTION
       "These objects are required for Systems sup-
      porting the Integrated Services Architecture."
   ::= { intSrvGroups 1 }
intSrvFlowsGroup OBJECT-GROUP
     OBJECTS {
        \verb"intSrvFlowType", intSrvFlowOwner", intSrvFlowDestAddr",
        intSrvFlowSenderAddr, intSrvFlowDestAddrLength,
        intSrvFlowSenderAddrLength, intSrvFlowProtocol,
       intSrvFlowDestPort, intSrvFlowPort, intSrvFlowInterface,
       intSrvFlowBestEffort, intSrvFlowRate, intSrvFlowBurst,
       intSrvFlowWeight, intSrvFlowQueue, intSrvFlowMinTU,
       intSrvFlowDiscard, intSrvFlowPoliced, intSrvFlowService,
        intSrvFlowIfAddr, intSrvFlowOrder, intSrvFlowStatus
   STATUS current
   DESCRIPTION
       "These objects are required for Systems sup-
      porting the Integrated Services Architecture."
   ::= { intSrvGroups 2 }
```

4. Security Considerations

END

The use of an SNMP SET results in an RSVP or Integrated Services reservation under rules that are different compared to if the reservation was negotiated using RSVP. However, no other security considerations exist other than those imposed by SNMP itself.

5. Authors' Addresses

Fred Baker
Postal: Cisco Systems
519 Lado Drive

Santa Barbara, California 93111

Phone: +1 805 681 0115 EMail: fred@cisco.com

John Krawczyk

Postal: ArrowPoint Communications

235 Littleton Road

Westford, Massachusetts 01886

Phone: +1 508 692 5875 EMail: jjk@tiac.net

Arun Sastry
Postal: Cisco Systems

210 W. Tasman Drive

San Jose, California 95314

Phone: +1 408 526 7685 EMail: arun@cisco.com

6. Acknowledgements

This document was produced by the Integrated Services Working Group.

The authors would like to thank the following people for providing feedback on this document:

Lou Berger, Fore Systems Bob Braden, ISI Viswanatha Rao, Compaq John Wroclawski, MIT

7. References

- [1] Rose, M., Editor, "Management Information Base for Network Management of TCP/IP-based internets", STD 17, RFC 1213, May 1990.
- [2] Information processing systems Open Systems Interconnection - Specification of Abstract Syntax Notation One (ASN.1), International Organization for Standardization. International Standard 8824, (December,

1987).

[3] Information processing systems - Open Systems Interconnection - Specification of Basic Encoding Rules for Abstract Notation One (ASN.1), International Organization for Standardization. International Standard 8825, (December, 1987).